

Manuelles Installieren von SUSE Linux Enterprise Server für SAP-Anwendungen mit Agama

WAS?

In diesem Artikel wird beschrieben, wie Sie SUSE Linux Enterprise Server für SAP-Anwendungen mithilfe von Agama installieren. Die hier aufgeführten Informationen gelten für die Installation der Produkte sowohl auf Bare-Metal- als auch auf virtuellen Maschinen.

WARUM?

Lesen Sie diesen Artikel, um mehr über die Installation von SUSE Linux Enterprise Server für SAP-Anwendungen mit Agama zu erfahren.

AUFWAND

Sie benötigen etwa 15 Minuten, um diesen Artikel zu lesen.

ZIEL

Erfahren Sie, wie Sie SUSE Linux Enterprise Server für SAP-Anwendungen mithilfe von Agama manuell installieren.

ANFORDERUNGEN

Ein Bare-Metal-Server oder eine virtuelle Maschine. Für

- Serverinstallationen ohne Desktop-Umgebung empfiehlt SUSE mindestens 1 CPU, 2 GB Arbeitsspeicher und 32 GB Speicher (einschließlich Speicherplatz für Btrfs-Snapshots in der Root-Partition, Swap-Space und Speicher für Softwarepakete).

Ein aktiver Registrierungscode für das Produkt, das Sie

- installieren möchten. Sie können im SUSE Customer Center einen Registrierungscode für das Produkt generieren und das Abonnement für Ihr Unternehmen aktivieren.



Anmerkung: Optionale Registrierung

Bei bestimmten Bildern, die mit dem Schlüssel des Entwicklers signiert sind, können Sie die Registrierung vor oder während der Installation überspringen. Außerdem können bestimmte Images alle installierbaren Pakete für Ihr Betriebssystem enthalten, die Sie als Offline-Paket-Repository verwenden können. In solchen Fällen benötigen Sie vor der Installation möglicherweise keinen aktiven Registrierungscode. Wenn Sie jedoch Softwarepakete aus den offiziellen Online-Repositorys verwenden, empfiehlt SUSE, Ihr Produkt beim SUSE Customer Center zu registrieren.

Veröffentlicht: 11.12.2025

Inhalt

- 1 Einführung in Agama 4

- 2 Installieren von SUSE Linux Enterprise Server für SAP-Anwendungen mit Agama 4
- 3 Weitere Informationen 18
- 4 Rechtliche Hinweise 19
- A GNU Free Documentation License 19

1 Einführung in Agama

Dieser Abschnitt bietet einen kurzen Überblick über Agama, das Standardinstallationsprogramm für SUSE Linux Enterprise Server für SAP-Anwendungen 16.0 und spätere Versionen.

1.1 Was ist Agama?

Agama ist ein flexibles und leistungsstarkes Open Source-Installationsprogramm, das von SUSE entwickelt wurde. Sie können es verwenden, um unterstützte Versionen von SUSE Linux Enterprise Server für SAP-Anwendungen auf einer Vielzahl von Computerarchitekturen manuell oder automatisiert zu installieren. Die auf Agama basierende Installationsmethode bietet eine intuitive Oberfläche für *sofort einsatzbereite* Images für verschiedene Anwendungsfälle und Workloads. In Kombination mit Cockpit und Ansible ersetzt es YaST in SUSE Linux Enterprise Server für SAP-Anwendungen.

2 Installieren von SUSE Linux Enterprise Server für SAP-Anwendungen mit Agama

In diesem Abschnitt wird beschrieben, wie SUSE Linux Enterprise Server für SAP-Anwendungen mithilfe der auf Agama basierenden ISO-Image-Datei installiert wird.

2.1 Einführung

In den folgenden Abschnitten wird das auf Agama basierende manuelle Installationsverfahren für SUSE Linux Enterprise Server für SAP-Anwendungen beschrieben. Die Informationen gelten sowohl für die Installation auf Bare-Metal- als auch auf virtuellen Maschinen.

2.2 Anforderungen

- Eine auf Agama basierende ISO-Image-Datei für unterstützte Versionen von SUSE Linux Enterprise Server für SAP-Anwendungen. Sie können diese von SUSE Customer Center herunterladen und die Prüfsumme überprüfen, um die Integrität sicherzustellen.



Anmerkung: Verfügbare Images für Produkte

Das auf Agama basierende Installations-Image ist für SUSE Linux Enterprise Server für SAP-Anwendungen 16.0 und spätere Versionen verfügbar.

2.3 Manuelles Installieren von SUSE Linux Enterprise Server für SAP-Anwendungen für ppc64le mit Agama

Wenn Sie SUSE Linux Enterprise Server für SAP-Anwendungen mithilfe von Agama manuell installieren möchten, führen Sie die folgenden Schritte aus:

VORGEHEN 1: MANUELLE INSTALLATION VON SUSE LINUX ENTERPRISE SERVER MIT AGAMA

1. Kopieren Sie das ISO-Image auf den VIOS-Server:

```
> scpSLES-Online-16.0-ppc64le-Beta2.install.iso padmin@VIOS_SERVER
```

Ersetzen Sie VIOS_SERVER durch den Hostnamen oder die IP-Adresse Ihres VIOS-Servers.

2. Erstellen Sie ein virtuelles optisches Gerät und laden Sie die ISO-Datei in das virtuelle Gerät auf dem VIOS-Server:

```
(VIOS)$mkvopt -name sles16-offline -file SLES-Online-16.0-ppc64le-Beta2.install.iso  
-ro  
(VIOS)$loadopt -f -release -disk sles16-offline -vtd vcdXY
```

Ersetzen Sie vcdXY durch Ihre virtuelle Geräteeinheit, die an das LPAR angeschlossen ist, das Sie starten möchten.

3. Starten Sie das System vom angeschlossenen virtuellen Gerät aus. Wählen Sie *Boot-Optionen auswählen* > *Installations-/Bootgerät auswählen* > *CD/DVD* > *Alle Geräte auflisten* aus und wählen Sie das virtuelle optische Gerät aus, in dem Sie [Schritt 2](#) erstellt haben. Wählen Sie dann den *normalen Startmodus* und bestätigen Sie Ihre Auswahl.
4. Melden Sie sich bei der Konsole an, um das Root-Passwort und die IP-Adresse zu erhalten.
 - a. Wählen Sie *agama-Installer* aus und drücken Sie **Eingabetaste**, um das System zu starten.

```
zumbi@shifu: ~
GNU GRUB version 2.12
+-----+
| agama-installer |
| Check Installation Media -- agama-installer |
| local           |
| Other options...|
+-----+

Use the ^ and v keys to select which entry is highlighted.
Press enter to boot the selected OS, 'e' to edit the commands
before booting or 'c' for a command-line.
The highlighted entry will be executed automatically in 55s.

109 jostaberry-11 [PowerPC HMC]
```

- b. Wenn der Startvorgang abgeschlossen ist, werden die IP-Adresse und das Root-Passwort angezeigt.

```
zumbi@shifu: ~
[ OK ] Finished Permit User Sessions.
[ OK ] Started Agama Installer Service.
      Starting Agama's D-Bus bus monitor...
      Starting Agama Web Server...
[ OK ] Started Agama's D-Bus bus monitor.
      Starting Generate issue file for Agama SSL certificate...
[ OK ] Started Agama Web Server.
[ OK ] Started Agama automatic profile runner.
      Starting Postpone login prompt aft...L fingerprint issue is generated...
[ OK ] Finished Generate issue file for Agama SSL certificate.
[ OK ] Finished Postpone login prompt aft...SSL fingerprint issue is generated.
[ OK ] Started Getty on tty1.
[ OK ] Started Serial Getty on hvc0.
[ OK ] Reached target Login Prompts.
[ OK ] Reached target Multi-User System.
[ OK ] Reached target Graphical Interface.
      Starting X11 session...
      Starting Service enabling compressing RAM with zRam...
[ 39.519984][ T4578] zram: Added device: zram0
[ 39.523811][ T4571] zram0: detected capacity change from 0 to 133694080
[ OK ] Created slice User Slice of UID 0.
      Starting User Runtime Directory /run/user/0...
[ OK ] Finished User Runtime Directory /run/user/0.
      Starting User Manager for UID 0...
[ 39.609973][ T4588] Adding 66846976k swap on /dev/zram0. Priority:100 extents:1 across:66846976k SS
[ OK ] Finished Service enabling compressing RAM with zRam.
[ OK ] Started User Manager for UID 0.
[ OK ] Started Session 1 of User root.
[ OK ] Started X11 session.


Welcome to Agama installer version 11+105! (hvc0)

SSH host key fingerprints:
  SHA256:nUjAtYbVkiw6E9yC+gRKNHA0bUnueLZJ8iI3Ghmy8k (ECDSA)
  SHA256:qGExR9jnnCMh7WM0EV8dujDu26HiDID2Mk/5b0cL4g (ED25519)
  SHA256:zoEcwrsfa5gxHwhIiK0mlm664JWtW3kMT0iWkZkrb0k (RSA)


Connect to the Agama installer using these URLs:
  https://agama.local
  https://10.161.27.65
  https://192.168.0.42

Password for root user: eMyYKmhR
jostaberry-11 login:
109 jostaberry-11 [PowerPC HMC]
```

5. Öffnen Sie einen Webbrowser, der auf den angegebenen URL in der Konsole verweist. Geben Sie das root-Passwort ein und fahren Sie mit der Installation fort.
6. Wählen Sie SUSE Linux Enterprise Server für SAP-Anwendungen 16.0 für die Installation aus und akzeptieren Sie die Lizenz, um fortzufahren.




7. Die Übersicht der wichtigsten Installationseinstellungen wird angezeigt. Passen Sie die Einstellungen an, indem Sie die Kategorie aus dem Menü auf der linken Seite auswählen, oder fahren Sie direkt mit der Installation fort.



Tipp: Sprache und Tastatur des Installationsprogramms


Klicken Sie auf das Pfeilmenü in der oberen rechten Ecke und wählen Sie *Optionen des Installationsprogramms* aus, um die vom Installationsprogramm verwendete Sprache und das Tastaturlayout zu ändern. Die Sprache kann nur bei lokalen Installationen geändert werden. Wenn Sie einen Webbrowser für eine Ferninstallation verwenden, konfigurieren Sie die bevorzugte Inhaltssprache in den Browsereinstellungen und laden Sie das Installationsprogramm erneut.

8. Produktregistrierung: Geben Sie einen Registrierungscode und optional eine gültige E-Mail-Adresse ein.




Anmerkung: Optionale Registrierung für Images, die mit dem Schlüssel des Entwicklers signiert wurden

Bei Images, die mit dem Schlüssel des Entwicklers signiert wurden, können Sie die Registrierung vor der Installation überspringen. Wenn das Image Ihres Produkts die Installation ohne Registrierung unterstützt, wird möglicherweise ein Pop-up ähnlich dem Folgenden angezeigt:




Um die Installation ohne Registrierung durchzuführen, wählen Sie im Pop-up *Trust* (Vertrauen) aus.


9. (Optional) Passen Sie Ihre Lokalisierungseinstellungen wie Sprache, Tastaturlayout und Zeitzone an.



10. (Optional) Konfigurieren Sie Ihre Netzwerkeinstellungen. Wenn Sie eine bestehende Netzwerkverbindung bearbeiten möchten, klicken Sie auf die drei Punkte.



11. Wählen Sie ein Speichergerät für die Installation aus.



Derzeit werden Installationen auf einzelnen Datenträgern oder LVM unterstützt. Um den Datenträger zu wechseln oder LVM zu verwenden, klicken Sie im Abschnitt *Installationsgeräte* auf die Schaltfläche *Weitere Optionen* für den Gerätenamen.

Um eine iSCSI-Festplatte zu erkennen, wählen Sie den iSCSI-Initiator aus und klicken Sie auf *iSCSI-Ziele ermitteln*.

Standardmäßig werden die Dateisysteme als neue Partitionen auf dem ausgewählten Gerät zugewiesen. Sie können dieses Verhalten in der Dropdownliste mit der Bezeichnung *Alle Inhalte werden gelöscht* in Abschnitt *Installationsgeräte* ändern. Die folgenden Speicherrichtlinien stehen zur Verfügung:

SPEICHERRICHTLINIEN

Aktuellen Inhalt löschen

Alle Partitionen werden entfernt und alle Daten auf den Datenträgern gehen verloren.

Vorhandene Partitionen verkleinern

Die Daten bleiben erhalten, aber die aktuellen Partitionen werden nach Bedarf verkleinert.

Verfügbaren Speicherplatz nutzen


Die Daten bleiben erhalten. Es wird nur der Speicherplatz verwendet, der keiner Partition zugewiesen ist.

Benutzerdefiniert

Wählen Sie aus, was mit jeder Partition geschehen soll.

Um einzelne Partitionen zu bearbeiten, erweitern Sie den Abschnitt *Partitionen und Dateisysteme*, indem Sie auf > klicken. Optional können Sie Btrfs-Snapshots und Boot-Optionen konfigurieren und die vollständige Datenträgerverschlüsselung (FDE) aktivieren.

12. (*Optional*) Fügen Sie der Installation zusätzliche Software hinzu, z. B. den KVM-Hypervisor oder den Cockpit-Systemverwaltungsdienst.




13. Konfigurieren Sie die Authentifizierungseinstellungen.


! Wichtig: Kein SSH-Zugriff für root

Der SSH-Zugriff für root ist standardmäßig deaktiviert. Daher wird dringend empfohlen, einen Systembenutzer anzulegen. Der erste Systembenutzer erhält automatisch sudo-Rechte und kann auch für den Zugriff auf Cockpit verwendet werden.


- a. Erstellen Sie einen Nicht-root-Benutzer. Klicken Sie auf *Jetzt einen Benutzer definieren* und geben Sie Details wie Benutzername und Passwort ein.




- b. Konfigurieren Sie die Authentifizierungsmethoden für root. Sie können ein sicheres Passwort, einen öffentlichen SSH-Schlüssel oder beides verwenden.



14. Klicken Sie auf *Installieren* und bestätigen Sie, um die Installation zu starten.



15. Warten Sie, bis die Systeminstallation abgeschlossen ist. Es dauert etwa 30 Minuten, bis die Installation abgeschlossen ist.






Tipp: Installationsprotokolle

Sie können das Pfeilmenü in der oberen rechten Ecke des Fensters verwenden, um die Protokolle und Systemmeldungen anzuzeigen.

16. Sobald die Installation abgeschlossen ist, wählen Sie *Neu starten*.



2.4 Zusammenfassung

Stellen Sie nach erfolgreichen Konfigurationsprüfungen, einer erfolgreichen Produktregistrierung sowie Installation und Neustart sicher, dass Sie sich anmelden und Ihr System verwenden können.

VORGEHEN 2: ÜBERPRÜFUNG DES SYSTEMS NACH DER INSTALLATION

1. Melden Sie sich beim System als root-Benutzer an.

```
Welcome to SUSE Linux Enterprise Server 16.0 Alpha3 (x86_64) - Kernel 6.4.0-sifo.1.8-default (tty1).

SSH host key: SHA256:bUpdqEfAYuoIgbMY0s70qIdMEHHC/eKikm7cL3kwCMA (RSA)
SSH host key: SHA256:L5PQdXeaN9edpLw0z29LWxCNKe26EWWWtNFopxMgn3U (ECDSA)
SSH host key: SHA256:CKA9BVCHu5jKhECTUSyBGQRyDQQMReyIfUIOR/nDsXY (ED25519)
enp1s0: 192.168.122.40 fe80::a486:c31a:e64:6c0c

Hint: Num Lock on

localhost login: root
Password: _
```

2. Führen Sie einige grundlegende Kommandos aus, um zu überprüfen, ob Ihr System wie erwartet funktioniert.

```
Welcome to SUSE Linux Enterprise Server 16.0 Alpha3 (x86_64) - Kernel 6.4.0-sifo.1.8-default (tty1).

SSH host key: SHA256:bUpdqEfAYuoIgbMY0s70qIdMEHHC/eKikm7cL3kwCMA (RSA)
SSH host key: SHA256:L5PQdXeaN9edpLw0z29LWxCNKe26EWWWtNFopxMgn3U (ECDSA)
SSH host key: SHA256:CKA9BVCHu5jKhECTUSyBGQRyDQQMReyIfUIOR/nDsXY (ED25519)
enp1s0: 192.168.122.40 fe80::a486:c31a:e64:6c0c

Hint: Num Lock on

localhost login: root
Password:
Have a lot of fun...
localhost:~ # whoami
root
localhost:~ # pwd
/root
localhost:~ #
```

3 Weitere Informationen

Informationen zu verwandten Themen finden Sie in den folgenden Ressourcen:

- Dokumentation des Agama Open Source-Projekts: <https://agama-project.github.io/docs>
- IBM Schnellstartanleitungen für die Installation von Linux auf POWER: <https://www.ibm.com/docs/en/linux-on-systems?topic=servers-quick-start-guides-installing-linux>.
- Anweisungen von IBM zur Installation von Linux auf PowerVM LPAR mithilfe einer virtuellen DVD (vDVD): <https://www.ibm.com/docs/en/linux-on-systems?topic=aim-installing-linux-powervm-lpar-by-using-virtual-dvd-vdvd>

4 Rechtliche Hinweise

Copyright © 2006–2025 , SUSE LLC und Mitwirkende. Alle Rechte vorbehalten.

Es wird die Genehmigung erteilt, dieses Dokument unter den Bedingungen der GNU Free Documentation License, Version 1.2 oder (optional) Version 1.3 zu vervielfältigen, zu verbreiten und/oder zu verändern; die unveränderlichen Abschnitte hierbei sind der Urheberrechtshinweis und die Lizenzbedingungen. Eine Kopie dieser Lizenz (Version 1.2) finden Sie in Abschnitt „GNU Free Documentation License“.

Die SUSE Marken finden Sie in <https://www.suse.com/company/legal/>. Alle anderen Marken von Drittanbietern sind Besitz ihrer jeweiligen Eigentümer. Markensymbole (®, ™ usw.) kennzeichnen Marken von SUSE und ihren Tochtergesellschaften. Sternchen (*) kennzeichnen Marken von Drittanbietern.

Alle Informationen in diesem Buch wurden mit größter Sorgfalt zusammengestellt. Auch hierdurch kann jedoch keine hundertprozentige Richtigkeit gewährleistet werden. Weder SUSE LLC noch ihre Tochtergesellschaften noch die Autoren noch die Übersetzer können für mögliche Fehler und deren Folgen haftbar gemacht werden.

A GNU Free Documentation License

Copyright (C) 2000, 2001, 2002 Free Software Foundation, Inc. 51 Franklin St, Fifth Floor, Boston, MA 02110-1301 USA. Everyone is permitted to copy and distribute verbatim copies of this license document, but changing it is not allowed.

0. PREAMBLE

The purpose of this License is to make a manual, textbook, or other functional and useful document "free" in the sense of freedom: to assure everyone the effective freedom to copy and redistribute it, with or without modifying it, either commercially or non-commercially. Secondly, this License preserves for the author and publisher a way to get credit for their work, while not being considered responsible for modifications made by others.

This License is a kind of "copyleft", which means that derivative works of the document must themselves be free in the same sense. It complements the GNU General Public License, which is a copyleft license designed for free software.

We have designed this License to use it for manuals for free software, because free software needs free documentation: a free program should come with manuals providing the same freedoms that the software does. But this License is not limited to software manuals; it can be used for any textual work, regardless of subject matter or whether it is published as a printed book. We recommend this License principally for works whose purpose is instruction or reference.

1. APPLICABILITY AND DEFINITIONS

This License applies to any manual or other work, in any medium, that contains a notice placed by the copyright holder saying it can be distributed under the terms of this License. Such a notice grants a world-wide, royalty-free license, unlimited in duration, to use that work under the conditions stated herein. The "Document", below, refers to any such manual or work. Any member of the public is a licensee, and is addressed as "you". You accept the license if you copy, modify or distribute the work in a way requiring permission under copyright law.

A "Modified Version" of the Document means any work containing the Document or a portion of it, either copied verbatim, or with modifications and/or translated into another language.

A "Secondary Section" is a named appendix or a front-matter section of the Document that deals exclusively with the relationship of the publishers or authors of the Document to the Document's overall subject (or to related matters) and contains nothing that could fall directly within that overall subject. (Thus, if the Document is in part a textbook of mathematics, a Secondary Section may not explain any mathematics.) The relationship could be a matter of historical connection with the subject or with related matters, or of legal, commercial, philosophical, ethical or political position regarding them.

The "Invariant Sections" are certain Secondary Sections whose titles are designated, as being those of Invariant Sections, in the notice that says that the Document is released under this License. If a section does not fit the above definition of Secondary then it is not allowed to be designated as Invariant. The Document may contain zero Invariant Sections. If the Document does not identify any Invariant Sections then there are none.

The "Cover Texts" are certain short passages of text that are listed, as Front-Cover Texts or Back-Cover Texts, in the notice that says that the Document is released under this License. A Front-Cover Text may be at most 5 words, and a Back-Cover Text may be at most 25 words.

A "Transparent" copy of the Document means a machine-readable copy, represented in a format whose specification is available to the general public, that is suitable for revising the document straightforwardly with generic text editors or (for images composed of pixels) generic paint programs or (for drawings) some widely available drawing editor, and that is suitable for input

to text formatters or for automatic translation to a variety of formats suitable for input to text formatters. A copy made in an otherwise Transparent file format whose markup, or absence of markup, has been arranged to thwart or discourage subsequent modification by readers is not Transparent. An image format is not Transparent if used for any substantial amount of text. A copy that is not "Transparent" is called "Opaque".

Examples of suitable formats for Transparent copies include plain ASCII without markup, Texinfo input format, LaTeX input format, SGML or XML using a publicly available DTD, and standard-conforming simple HTML, PostScript or PDF designed for human modification. Examples of transparent image formats include PNG, XCF and JPG. Opaque formats include proprietary formats that can be read and edited only by proprietary word processors, SGML or XML for which the DTD and/or processing tools are not generally available, and the machine-generated HTML, PostScript or PDF produced by some word processors for output purposes only.

The "Title Page" means, for a printed book, the title page itself, plus such following pages as are needed to hold, legibly, the material this License requires to appear in the title page. For works in formats which do not have any title page as such, "Title Page" means the text near the most prominent appearance of the work's title, preceding the beginning of the body of the text.

A section "Entitled XYZ" means a named subunit of the Document whose title either is precisely XYZ or contains XYZ in parentheses following text that translates XYZ in another language. (Here XYZ stands for a specific section name mentioned below, such as "Acknowledgements", "Dedications", "Endorsements", or "History".) To "Preserve the Title" of such a section when you modify the Document means that it remains a section "Entitled XYZ" according to this definition.

The Document may include Warranty Disclaimers next to the notice which states that this License applies to the Document. These Warranty Disclaimers are considered to be included by reference in this License, but only as regards disclaiming warranties: any other implication that these Warranty Disclaimers may have is void and has no effect on the meaning of this License.

2. VERBATIM COPYING

You may copy and distribute the Document in any medium, either commercially or non-commercially, provided that this License, the copyright notices, and the license notice saying this License applies to the Document are reproduced in all copies, and that you add no other conditions whatsoever to those of this License. You may not use technical measures to obstruct or control the reading or further copying of the copies you make or distribute. However, you may accept compensation in exchange for copies. If you distribute a large enough number of copies you must also follow the conditions in section 3.

You may also lend copies, under the same conditions stated above, and you may publicly display copies.

3. COPYING IN QUANTITY

If you publish printed copies (or copies in media that commonly have printed covers) of the Document, numbering more than 100, and the Document's license notice requires Cover Texts, you must enclose the copies in covers that carry, clearly and legibly, all these Cover Texts: Front-Cover Texts on the front cover, and Back-Cover Texts on the back cover. Both covers must also clearly and legibly identify you as the publisher of these copies. The front cover must present the full title with all words of the title equally prominent and visible. You may add other material on the covers in addition. Copying with changes limited to the covers, as long as they preserve the title of the Document and satisfy these conditions, can be treated as verbatim copying in other respects.

If the required texts for either cover are too voluminous to fit legibly, you should put the first ones listed (as many as fit reasonably) on the actual cover, and continue the rest onto adjacent pages.

If you publish or distribute Opaque copies of the Document numbering more than 100, you must either include a machine-readable Transparent copy along with each Opaque copy, or state in or with each Opaque copy a computer-network location from which the general network-using public has access to download using public-standard network protocols a complete Transparent copy of the Document, free of added material. If you use the latter option, you must take reasonably prudent steps, when you begin distribution of Opaque copies in quantity, to ensure that this Transparent copy will remain thus accessible at the stated location until at least one year after the last time you distribute an Opaque copy (directly or through your agents or retailers) of that edition to the public.

It is requested, but not required, that you contact the authors of the Document well before redistributing any large number of copies, to give them a chance to provide you with an updated version of the Document.

4. MODIFICATIONS

You may copy and distribute a Modified Version of the Document under the conditions of sections 2 and 3 above, provided that you release the Modified Version under precisely this License, with the Modified Version filling the role of the Document, thus licensing distribution and modification of the Modified Version to whoever possesses a copy of it. In addition, you must do these things in the Modified Version:

- A. Use in the Title Page (and on the covers, if any) a title distinct from that of the Document, and from those of previous versions (which should, if there were any, be listed in the History section of the Document). You may use the same title as a previous version if the original publisher of that version gives permission.
- B. List on the Title Page, as authors, one or more persons or entities responsible for authorship of the modifications in the Modified Version, together with at least five of the principal authors of the Document (all of its principal authors, if it has fewer than five), unless they release you from this requirement.
- C. State on the Title page the name of the publisher of the Modified Version, as the publisher.
- D. Preserve all the copyright notices of the Document.
- E. Add an appropriate copyright notice for your modifications adjacent to the other copyright notices.
- F. Include, immediately after the copyright notices, a license notice giving the public permission to use the Modified Version under the terms of this License, in the form shown in the Addendum below.
- G. Preserve in that license notice the full lists of Invariant Sections and required Cover Texts given in the Document's license notice.
- H. Include an unaltered copy of this License.
- I. Preserve the section Entitled "History", Preserve its Title, and add to it an item stating at least the title, year, new authors, and publisher of the Modified Version as given on the Title Page. If there is no section Entitled "History" in the Document, create one stating the title, year, authors, and publisher of the Document as given on its Title Page, then add an item describing the Modified Version as stated in the previous sentence.

- J. Preserve the network location, if any, given in the Document for public access to a Transparent copy of the Document, and likewise the network locations given in the Document for previous versions it was based on. These may be placed in the "History" section. You may omit a network location for a work that was published at least four years before the Document itself, or if the original publisher of the version it refers to gives permission.
- K. For any section Entitled "Acknowledgements" or "Dedications", Preserve the Title of the section, and preserve in the section all the substance and tone of each of the contributor acknowledgements and/or dedications given therein.
- L. Preserve all the Invariant Sections of the Document, unaltered in their text and in their titles. Section numbers or the equivalent are not considered part of the section titles.
- M. Delete any section Entitled "Endorsements". Such a section may not be included in the Modified Version.
- N. Do not retitle any existing section to be Entitled "Endorsements" or to conflict in title with any Invariant Section.
- O. Preserve any Warranty Disclaimers.

If the Modified Version includes new front-matter sections or appendices that qualify as Secondary Sections and contain no material copied from the Document, you may at your option designate some or all of these sections as invariant. To do this, add their titles to the list of Invariant Sections in the Modified Version's license notice. These titles must be distinct from any other section titles.

You may add a section Entitled "Endorsements", provided it contains nothing but endorsements of your Modified Version by various parties--for example, statements of peer review or that the text has been approved by an organization as the authoritative definition of a standard.

You may add a passage of up to five words as a Front-Cover Text, and a passage of up to 25 words as a Back-Cover Text, to the end of the list of Cover Texts in the Modified Version. Only one passage of Front-Cover Text and one of Back-Cover Text may be added by (or through arrangements made by) any one entity. If the Document already includes a cover text for the same cover, previously added by you or by arrangement made by the same entity you are acting on behalf of, you may not add another; but you may replace the old one, on explicit permission from the previous publisher that added the old one.

The author(s) and publisher(s) of the Document do not by this License give permission to use their names for publicity for or to assert or imply endorsement of any Modified Version.

5. COMBINING DOCUMENTS

You may combine the Document with other documents released under this License, under the terms defined in section 4 above for modified versions, provided that you include in the combination all of the Invariant Sections of all of the original documents, unmodified, and list them all as Invariant Sections of your combined work in its license notice, and that you preserve all their Warranty Disclaimers.

The combined work need only contain one copy of this License, and multiple identical Invariant Sections may be replaced with a single copy. If there are multiple Invariant Sections with the same name but different contents, make the title of each such section unique by adding at the end of it, in parentheses, the name of the original author or publisher of that section if known, or else a unique number. Make the same adjustment to the section titles in the list of Invariant Sections in the license notice of the combined work.

In the combination, you must combine any sections Entitled "History" in the various original documents, forming one section Entitled "History"; likewise combine any sections Entitled "Acknowledgements", and any sections Entitled "Dedications". You must delete all sections Entitled "Endorsements".

6. COLLECTIONS OF DOCUMENTS

You may make a collection consisting of the Document and other documents released under this License, and replace the individual copies of this License in the various documents with a single copy that is included in the collection, provided that you follow the rules of this License for verbatim copying of each of the documents in all other respects.

You may extract a single document from such a collection, and distribute it individually under this License, provided you insert a copy of this License into the extracted document, and follow this License in all other respects regarding verbatim copying of that document.

7. AGGREGATION WITH INDEPENDENT WORKS

A compilation of the Document or its derivatives with other separate and independent documents or works, in or on a volume of a storage or distribution medium, is called an "aggregate" if the copyright resulting from the compilation is not used to limit the legal rights of the compilation's users beyond what the individual works permit. When the Document is included in an aggregate, this License does not apply to the other works in the aggregate which are not themselves derivative works of the Document.

If the Cover Text requirement of section 3 is applicable to these copies of the Document, then if the Document is less than one half of the entire aggregate, the Document's Cover Texts may be placed on covers that bracket the Document within the aggregate, or the electronic equivalent of covers if the Document is in electronic form. Otherwise they must appear on printed covers that bracket the whole aggregate.

8. TRANSLATION

Translation is considered a kind of modification, so you may distribute translations of the Document under the terms of section 4. Replacing Invariant Sections with translations requires special permission from their copyright holders, but you may include translations of some or all Invariant Sections in addition to the original versions of these Invariant Sections. You may include a translation of this License, and all the license notices in the Document, and any Warranty Disclaimers, provided that you also include the original English version of this License and the original versions of those notices and disclaimers. In case of a disagreement between the translation and the original version of this License or a notice or disclaimer, the original version will prevail. If a section in the Document is Entitled "Acknowledgements", "Dedications", or "History", the requirement (section 4) to Preserve its Title (section 1) will typically require changing the actual title.

9. TERMINATION

You may not copy, modify, sublicense, or distribute the Document except as expressly provided for under this License. Any other attempt to copy, modify, sublicense or distribute the Document is void, and will automatically terminate your rights under this License. However, parties who have received copies, or rights, from you under this License will not have their licenses terminated so long as such parties remain in full compliance.

10. FUTURE REVISIONS OF THIS LICENSE

The Free Software Foundation may publish new, revised versions of the GNU Free Documentation License from time to time. Such new versions will be similar in spirit to the present version, but may differ in detail to address new problems or concerns. See <https://www.gnu.org/copyleft/>.

Each version of the License is given a distinguishing version number. If the Document specifies that a particular numbered version of this License "or any later version" applies to it, you have the option of following the terms and conditions either of that specified version or of any later version that has been published (not as a draft) by the Free Software Foundation. If the Document does not specify a version number of this License, you may choose any version ever published (not as a draft) by the Free Software Foundation.

ADDENDUM: How to use this License for your documents

```
Copyright (c) YEAR YOUR NAME.  
Permission is granted to copy, distribute and/or modify this document  
under the terms of the GNU Free Documentation License, Version 1.2  
or any later version published by the Free Software Foundation;  
with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts.  
A copy of the license is included in the section entitled "GNU  
Free Documentation License".
```

If you have Invariant Sections, Front-Cover Texts and Back-Cover Texts, replace the “with...Texts.” line with this:

```
with the Invariant Sections being LIST THEIR TITLES, with the  
Front-Cover Texts being LIST, and with the Back-Cover Texts being LIST.
```

If you have Invariant Sections without Cover Texts, or some other combination of the three, merge those two alternatives to suit the situation.

If your document contains nontrivial examples of program code, we recommend releasing these examples in parallel under your choice of free software license, such as the GNU General Public License, to permit their use in free software.