

# Installing SUSE Linux Enterprise Server Manually Using Agama On IBM Z

## WHAT?

This article describes how to install SUSE Linux Enterprise Server using Agama. The information presented here applies to installation of the products on both bare metal and virtual machines.

## WHY?

Read this article to understand the process of installing SUSE Linux Enterprise Server using Agama.

## EFFORT

You may need 15 minutes to read this article.

## GOAL

Learn how to manually install SUSE Linux Enterprise Server using Agama.

## REQUIREMENTS

- A bare metal server or a virtual machine. For server installations without any desktop environment, SUSE recommends a minimum of 1 CPU, 2 GB memory and 32 GB storage (which includes storage for Btrfs snapshots in the root partition, swap space, and storage for software packages).

An active registration code for the product you want to install.

- You can generate a registration code for the product and activate its subscription for your organization at the SUSE Customer Center.



### Note: Optional registration

Certain images that are signed with the developer's key may allow you to skip registration before or while installation. Besides, certain images may contain all installable packages for your operating system that you can use as an offline package repository. In such cases, you may not need an active registration code before installation. However, if you use software packages from the official online repositories, SUSE recommends registering your product with the SUSE Customer Center.

Publication Date: 27 Nov 2025

## Contents

- 1 Introduction to Agama 4
- 2 Installing SUSE Linux Enterprise Server using Agama 4

- 3 For more information **18**
- 4 Legal Notice **18**
- A GNU Free Documentation License **19**

# 1 Introduction to Agama

This section provides a short overview of Agama, which is the default installer for SUSE Linux Enterprise Server 16.0 and later versions.

## 1.1 What is Agama?

Agama is a flexible and powerful open source installer developed by SUSE. You can use it to perform manual or automated installation of supported SUSE Linux Enterprise Server versions on a variety of machine architectures. The Agama-based installation method provides an intuitive interface for *ready-to-use* images for different use cases and workloads. In combination with Cockpit and Ansible, it substitutes YaST in SUSE Linux Enterprise Server.

# 2 Installing SUSE Linux Enterprise Server using Agama

This section describes how to install SUSE Linux Enterprise Server using the Agama-based ISO image file.

## 2.1 Introduction

The following sections describe the Agama-based manual installation procedure for SUSE Linux Enterprise Server. The information applies to installation on both bare metal and virtual machines.

## 2.2 Requirements

- An Agama-based ISO image file for supported versions of SUSE Linux Enterprise Server. You can download it from the SUSE Customer Center and verify its checksum to ensure its integrity.



## Note: Available images for products

The Agama-based installation image is available for SUSE Linux Enterprise Server 16.0 and later versions.

## 2.3 Manually installing SUSE Linux Enterprise Server for s390x using Agama

To manually install SUSE Linux Enterprise Server using Agama, perform the following steps:

### PROCEDURE 1: MANUAL INSTALLATION OF SUSE LINUX ENTERPRISE USING AGAMA

1. Download [SLES-Online-16.0-s390x-Beta4.install.iso](#) and mount it:

```
> sudo mkdir -p /srv/ftp/agama
> sudo mount -o loop SLES-Online-16.0-s390x-Beta4.install.iso /srv/ftp/agama
```

2. *(Optional)* For installation in an air-gapped environment or without registration, download [SLES-16.0-Full-s390x-Beta4.install.iso](#) and mount it.

```
> sudo mkdir -p /srv/ftp/agama-offline
> sudo mount -o loop SLES-16.0-Full-s390x-Beta4.install.iso /srv/ftp/agama-offline
```

3. Use the following parmfile to start the installation:

#### EXAMPLE 1: EXAMPLE PARMFILE

```
cio_ignore=all,!condev,!0.0.0160 ❶
rd.zdev=dasd,0.0.0160 ❷
rd.zdev=qeth,0.0.0800:0.0.0801:0.0.0802,layer2=1,portno=0 ❸
ip=192.168.3.100 ❹::192.168.3.254:24 ❺::enc800:none
ip=192.168.3.100::192.168.3.254:24:SLE16-Beta2:enc800:none
hostname=jupiter ❻ nameserver=192.168.1.116 ❼
root=live:ftp://192.168.3.105/agama/LiveOS/squashfs.img ❽
live.password=linux ❾
```

- ❶ Only expose the devices that the machine should be aware of
- ❷ Activation of a DASD device
- ❸ Activation of a qeth device

- ④ IP configuration. The different parameters are separated by colons (:). You can omit unneeded parameters by leaving them out, meaning you get two or more subsequent colons. For a complete configuration reference, refer to [man 7 dracut.cmdline](#). If no IP configuration is specified, it will be assigned with DHCP and the IP address will be displayed on the console after boot.



### Important: Multiple network interfaces

If your system has more than one network interface, IP configurations may be swapped after the installation, leaving the system unreachable.

To prevent this from happening, either bind each IP configuration to a particular interface by interface name or MAC address. If you use a MAC address, make sure to format it as 00-11-22-33-44-55 instead of 00:11:22:33:44:55



### Tip

As the console is hard to read on x3270, configuring the network in the parm-file is recommended.

- ⑤ IP address of the gateway for the system
- ⑥ Host name of the system. You can also set the host name in the `ip` parameter, however it is transient whereas `hostname` gets written to `/etc/hostname`.
- ⑦ IP address of the DNS server for the system
- ⑧ URI of the installer ISO mounted in [Step 1](#). For installation in an LPAR, use the ISO file directly as in:

```
root=live:ftp://192.168.3.105/agama/SLES-Online-16.0-s390x-Beta4.install.iso
```

- ⑨ Password for the system administrator `root`. If you do not set a password, a random password will be generated and displayed on the console after boot. As the console is hard to read on x3270, setting a `root` password in the parmfile is recommended.

Adjust your parmfile accordingly:

- For installation in an air-gapped environment or without registration, add the `agama.install_url` to the parmfile to install from SLES-16.0-Full-s390x-Beta4.install.iso mounted in [Step 2](#):

```
agama.install_url=ftp://192.168.3.105/agama-offline/install
```

- If you are using a VLAN, add the `vlan` parameter. Make sure to specify the virtual device instead of the underlying physical device.

```
ip=192.168.3.100::192.168.3.254:24::enc800.2174:none  
hostname=jupiter nameserver=192.168.1.116 vlan=enc800.2174:enc800
```



### Tip: `ifcfg` vs `ip` syntax

Earlier versions of SUSE Linux Enterprise used **linuxrc** using the interface configuration (`ifcfg`) files, whereas SUSE Linux Enterprise 16 uses **dracut** with `ip` syntax for NetworkManager. While Agama supports translating some options, it is recommended to use the new and more powerful syntax.

TABLE 1: `ifcfg` VS `ip`

<code>ifcfg</code>	<code>dracut</code>
<code>ifcfg = * = dhcp</code>	<code>ip = dhcp</code>
<code>ifcfg = eth0 = dhcp</code>	<code>ip = eth0:dhcp</code>
<code>ifcfg = eth0.10 = 192.168.0.100/24,192.168.0.1 eth0.10:eth0</code>	<code>ip = 192.168.0.100::192.168.0.1:24::eth0.10</code>
<code>ifcfg = "eth0 = 192.168.0.33/24 10.0.0.100/24,192.168.0.1,192.168.0.1 10.0.0.1,example.com"</code>	<code>ip = 192.168.0.33::192.168.0.1:24::eth0 nameserver = 192.168.0.1 nameserv- er = 10.0.0.1 ip = 10.0.0.100::24::eth0</code>

For a complete list of **dracut** options, refer to [man 7 dracut.cmdline](#).




## Note: DASD alias devices

DASD alias devices are special in that they appear not operational until at least one associated DASD base device has been enabled. As a result, the Agama installer cannot determine their actual type (ECKD or FBA DASD).


As a workaround, specify `dasd-eckd` as device type. This should provide `chzdev` with enough information to create `udev` rules for enabling these devices even in the absence of a working device. When the the base device is enabled later and the alias devices become operational, they will be automatically set online.

4. Open a web browser pointing to the given IP address from the parmfile. Enter the root password and proceed with the installation.
5. Select SUSE Linux Enterprise Server 16.0 for installation and accept the license to continue.



6. The overview with the most relevant installation settings is shown. Adjust the settings by selecting the category from the menu on the left or directly proceed with the installation.





### Tip: Installer language and keyboard

Click the arrow menu in the top right corner and select *Installer options* to change the language and keyboard layout used by the installer. The language can only be changed on local installations. If you are using a web browser for a remote installation, configure the preferred content language in the browser settings and reload the installer.

7. Register your product. Enter a registration code and optionally a valid email address.

SUSE Linux Enterprise Server 16.0

English us Install

Overview

Hostname

Registration

Localization

Network

Storage

Software

Authentication

### Registration

⚠ SUSE Linux Enterprise Server 16.0 must be registered.

🔔 The product will be registered with "agama" hostname  
You cannot change it later. Go to the [hostname](#) section if you want to modify it before proceeding with registration.

Registration server

SUSE Customer Center (SCC)

Registration code

Using US keyboard

☐ Provide email address

Register



## Note: Optional registration for images signed with the developer's key


Images signed with the developer's key may allow you to skip registration before installation. If your product's image supports installation without registration, you may see a pop-up similar to the following:

The key F7B14C08AE4D69BA (home:adrianSuSE OBS Project  
<home:adrianSuSE@build.suse.de>) with fingerprint D788 D957 AF06 F219 7863 0FD6  
F7B1 4C08 AE4D 69BA is unknown. Do you want to trust this key?


Trust Skip

To install without registration, select *Trust* on the pop-up.


8. (Optional) Adjust your localization settings such as language, keyboard layout and time zone.



9. (Optional) Configure your network settings. To edit an existing network connection, click the three dots.



## 10. Select a storage device for installation.



Currently installations on single discs or LVM are supported. To change the disk or use LVM, click the device name *More devices* button in the *Installation devices* section.

To use DASD, iSCSI or zFCP devices, you need configure them first. Click *Other options* and select the desired technology. The DASD and zFCP options are only available if the corresponding devices are attached.

To activate a DASD disk, select it from the list and click *Perform an action* > *Activate*. Once the disk is activated, you can select it for installation in the previous screen.

To activate a zFCP disk, select it from the list and activate it by clicking on the three-dot menu. If the activation status is not displayed correctly, press **F5** to refresh the installer interface.

To detect an iSCSI disk, select the iSCSI initiator and click *Discover iSCSI targets*.

By default, the file systems will be allocated as new partitions on the selected device. You can change this behavior in the drop-down list labeled *All content will be deleted* drop-down list in the *Installation devices* section. The following space policies are available:

### SPACE POLICIES

#### Delete current content

All partitions will be removed and any data on the disks will be lost.

### Shrink existing partitions

The data is kept, but current partitions will be shrunk as needed.

### Use available space


The data is kept. Only the space not assigned to any partition will be used.

### Custom

Select what to do with each partition.

To edit individual partitions, expand the *Partitions and file systems* section by clicking on the > Optionally, you can configure Btrfs snapshots, boot options and enable full disk encryption (FDE).

11. (Optional) Add additional software to install such as the KVM hypervisor or Cockpit system management service.



### Note: Trust the GPG key for the Package Hub repository


If you select the Package Hub add-on and see a popup, trust the GPG key for that repository.

## 12. Configure the authentication settings.


### ! Important: No SSH root access

SSH access for root is disabled by default. Therefore it is strongly recommended to create a system user. The first system user is granted sudo privileges automatically and can also be used for accessing Cockpit.


- a. Create a non-root user. Click *Define a user now* and enter details such as user name and password.




- b. Configure the authentication methods for the root. You can use a secure password, a SSH public key, or both.



13. Click *Install* and confirm to start the installation.



14. Wait for the system installation to complete. The time of the installation depends on the system's performance, the installation size and your network connection speed.




### Tip: Installation logs

You can use the arrow menu in the top right corner of the window to view the logs and system messages.

15. Once the installation is complete, select *Reboot*.





## 2.4 Summary

After successful configuration checks, product registration, installation and reboot, verify that you can log in and use your system.

### PROCEDURE 2: VERIFYING THE SYSTEM AFTER INSTALLATION

1. Log in to the system as root.

```
Welcome to SUSE Linux Enterprise Server 16.0 Alpha3 (x86_64) - Kernel 6.4.0-sifo.1.8-default (tty1).
SSH host key: SHA256:bUpdqEfAYuo1gbMY0s70qIdMEHHC/eKikm7cL3kwCMA (RSA)
SSH host key: SHA256:L5PQdXeaN9edpLw0z29LWxCNKe26EWWWtNFopxMgn3U (ECDSA)
SSH host key: SHA256:CKA9BVCHu5.jKhECTUSyBGQRyOQQMRyIfUIOR/nDsXY (ED25519)
enp1s0: 192.168.122.40 fe80::a486:c31a:e64:6c0c

Hint: Num Lock on

localhost login: root
Password: _
```

2. To verify that your system is working as expected, run a few basic commands.

```
Welcome to SUSE Linux Enterprise Server 16.0 Alpha3 (x86_64) - Kernel 6.4.0-sifo.1.8-default (tty1).


SSH host key: SHA256:bUpdqEfAYuo1gbMY0s70qIdMEHHC/eKikn7cL3kwCMA (RSA)
SSH host key: SHA256:L5PQdXeaN9edpLw0z29LWxCNKe26EWWtNFopxMgn3U (ECDSA)
SSH host key: SHA256:CKA9BUCHu5jKhECTUSyBGQRyOQQMReyIfUIOR/nDsXY (ED25519)
enp1s0: 192.168.122.40 fe80::a486:c31a:e64:6c0c

Hint: Num Lock on

localhost login: root
Password:
Have a lot of fun...
localhost:~ # whoami
root
localhost:~ # pwd
/root
localhost:~ #
```

### 3 For more information


For information on related topics, refer to the following resources:

- Documentation of the Agama open-source project: <https://agama-project.github.io/docs/user> 
- IBM documentation for SUSE distributions <https://www.ibm.com/docs/en/linux-on-systems?topic=distributions-suse-linux-enterprise-server>

### 4 Legal Notice

Copyright© 2006–2025 SUSE LLC and contributors. All rights reserved.

Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.2 or (at your option) version 1.3; with the Invariant Section being this copyright notice and license. A copy of the license version 1.2 is included in the section entitled “GNU Free Documentation License”.

For SUSE trademarks, see <https://www.suse.com/company/legal/> . All other third-party trademarks are the property of their respective owners. Trademark symbols (®, ™ etc.) denote trademarks of SUSE and its affiliates. Asterisks (\*) denote third-party trademarks.

All information found in this book has been compiled with utmost attention to detail. However, this does not guarantee complete accuracy. Neither SUSE LLC, its affiliates, the authors, nor the translators shall be held liable for possible errors or the consequences thereof.

# A GNU Free Documentation License

Copyright (C) 2000, 2001, 2002 Free Software Foundation, Inc. 51 Franklin St, Fifth Floor, Boston, MA 02110-1301 USA. Everyone is permitted to copy and distribute verbatim copies of this license document, but changing it is not allowed.

## 0. PREAMBLE

The purpose of this License is to make a manual, textbook, or other functional and useful document "free" in the sense of freedom: to assure everyone the effective freedom to copy and redistribute it, with or without modifying it, either commercially or non-commercially. Secondly, this License preserves for the author and publisher a way to get credit for their work, while not being considered responsible for modifications made by others.

This License is a kind of "copyleft", which means that derivative works of the document must themselves be free in the same sense. It complements the GNU General Public License, which is a copyleft license designed for free software.

We have designed this License to use it for manuals for free software, because free software needs free documentation: a free program should come with manuals providing the same freedoms that the software does. But this License is not limited to software manuals; it can be used for any textual work, regardless of subject matter or whether it is published as a printed book. We recommend this License principally for works whose purpose is instruction or reference.

## 1. APPLICABILITY AND DEFINITIONS

This License applies to any manual or other work, in any medium, that contains a notice placed by the copyright holder saying it can be distributed under the terms of this License. Such a notice grants a world-wide, royalty-free license, unlimited in duration, to use that work under the conditions stated herein. The "Document", below, refers to any such manual or work. Any member of the public is a licensee, and is addressed as "you". You accept the license if you copy, modify or distribute the work in a way requiring permission under copyright law.

A "Modified Version" of the Document means any work containing the Document or a portion of it, either copied verbatim, or with modifications and/or translated into another language.

A "Secondary Section" is a named appendix or a front-matter section of the Document that deals exclusively with the relationship of the publishers or authors of the Document to the Document's overall subject (or to related matters) and contains nothing that could fall directly within that

overall subject. (Thus, if the Document is in part a textbook of mathematics, a Secondary Section may not explain any mathematics.) The relationship could be a matter of historical connection with the subject or with related matters, or of legal, commercial, philosophical, ethical or political position regarding them.

The "Invariant Sections" are certain Secondary Sections whose titles are designated, as being those of Invariant Sections, in the notice that says that the Document is released under this License. If a section does not fit the above definition of Secondary then it is not allowed to be designated as Invariant. The Document may contain zero Invariant Sections. If the Document does not identify any Invariant Sections then there are none.

The "Cover Texts" are certain short passages of text that are listed, as Front-Cover Texts or Back-Cover Texts, in the notice that says that the Document is released under this License. A Front-Cover Text may be at most 5 words, and a Back-Cover Text may be at most 25 words.

A "Transparent" copy of the Document means a machine-readable copy, represented in a format whose specification is available to the general public, that is suitable for revising the document straightforwardly with generic text editors or (for images composed of pixels) generic paint programs or (for drawings) some widely available drawing editor, and that is suitable for input to text formatters or for automatic translation to a variety of formats suitable for input to text formatters. A copy made in an otherwise Transparent file format whose markup, or absence of markup, has been arranged to thwart or discourage subsequent modification by readers is not Transparent. An image format is not Transparent if used for any substantial amount of text. A copy that is not "Transparent" is called "Opaque".

Examples of suitable formats for Transparent copies include plain ASCII without markup, Texinfo input format, LaTeX input format, SGML or XML using a publicly available DTD, and standard-conforming simple HTML, PostScript or PDF designed for human modification. Examples of transparent image formats include PNG, XCF and JPG. Opaque formats include proprietary formats that can be read and edited only by proprietary word processors, SGML or XML for which the DTD and/or processing tools are not generally available, and the machine-generated HTML, PostScript or PDF produced by some word processors for output purposes only.

The "Title Page" means, for a printed book, the title page itself, plus such following pages as are needed to hold, legibly, the material this License requires to appear in the title page. For works in formats which do not have any title page as such, "Title Page" means the text near the most prominent appearance of the work's title, preceding the beginning of the body of the text.

A section "Entitled XYZ" means a named subunit of the Document whose title either is precisely XYZ or contains XYZ in parentheses following text that translates XYZ in another language. (Here XYZ stands for a specific section name mentioned below, such as "Acknowledgements", "Dedications", "Endorsements", or "History".) To "Preserve the Title" of such a section when you modify the Document means that it remains a section "Entitled XYZ" according to this definition. The Document may include Warranty Disclaimers next to the notice which states that this License applies to the Document. These Warranty Disclaimers are considered to be included by reference in this License, but only as regards disclaiming warranties: any other implication that these Warranty Disclaimers may have is void and has no effect on the meaning of this License.

## 2. VERBATIM COPYING

You may copy and distribute the Document in any medium, either commercially or non-commercially, provided that this License, the copyright notices, and the license notice saying this License applies to the Document are reproduced in all copies, and that you add no other conditions whatsoever to those of this License. You may not use technical measures to obstruct or control the reading or further copying of the copies you make or distribute. However, you may accept compensation in exchange for copies. If you distribute a large enough number of copies you must also follow the conditions in section 3.

You may also lend copies, under the same conditions stated above, and you may publicly display copies.

## 3. COPYING IN QUANTITY

If you publish printed copies (or copies in media that commonly have printed covers) of the Document, numbering more than 100, and the Document's license notice requires Cover Texts, you must enclose the copies in covers that carry, clearly and legibly, all these Cover Texts: Front-Cover Texts on the front cover, and Back-Cover Texts on the back cover. Both covers must also clearly and legibly identify you as the publisher of these copies. The front cover must present the full title with all words of the title equally prominent and visible. You may add other material on the covers in addition. Copying with changes limited to the covers, as long as they preserve the title of the Document and satisfy these conditions, can be treated as verbatim copying in other respects.

If the required texts for either cover are too voluminous to fit legibly, you should put the first ones listed (as many as fit reasonably) on the actual cover, and continue the rest onto adjacent pages.

If you publish or distribute Opaque copies of the Document numbering more than 100, you must either include a machine-readable Transparent copy along with each Opaque copy, or state in or with each Opaque copy a computer-network location from which the general network-using public has access to download using public-standard network protocols a complete Transparent copy of the Document, free of added material. If you use the latter option, you must take reasonably prudent steps, when you begin distribution of Opaque copies in quantity, to ensure that this Transparent copy will remain thus accessible at the stated location until at least one year after the last time you distribute an Opaque copy (directly or through your agents or retailers) of that edition to the public.

It is requested, but not required, that you contact the authors of the Document well before redistributing any large number of copies, to give them a chance to provide you with an updated version of the Document.

#### 4. MODIFICATIONS

You may copy and distribute a Modified Version of the Document under the conditions of sections 2 and 3 above, provided that you release the Modified Version under precisely this License, with the Modified Version filling the role of the Document, thus licensing distribution and modification of the Modified Version to whoever possesses a copy of it. In addition, you must do these things in the Modified Version:

- A. Use in the Title Page (and on the covers, if any) a title distinct from that of the Document, and from those of previous versions (which should, if there were any, be listed in the History section of the Document). You may use the same title as a previous version if the original publisher of that version gives permission.
- B. List on the Title Page, as authors, one or more persons or entities responsible for authorship of the modifications in the Modified Version, together with at least five of the principal authors of the Document (all of its principal authors, if it has fewer than five), unless they release you from this requirement.
- C. State on the Title page the name of the publisher of the Modified Version, as the publisher.
- D. Preserve all the copyright notices of the Document.

- E. Add an appropriate copyright notice for your modifications adjacent to the other copyright notices.
- F. Include, immediately after the copyright notices, a license notice giving the public permission to use the Modified Version under the terms of this License, in the form shown in the Addendum below.
- G. Preserve in that license notice the full lists of Invariant Sections and required Cover Texts given in the Document's license notice.
- H. Include an unaltered copy of this License.
- I. Preserve the section Entitled "History", Preserve its Title, and add to it an item stating at least the title, year, new authors, and publisher of the Modified Version as given on the Title Page. If there is no section Entitled "History" in the Document, create one stating the title, year, authors, and publisher of the Document as given on its Title Page, then add an item describing the Modified Version as stated in the previous sentence.
- J. Preserve the network location, if any, given in the Document for public access to a Transparent copy of the Document, and likewise the network locations given in the Document for previous versions it was based on. These may be placed in the "History" section. You may omit a network location for a work that was published at least four years before the Document itself, or if the original publisher of the version it refers to gives permission.
- K. For any section Entitled "Acknowledgements" or "Dedications", Preserve the Title of the section, and preserve in the section all the substance and tone of each of the contributor acknowledgements and/or dedications given therein.
- L. Preserve all the Invariant Sections of the Document, unaltered in their text and in their titles. Section numbers or the equivalent are not considered part of the section titles.
- M. Delete any section Entitled "Endorsements". Such a section may not be included in the Modified Version.
- N. Do not retitle any existing section to be Entitled "Endorsements" or to conflict in title with any Invariant Section.
- O. Preserve any Warranty Disclaimers.

If the Modified Version includes new front-matter sections or appendices that qualify as Secondary Sections and contain no material copied from the Document, you may at your option designate some or all of these sections as invariant. To do this, add their titles to the list of Invariant Sections in the Modified Version's license notice. These titles must be distinct from any other section titles.

You may add a section Entitled "Endorsements", provided it contains nothing but endorsements of your Modified Version by various parties--for example, statements of peer review or that the text has been approved by an organization as the authoritative definition of a standard.

You may add a passage of up to five words as a Front-Cover Text, and a passage of up to 25 words as a Back-Cover Text, to the end of the list of Cover Texts in the Modified Version. Only one passage of Front-Cover Text and one of Back-Cover Text may be added by (or through arrangements made by) any one entity. If the Document already includes a cover text for the same cover, previously added by you or by arrangement made by the same entity you are acting on behalf of, you may not add another; but you may replace the old one, on explicit permission from the previous publisher that added the old one.

The author(s) and publisher(s) of the Document do not by this License give permission to use their names for publicity for or to assert or imply endorsement of any Modified Version.

## 5. COMBINING DOCUMENTS

You may combine the Document with other documents released under this License, under the terms defined in section 4 above for modified versions, provided that you include in the combination all of the Invariant Sections of all of the original documents, unmodified, and list them all as Invariant Sections of your combined work in its license notice, and that you preserve all their Warranty Disclaimers.

The combined work need only contain one copy of this License, and multiple identical Invariant Sections may be replaced with a single copy. If there are multiple Invariant Sections with the same name but different contents, make the title of each such section unique by adding at the end of it, in parentheses, the name of the original author or publisher of that section if known, or else a unique number. Make the same adjustment to the section titles in the list of Invariant Sections in the license notice of the combined work.

In the combination, you must combine any sections Entitled "History" in the various original documents, forming one section Entitled "History"; likewise combine any sections Entitled "Acknowledgements", and any sections Entitled "Dedications". You must delete all sections Entitled "Endorsements".



## 6. COLLECTIONS OF DOCUMENTS

You may make a collection consisting of the Document and other documents released under this License, and replace the individual copies of this License in the various documents with a single copy that is included in the collection, provided that you follow the rules of this License for verbatim copying of each of the documents in all other respects.

You may extract a single document from such a collection, and distribute it individually under this License, provided you insert a copy of this License into the extracted document, and follow this License in all other respects regarding verbatim copying of that document.

## 7. AGGREGATION WITH INDEPENDENT WORKS

A compilation of the Document or its derivatives with other separate and independent documents or works, in or on a volume of a storage or distribution medium, is called an "aggregate" if the copyright resulting from the compilation is not used to limit the legal rights of the compilation's users beyond what the individual works permit. When the Document is included in an aggregate, this License does not apply to the other works in the aggregate which are not themselves derivative works of the Document.

If the Cover Text requirement of section 3 is applicable to these copies of the Document, then if the Document is less than one half of the entire aggregate, the Document's Cover Texts may be placed on covers that bracket the Document within the aggregate, or the electronic equivalent of covers if the Document is in electronic form. Otherwise they must appear on printed covers that bracket the whole aggregate.

## 8. TRANSLATION

Translation is considered a kind of modification, so you may distribute translations of the Document under the terms of section 4. Replacing Invariant Sections with translations requires special permission from their copyright holders, but you may include translations of some or all Invariant Sections in addition to the original versions of these Invariant Sections. You may include a translation of this License, and all the license notices in the Document, and any Warranty Disclaimers, provided that you also include the original English version of this License and the original versions of those notices and disclaimers. In case of a disagreement between the translation and the original version of this License or a notice or disclaimer, the original version will prevail.

If a section in the Document is Entitled "Acknowledgements", "Dedications", or "History", the requirement (section 4) to Preserve its Title (section 1) will typically require changing the actual title.

## 9. TERMINATION

You may not copy, modify, sublicense, or distribute the Document except as expressly provided for under this License. Any other attempt to copy, modify, sublicense or distribute the Document is void, and will automatically terminate your rights under this License. However, parties who have received copies, or rights, from you under this License will not have their licenses terminated so long as such parties remain in full compliance.

## 10. FUTURE REVISIONS OF THIS LICENSE

The Free Software Foundation may publish new, revised versions of the GNU Free Documentation License from time to time. Such new versions will be similar in spirit to the present version, but may differ in detail to address new problems or concerns. See <https://www.gnu.org/copyleft/>.

Each version of the License is given a distinguishing version number. If the Document specifies that a particular numbered version of this License "or any later version" applies to it, you have the option of following the terms and conditions either of that specified version or of any later version that has been published (not as a draft) by the Free Software Foundation. If the Document does not specify a version number of this License, you may choose any version ever published (not as a draft) by the Free Software Foundation.

## ADDENDUM: How to use this License for your documents

```
Copyright (c) YEAR YOUR NAME.  
Permission is granted to copy, distribute and/or modify this document  
under the terms of the GNU Free Documentation License, Version 1.2  
or any later version published by the Free Software Foundation;  
with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts.  
A copy of the license is included in the section entitled "GNU  
Free Documentation License".
```

If you have Invariant Sections, Front-Cover Texts and Back-Cover Texts, replace the “with...Texts.” line with this:

```
with the Invariant Sections being LIST THEIR TITLES, with the
Front-Cover Texts being LIST, and with the Back-Cover Texts being LIST.
```

If you have Invariant Sections without Cover Texts, or some other combination of the three, merge those two alternatives to suit the situation.

If your document contains nontrivial examples of program code, we recommend releasing these examples in parallel under your choice of free software license, such as the GNU General Public License, to permit their use in free software.