

SUSE Linux Enterprise Server 15 SP3

Installation Quick Start

This Quick Start guides you step-by-step through the installation of SUSE® Linux Enterprise Server 15 SP3.

Publication Date: November 28, 2024

Contents

- 1 Welcome to SUSE Linux Enterprise Server 2
- 2 The installation procedure 3
- 3 Legal notice 26
- 4 GNU Free Documentation License 27

1 Welcome to SUSE Linux Enterprise Server

Use the following procedures to install the product on all supported hardware platforms. They assume you have successfully booted/IPLed into the installation system. For more detailed installation instructions and deployment strategies, refer to the *Book "Deployment Guide"*. For platform specific preparations required to boot or IPL into the installation system, refer to the following parts of the aforementioned guide:

- *Book "Deployment Guide", Chapter 2 "Installation on AMD64 and Intel 64"*
- *Book "Deployment Guide", Chapter 3 "Installation on AArch64"*
- *Book "Deployment Guide", Chapter 4 "Installation on IBM POWER"*
- *Book "Deployment Guide", Chapter 5 "Installation on IBM Z and LinuxONE"*

1.1 The Unified Installer

Starting with SUSE Linux Enterprise Server 15, the installation medium only consists of the Unified Installer, a minimal system for installing, updating, and registering all SUSE Linux Enterprise base products. During the installation you can add functionality by selecting modules and extensions to be installed on top of the Unified Installer.

1.2 Installing offline or without registration

The default installation medium `SLE-15-SP3-Online-ARCH-GM-media1.iso` is optimized for size and does not contain any modules and extensions. Therefore, the installation requires network access to register your product and retrieve repository data for the modules and extensions.

For installation without registering the system, use the `SLE-15-SP3-Full-ARCH-GM-media1.iso` image from <https://download.suse.com/>.



Tip: Copying the installation media image to a removable flash disk

Use the following command to copy the contents of the installation image to a removable flash disk.

```
> sudo dd if=IMAGE of=FLASH_DISK bs=4M && sync
```

IMAGE needs to be replaced with the path to the SLE-15-SP3-Online-ARCH-GM-media1.iso or SLE-15-SP3-Full-ARCH-GM-media1.iso image file. FLASH_DISK needs to be replaced with the flash device. To identify the device, insert it and run:

```
# grep -Ff <(hwinfo --disk --short) <(hwinfo --usb --short)
disk:
  /dev/sdc                General USB Flash Disk
```

Make sure the size of the device is sufficient for the desired image. You can check the size of the device with:

```
# fdisk -l /dev/sdc | grep -e "^/dev"
/dev/sdc1 *      2048 31490047 31488000  15G 83 Linux
```

In this example, the device has a capacity of 15 GB. The command to use for the SLE-15-SP3-Full-ARCH-GM-media1.iso would be:


```
dd if=SLE-15-SP3-Full-ARCH-GM-media1.iso of=/dev/sdc bs=4M && sync
```

The device must not be mounted when running the dd command. Note that all data on the partition will be erased!

2 The installation procedure

To install SUSE Linux Enterprise Server, boot or IPL into the installer from the Unified Installer medium and start the installation.

2.1 Language, keyboard, and product selection



The *Language* and *Keyboard Layout* settings are initialized with the language you chose on the boot screen. If you did not change the default, it will be English (US). Change the settings here, if necessary. Use the *Keyboard Test* text box to test the layout.

With the Unified Installer you can install all SUSE Linux Enterprise base products:

- SUSE Linux Enterprise Server 15 SP3 (covered here)
- SUSE Linux Enterprise Desktop 15 SP3 (for installation instructions, refer to <https://documentation.suse.com/sled/>)
- SUSE Linux Enterprise High Performance Computing 15 SP3
- SUSE Linux Enterprise Real Time 15 SP3 (for installation instructions, refer to <https://documentation.suse.com/sle-rt/>)

- SUSE Linux Enterprise Server for SAP Applications 15 SP3 (for installation instructions, refer to <https://documentation.suse.com/sles-sap>)
- SUSE Manager Server 4.2 (for installation instructions, refer to <https://documentation.suse.com/suma/>)
- SUSE Manager Proxy 4.2 (for installation instructions, refer to <https://documentation.suse.com/suma/>)
- SUSE Manager Retail Branch Server 4.2 (for installation instructions, refer to <https://documentation.suse.com/suma-retail>)

Select a product for installation. You need to have a registration code for the respective product. In this document it is assumed you have chosen SUSE Linux Enterprise Server. Proceed with *Next*.



Tip: High contrast color scheme


If you have difficulties to read the labels in the installer, press **Shift + F4** to switch to the color scheme for vision impaired users. Press the buttons again to switch back to the default scheme.

2.2 License agreement



Read the License Agreement. It is presented in the language you have chosen on the boot screen. Translations are available via the *License Language* drop-down box. You need to accept the agreement by checking *I Agree to the License Terms* to install SUSE Linux Enterprise Server. Proceed with *Next*.

2.3 Network settings



A system analysis is performed, where the installer probes for storage devices, and tries to find other installed systems. If the network was automatically configured via DHCP during the start of the installation, you will be taken to the registration step.

If the network is not yet configured, the *Network Settings* dialog opens. Choose a network interface from the list and configure it with *Edit*. Alternatively, *Add* an interface manually. See *Book "Deployment Guide", Chapter 8 "Installation steps", Section 8.6 "Network settings"* and *Book "Administration Guide", Chapter 19 "Basic networking", Section 19.4 "Configuring a network connection with YaST"* for more information. If you prefer to do an installation without network access, skip this step without making any changes and proceed with *Next*.

2.4 IBM Z: disk activation

Skip this step if you are not installing on IBM Z hardware.

Disk Activation

[Network Configuration...](#)[Configure DASD Disks](#)[Configure zFCP Disks](#)[Configure iSCSI Disks](#)[Help](#)[Abort](#)[Back](#)[Next](#)

Configure the attached hard disks. Select DASD, Fibre Channel Attached SCSI Disks (zFCP), or iSCSI for the installation of SUSE Linux Enterprise Server. The DASD and zFCP configuration buttons are only available if the corresponding devices are attached. Proceed with *Next* to set up the selected disk type. For more information, refer to *Book "Deployment Guide", Chapter 8 "Installation steps", Section 8.5 "IBM Z: disk activation"*.

2.5 Registration

SUSE

Registration

SUSE Linux Enterprise Server 15 SP3

Please select your preferred method of registration.

- Register System via scc.suse.com
 - E-mail Address
 - Registration Code
- Register System via local RMT Server
 - Local Registration Server URL
 - https://rmt.example.com
- Skip Registration

[Help](#) [Abort](#) [Back](#) [Next](#)

To get technical support and product updates, you need to register and activate SUSE Linux Enterprise Server with the SUSE Customer Center or a local registration server. Registering your product at this stage also grants you immediate access to the update repository. This enables you to install the system with the latest updates and patches available.

When registering, repositories and dependencies for the modules and extensions, which you install with the next step, are loaded from the registration server.

Register system via scc.suse.com

To register with the SUSE Customer Center, enter the *E-mail Address* associated with your SCC account and the *Registration Code* for SUSE Linux Enterprise Server. Proceed with *Next*.

Register system via local RMT server

If your organization provides a local registration server, you may alternatively register there. Activate *Register System via local RMT Server* and either choose a URL from the drop-down box or type in an address. Proceed with *Next*.

Skip registration

If you are offline or want to skip registration, activate *Skip Registration*. Accept the warning with *OK* and proceed with *Next*.

Important: Skipping the registration

Your system and extensions need to be registered in order to retrieve updates and to be eligible for support. Skipping the registration is only possible when installing from the [SLE-15-SP3-Full-ARCH-GM-media1.iso](#) image.

If you do not register during the installation, you can do so at any time later from the running system. To do so, run *YaST > Product Registration* or the command line tool **SUSE-Connect**.


Tip: Installing product patches at installation time

After SUSE Linux Enterprise Server has been successfully registered, you are asked whether to install the latest available online updates during the installation. If choosing *Yes*, the system will be installed with the most current packages without having to apply the updates after installation. Activating this option is recommended.

Note: Firewall settings for receiving updates

By default, the firewall on SUSE Linux Enterprise Server only blocks incoming connections. If your system is behind another firewall that blocks outgoing traffic, make sure to allow connections to <https://scc.suse.com/>  and https://updates.suse.com  on ports 80 and 443 in order to receive updates.

2.6 Extension and module selection



After the system is successfully registered, the installer lists modules and extensions that are available for SUSE Linux Enterprise Server. Modules are components which allow you to shape the product according to your needs. They are free of charge. Extensions add functionality to your product. They are offered as subscriptions and require a registration key that is liable for costs.

The availability of certain modules or extensions depends on the product you have chosen in the first step of this installation. For a description of the modules and their life cycles, select a module to see the accompanying text. More detailed information is available in the [Modules and Extensions Quick Start \(https://documentation.suse.com/sles-15/html/SLES-all/article-modules.html\)](https://documentation.suse.com/sles-15/html/SLES-all/article-modules.html).

The selection of modules indirectly affects the scope of the installation, because it defines which software sources (repositories) are available for installation and in the running system.

The following modules and extensions are available for SUSE Linux Enterprise Server:

Basesystem Module

This module adds a basic system on top of the Unified Installer. It is required by all other modules and extensions. The scope of an installation that only contains the base system is comparable to the installation pattern *minimal system* of previous SUSE Linux Enterprise Server versions. This module is selected for installation by default and should not be de-selected.

Dependencies: None

Certifications Module

Contains the FIPS 140-2 certification packages.

Dependencies: Basesystem

Containers Module

Contains support and tools for containers.

Dependencies: Basesystem

Desktop Applications Module

Adds a graphical user interface and essential desktop applications to the system.

Dependencies: Basesystem

Development Tools Module

Contains compilers (including `gcc`) and libraries required for compiling and debugging applications. Replaces the former Software Development Kit (SDK).

Dependencies: Basesystem, Desktop Applications

Legacy Module

Helps you with migrating applications from earlier versions of SUSE Linux Enterprise Server and other systems to SLES 15 SP3, by providing packages which are discontinued on SUSE Linux Enterprise. Packages in this module are selected based on the requirement for migration and the level of complexity of configuration.

This module is recommended when migrating from a previous product version.

Dependencies: Basesystem, Server Applications

NVIDIA Compute Module

Contains the NVIDIA CUDA (Compute Unified Device Architecture) drivers.

The software in this module is provided by NVIDIA under the [CUDA End User License Agreement \(http://docs.nvidia.com/cuda/eula/\)](http://docs.nvidia.com/cuda/eula/) and is not supported by SUSE.

Dependencies: Basesystem

Public Cloud Module

Contains all tools required to create images for deploying SUSE Linux Enterprise Server in cloud environments such as the Amazon Web Services (AWS), Microsoft Azure, Google Compute Platform, or OpenStack.

Dependencies: Basesystem, Server Applications

Python 2 Module

SUSE Linux Enterprise 15 SP3 uses Python version 3. This module contains the Python 2 runtime and modules.

Dependencies: Basesystem

Server Applications Module

Adds server functionality by providing network services such as DHCP server, name server, or Web server. This module is selected for installation by default; deselecting it is not recommended.

Dependencies: Basesystem

SUSE Linux Enterprise High Availability

Adds clustering support for mission critical setups to SUSE Linux Enterprise Server. This extension requires a separate license key.

Dependencies: Basesystem, Server Applications

SUSE Linux Enterprise Live Patching

Adds support for performing critical patching without having to shut down the system. This extension requires a separate license key.

Dependencies: Basesystem, Server Applications

SUSE Linux Enterprise Workstation Extension

Extends the functionality of SUSE Linux Enterprise Server with packages from SUSE Linux Enterprise Desktop, like additional desktop applications (office suite, e-mail client, graphical editor, etc.) and libraries. It allows to combine both products to create a fully featured workstation. This extension requires a separate license key.

Dependencies: Basesystem, Desktop Applications

SUSE Package Hub

Provides access to packages for SUSE Linux Enterprise Server maintained by the openSUSE community. These packages are delivered without L3 support and do not interfere with the supportability of SUSE Linux Enterprise Server. For more information refer to <https://packagehub.suse.com/>.

Dependencies: Basesystem

Transactional Server Module

Adds support for transactional updates. Updates are either applied to the system all together in a single transaction, or not. This happens without influencing the running system. If an update fails, or if the successful update is deemed to be incompatible or otherwise incorrect, it can be discarded to immediately return the system to its previous functioning state.

Dependencies: Basesystem

Web and Scripting Module

Contains packages intended for a running Web server.

Dependencies: Basesystem, Server Applications

Some modules depend on the installation of other modules. Therefore, when selecting a module, other modules may be selected automatically to fulfill dependencies.

Depending on the product, the registration server can mark modules and extensions as recommended. Recommended modules and extensions are preselected for registration and installation. To avoid installing these recommendations, deselect them manually.


Select the modules and extension you want to install and proceed with *Next*. In case you have chosen one or more extensions, you will be prompted to provide the respective registration codes. Depending on your choice, it may also be necessary to accept additional license agreements.



Important: Default modules for offline installation

When performing an offline installation from the *SLE-15-SP3-Full-ARCH-GM-media1.iso*, only the *Basesystem Module* is selected by default. To install the complete default package set of SUSE Linux Enterprise Server, additionally select the *Server Applications Module*.

2.7 Add-on product



The *Add-On Product* dialog allows you to add additional software sources (so-called “repositories”) to SUSE Linux Enterprise Server, that are not provided by the SUSE Customer Center. Such add-on products may include third-party products and drivers or additional software for your system.




Tip: Adding drivers during the installation

You can also add driver update repositories via the *Add-On Product* dialog. Driver updates for SUSE Linux Enterprise are provided at <http://drivers.suse.com/>. These drivers have been created via the SUSE SolidDriver Program.

If you want to skip this step, proceed with *Next*. Otherwise activate *I would like to Install an Add-on Product*. Specify a media type, a local path, or a network resource hosting the repository and follow the on-screen instructions.

Check *Download Repository Description Files* to download the files describing the repository now. If deactivated, they will be downloaded after the installation has started. Proceed with *Next* and insert a medium if required. Depending on the product's content it may be necessary to accept additional license agreements. Proceed with *Next*. If you have chosen an add-on product requiring a registration key, you will be asked to enter it before proceeding to the next step.

2.8 System role




The availability of system roles depends on your selection of modules and extensions. System roles define, for example, the set of software patterns that is going to be preselected for the installation. Refer to the description on screen to make your choice. Select a role and proceed with *Next*. If from the enabled modules only one role or no role is suitable for the respective base product, the *System Role* dialog is omitted.



Tip: Release notes

From this point on, the Release Notes can be viewed from any screen during the installation process by selecting *Release Notes*.

2.9 Suggested partitioning



Review the partition setup proposed by the system. If necessary, change it. You have the following options:

Guided setup

Starts a wizard which lets you refine the partitioning proposal. Options available here depend on your system setup. In case it contains more than a single hard disk, you may choose which disk(s) to use and where to place the root partition. If the disk(s) already contain partitions, decide whether to remove or resize them.

In subsequent steps you may also add LVM support and disk encryption. You can change the file system for the root partition and decide whether to have a separate home partition or not.

Expert partitioner

Opens the *Expert Partitioner* described in Book “*Deployment Guide*”, Chapter 10 “*Expert Partitioner*”, Section 10.1 “*Using the Expert Partitioner*”. This gives you full control over the partitioning setup and lets you create a custom setup. This option is intended for experts.



Warning: Disk space units

Note that for partitioning purposes, disk space is measured in binary units, rather than in decimal units. For example, if you enter sizes of 1GB, 1GiB or 1G, they all signify 1 GiB (Gibibyte), as opposed to 1 GB (Gigabyte).

Binary

1 GiB = 1 073 741 824 bytes.

Decimal


1 GB = 1 000 000 000 bytes.

Difference

1 GiB ≈ 1.07 GB.


To accept the proposed setup without any changes, choose *Next* to proceed.

2.10 Clock and time zone



Select the clock and time zone to use in your system. To manually adjust the time or to configure an NTP server for time synchronization, choose *Other Settings*. See Book *“Deployment Guide”, Chapter 8 “Installation steps”, Section 8.12 “Clock and time zone”* for detailed information. Proceed with *Next*.

2.11 Local user



The screenshot shows the SUSE Local User creation interface. It features a dark theme with the SUSE logo in the top left. The main heading is "Local User". Below this, there are two radio button options: "Create New User" (which is selected) and "Skip User Creation". The "Create New User" section includes four text input fields: "User's Full Name", "Username", "Password", and "Confirm Password". Below these fields are two checkboxes: "Use this password for system administrator" and "Automatic Login". At the bottom of the screen, there are three buttons: "Help", "Release Notes...", and "Next" (highlighted in green), along with "Abort" and "Back" buttons.

To create a local user, type the first and last name in the *User's Full Name* field, the login name in the *Username* field, and the password in the *Password* field.

The password should be at least eight characters long and should contain both uppercase and lowercase letters and numbers. The maximum length for passwords is 72 characters, and passwords are case-sensitive.


For security reasons it is also strongly recommended *not* to enable the *Automatic Login*. You should also *not Use this Password for the System Administrator* but rather provide a separate root password in the next installation step.

If you install on a system where a previous Linux installation was found, you may *Import User Data from a Previous Installation*. Click *Choose User* for a list of available user accounts. Select one or more user.

In an environment where users are centrally managed (for example by NIS or LDAP) you can skip the creation of local users. Select *Skip User Creation* in this case.

Proceed with *Next*.

2.12 Authentication for the system administrator “root”



The screenshot shows the SUSE logo at the top left. The main heading is "Authentication for the System Administrator 'root'". Below this, there is a warning: "Do not forget what you enter here." The form contains three input fields: "Password for root User", "Confirm Password", and "Test Keyboard Layout". Below these is the "Import Public SSH Key" section, which includes a dropdown menu showing "QEMU_DVD-ROM (/dev/sr0)", a "Refresh" button, and a "Browse..." button. At the bottom of the screen, there are four buttons: "Help", "Release Notes...", "Abort", and "Next".

Type a password for the system administrator (called the root user) or provide a public SSH key. If you want, you can use both.

Because the root user is equipped with extensive permissions, the password should be chosen carefully. You should never forget the root password! After you entered it here, the password cannot be retrieved.




Tip: Passwords and keyboard layout

It is recommended to only use US ASCII characters. In case of a system error or when you need to start your system in rescue mode, the keyboard may not be localized.

If you want to access the system remotely via SSH using a public key, import a key from a removable media or an existing partition. See *Book “Deployment Guide”, Chapter 8 “Installation steps”, Section 8.14 “Authentication for the system administrator root”* for more information.

Proceed with *Next*.

2.13 Installation settings



Use the *Installation Settings* screen to review and—if necessary—change several proposed installation settings. The current configuration is listed for each setting. To change it, click the headline. Some settings, such as firewall or SSH can directly be changed by clicking the respective links.

Important: Remote access

Changes you can make here, can also be made later at any time from the installed system. However, if you need remote access right after the installation, you may need to open the SSH port in the *Security* settings.

Software

The scope of the installation is defined by the modules and extensions you have chosen for this installation. However, depending on your selection, not all packages available in a module are selected for installation.

Clicking *Software* opens the *Software Selection and System Tasks* screen, where you can change the software selection by selecting or deselecting patterns. Each pattern contains several software packages needed for specific functions (for example, *KVM Host Server*). For a more detailed selection based on software packages to install, select *Details* to switch to the YaST *Software Manager*. See Book “*Deployment Guide*”, Chapter 21 “*Installing or removing software*” for more information.

Booting

This section shows the boot loader configuration. Changing the defaults is only recommended if really needed. Refer to Book “*Administration Guide*”, Chapter 14 “*The boot loader GRUB 2*” for details.

Security

The *CPU Mitigations* refer to kernel boot command line parameters for software mitigations that have been deployed to prevent CPU side-channel attacks. Click the selected entry to choose a different option. For details, see Book “*Administration Guide*”, Chapter 14 “*The boot loader GRUB 2*” *CPU Mitigations*.

By default, the *Firewall* is enabled on all configured network interfaces. To completely disable `firewalld` for, click *disable* (not recommended). Refer to Book “*Security and Hardening Guide*”, Chapter 23 “*Masquerading and firewalls*” for configuration details.



Note: Firewall settings for receiving updates

By default, the firewall on SUSE Linux Enterprise Server only blocks incoming connections. If your system is behind another firewall that blocks outgoing traffic, make sure to allow connections to <https://scc.suse.com/> and <https://updates.suse.com/> on ports 80 and 443 in order to receive updates.

The *SSH service* is enabled by default, but its port (22) is closed in the firewall. Click *open* to open the port or *disable* to disable the service. Note that if SSH is disabled, remote logins will not be possible. Refer to Book “*Security and Hardening Guide*”, Chapter 22 “*Securing network operations with OpenSSH*” for more information.

Network configuration

Displays the current network configuration. By default, **wicked** is used for server installations and NetworkManager for desktop workloads. Click *Network Configuration* to change the settings. For details, see Book “*Administration Guide*”, Chapter 19 “*Basic networking*”, Section 19.4 “*Configuring a network connection with YaST*”.



Important: Support for NetworkManager

SUSE only supports NetworkManager for desktop workloads with SLED or the Workstation extension. All server certifications are done with **wicked** as the network configuration tool, and using NetworkManager may invalidate them. NetworkManager is not supported by SUSE for server workloads.

Kdump

Kdump saves the memory image (“core dump”) to the file system in case the kernel crashes. This enables you to find the cause of the crash by debugging the dump file. Kdump is preconfigured and enabled by default. See Book “*System Analysis and Tuning Guide*”, Chapter 20 “*Kexec and Kdump*”, Section 20.7 “*Basic Kdump configuration*” for more information.


Default systemd target

In case you have installed the desktop applications module, the system boots into the *graphical* target, with network, multiuser and display manager support. Switch to *multi-user* if you do not need to log in via display manager.

System

View detailed hardware information by clicking *System*. In the resulting screen you can also change *Kernel Settings*—see Book “*Deployment Guide*”, Chapter 8 “*Installation steps*”, Section 8.15.9 “*System*” for more information.

2.14 Start the installation



After you have finalized the system configuration on the *Installation Settings* screen, click *Install*. Depending on your software selection you may need to agree to license agreements before the installation confirmation screen pops up. Up to this point no changes have been made to your system. After you click *Install* a second time, the installation process starts.

2.15 The installation process

SUSE

Performing Installation

Details SLES15-SP3 Release Notes

Media	Remaining	Packages	Time
Total	1.480 GiB	779	04:42
SLE-Product-SLES15-SP3-Pool	1.44 MiB	2	00:00
SLE-Module-Basesystem15-SP3-Pool	814.45 MiB	341	02:32
SLE-Module-Basesystem15-SP3-Updates	11.17 MiB	2	00:02
SLE-Module-Server-Applications15-SP3-Pool	632.2 KiB	5	00:00
SLE-Module-Desktop-Applications15-SP3-Pool	687.83 MiB	429	02:08

Actions performed:

- Downloading ruby2.5-rubygem-cfa (download size 38.9 KiB)
- Installing ruby2.5-rubygem-cfa-1.0.2-1.33.x86_64.rpm (installed size 62.1 KiB)
- Downloading ruby2.5-rubygem-nokogiri (download size 9.06 MiB)
- Installing ruby2.5-rubygem-nokogiri-1.8.5-3.6.1.x86_64.rpm (installed size 9.59 MiB)
- Downloading ruby2.5-rubygem-cheetah (download size 33 KiB)
- Installing ruby2.5-rubygem-cheetah-0.5.2-1.33.x86_64.rpm (installed size 50.4 KiB)
- Downloading yast2-ruby-bindings (download size 141.6 KiB)
- Installing yast2-ruby-bindings-4.3.14-1.1.x86_64.rpm (installed size 450.4 KiB)
- Downloading libsamba-util0 (download size 277.2 KiB)
- Installing libsamba-util0-4.13.4+git.187.5ad4708741a-1.24.x86_64.rpm (installed size 458.3 KiB)
- Downloading ruby2.5-rubygem-cfa_grub2 (download size 21.7 KiB)
- Installing ruby2.5-rubygem-cfa_grub2-2.0.0-1.55.x86_64.rpm (installed size 24.3 KiB)

Installing ruby2.5-rubygem-cfa_grub2-2.0.0-1.55.x86_64.rpm (installed size 24.3 KiB)

0%

Installing Packages... (Remaining: 1.480 GiB / 04:42, 779 packages)

52%

Help Abort Back Next

During the installation, the progress is shown in detail on the *Details* tab. The *SUSE Linux Enterprise Server Release Notes* tab shows important information; reading them is recommended.

After the installation routine has finished, the computer is rebooted into the installed system. Log in and start YaST to fine-tune the system. If you are not using a graphical desktop or are working from remote, refer to *Book "Administration Guide", Chapter 4 "YaST in text mode"* for information on using YaST from a terminal.

3 Legal notice

Copyright© 2006– 2024 SUSE LLC and contributors. All rights reserved.

Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.2 or (at your option) version 1.3; with the Invariant Section being this copyright notice and license. A copy of the license version 1.2 is included in the section entitled “GNU Free Documentation License”.

For SUSE trademarks, see <https://www.suse.com/company/legal/>. All other third-party trademarks are the property of their respective owners. Trademark symbols (®, ™ etc.) denote trademarks of SUSE and its affiliates. Asterisks (*) denote third-party trademarks.

All information found in this book has been compiled with utmost attention to detail. However, this does not guarantee complete accuracy. Neither SUSE LLC, its affiliates, the authors, nor the translators shall be held liable for possible errors or the consequences thereof.

GNU Free Documentation License

Copyright (C) 2000, 2001, 2002 Free Software Foundation, Inc. 51 Franklin St, Fifth Floor, Boston, MA 02110-1301 USA. Everyone is permitted to copy and distribute verbatim copies of this license document, but changing it is not allowed.

0. PREAMBLE

The purpose of this License is to make a manual, textbook, or other functional and useful document “free” in the sense of freedom: to assure everyone the effective freedom to copy and redistribute it, with or without modifying it, either commercially or non-commercially. Secondly, this License preserves for the author and publisher a way to get credit for their work, while not being considered responsible for modifications made by others.

This License is a kind of “copyleft”, which means that derivative works of the document must themselves be free in the same sense. It complements the GNU General Public License, which is a copyleft license designed for free software.

We have designed this License to use it for manuals for free software, because free software needs free documentation: a free program should come with manuals providing the same freedoms that the software does. But this License is not limited to software manuals; it can be used for any textual work, regardless of subject matter or whether it is published as a printed book. We recommend this License principally for works whose purpose is instruction or reference.

1. APPLICABILITY AND DEFINITIONS

This License applies to any manual or other work, in any medium, that contains a notice placed by the copyright holder saying it can be distributed under the terms of this License. Such a notice grants a world-wide, royalty-free license, unlimited in duration, to use that work under the conditions stated herein. The “Document”, below, refers to any such manual or work. Any member of the public is a licensee, and is addressed as “you”. You accept the license if you copy, modify or distribute the work in a way requiring permission under copyright law.

A “Modified Version” of the Document means any work containing the Document or a portion of it, either copied verbatim, or with modifications and/or translated into another language.

A “Secondary Section” is a named appendix or a front-matter section of the Document that deals exclusively with the relationship of the publishers or authors of the Document to the Document’s overall subject (or to related matters) and contains nothing that could fall directly within that overall subject. (Thus, if the Document is in part a textbook of mathematics, a Secondary Section may not explain any mathematics.) The relationship could be a matter of historical connection with the subject or with related matters, or of legal, commercial, philosophical, ethical or political position regarding them.

The “Invariant Sections” are certain Secondary Sections whose titles are designated, as being those of Invariant Sections, in the notice that says that the Document is released under this License. If a section does not fit the above definition of Secondary then it is not allowed to be designated as Invariant. The Document may contain zero Invariant Sections. If the Document does not identify any Invariant Sections then there are none.

The “Cover Texts” are certain short passages of text that are listed, as Front-Cover Texts or Back-Cover Texts, in the notice that says that the Document is released under this License. A Front-Cover Text may be at most 5 words, and a Back-Cover Text may be at most 25 words.

A “Transparent” copy of the Document means a machine-readable copy, represented in a format whose specification is available to the general public, that is suitable for revising the document straightforwardly with generic text editors or (for images composed of pixels) generic paint programs or (for drawings) some widely available drawing editor, and that is suitable for input to text formatters or for automatic translation to a variety of formats suitable for input to text formatters. A copy made in an otherwise Transparent file format whose markup, or absence of markup, has been arranged to thwart or discourage subsequent modification by readers is not Transparent. An image format is not Transparent if used for any substantial amount of text. A copy that is not “Transparent” is called “Opaque”.

Examples of suitable formats for Transparent copies include plain ASCII without markup, Texinfo input format, LaTeX input format, SGML or XML using a publicly available DTD, and standard-conforming simple HTML, PostScript or PDF designed for human modification. Examples of transparent image formats include PNG, XCF and JPG. Opaque formats include proprietary formats that can be read and edited only by proprietary word processors, SGML or XML for which the DTD and/or processing tools are not generally available, and the machine-generated HTML, PostScript or PDF produced by some word processors for output purposes only.

The “Title Page” means, for a printed book, the title page itself, plus such following pages as are needed to hold, legibly, the material this License requires to appear in the title page. For works in formats which do not have any title page as such, “Title Page” means the text near the most prominent appearance of the work’s title, preceding the beginning of the body of the text.

A section “Entitled XYZ” means a named subunit of the Document whose title either is precisely XYZ or contains XYZ in parentheses following text that translates XYZ in another language. (Here XYZ stands for a specific section name mentioned below, such as “Acknowledgements”, “Dedications”, “Endorsements”, or “History”.) To “Preserve the Title” of such a section when you modify the Document means that it remains a section “Entitled XYZ” according to this definition.

The Document may include Warranty Disclaimers next to the notice which states that this License applies to the Document. These Warranty Disclaimers are considered to be included by reference in this License, but only as regards disclaiming warranties: any other implication that these Warranty Disclaimers may have is void and has no effect on the meaning of this License.

2. VERBATIM COPYING

You may copy and distribute the Document in any medium, either commercially or non-commercially, provided that this License, the copyright notices, and the license notice saying this License applies to the Document are reproduced in all copies, and that you add no other conditions whatsoever to those of this License. You may not use technical measures to obstruct or control the reading or further copying of the copies you make or distribute. However, you may accept compensation in exchange for copies. If you distribute a large enough number of copies you must also follow the conditions in section 3.

You may also lend copies, under the same conditions stated above, and you may publicly display copies.

3. COPYING IN QUANTITY

If you publish printed copies (or copies in media that commonly have printed covers) of the Document, numbering more than 100, and the Document's license notice requires Cover Texts, you must enclose the copies in covers that carry, clearly and legibly, all these Cover Texts: Front-Cover Texts on the front cover, and Back-Cover Texts on the back cover. Both covers must also clearly and legibly identify you as the publisher of these copies. The front cover must present the full title with all words of the title equally prominent and visible. You may add other material on the covers in addition. Copying with changes limited to the covers, as long as they preserve the title of the Document and satisfy these conditions, can be treated as verbatim copying in other respects. If the required texts for either cover are too voluminous to fit legibly, you should put the first ones listed (as many as fit reasonably) on the actual cover, and continue the rest onto adjacent pages. If you publish or distribute Opaque copies of the Document numbering more than 100, you must either include a machine-readable Transparent copy along with each Opaque copy, or state in or with each Opaque copy a computer-network location from which the general network-using public has access to download using public-standard network protocols a complete Transparent copy of the Document, free of added material. If you use the latter option, you must take reasonably prudent steps, when you begin distribution of Opaque copies in quantity, to ensure that this Transparent copy will remain thus accessible at the stated location until at least one year after the last time you distribute an Opaque copy (directly or through your agents or retailers) of that edition to the public.

It is requested, but not required, that you contact the authors of the Document well before redistributing any large number of copies, to give them a chance to provide you with an updated version of the Document.

4. MODIFICATIONS

You may copy and distribute a Modified Version of the Document under the conditions of sections 2 and 3 above, provided that you release the Modified Version under precisely this License, with the Modified Version filling the role of the Document, thus licensing distribution and modification of the Modified Version to whoever possesses a copy of it. In addition, you must do these things in the Modified Version:

- A. Use in the Title Page (and on the covers, if any) a title distinct from that of the Document, and from those of previous versions (which should, if there were any, be listed in the History section of the Document). You may use the same title as a previous version if the original publisher of that version gives permission.
- B. List on the Title Page, as authors, one or more persons or entities responsible for authorship of the modifications in the Modified Version, together with at least five of the principal authors of the Document (all of its principal authors, if it has fewer than five), unless they release you from this requirement.
- C. State on the Title page the name of the publisher of the Modified Version, as the publisher.
- D. Preserve all the copyright notices of the Document.
- E. Add an appropriate copyright notice for your modifications adjacent to the other copyright notices.
- F. Include, immediately after the copyright notices, a license notice giving the public permission to use the Modified Version under the terms of this License, in the form shown in the Addendum below.
- G. Preserve in that license notice the full lists of Invariant Sections and required Cover Texts given in the Document's license notice.
- H. Include an unaltered copy of this License.
- I. Preserve the section Entitled "History", Preserve its Title, and add to it an item stating at least the title, year, new authors, and publisher of the Modified Version as given on the Title Page. If there is no section Entitled "History" in the Document, create one stating the title, year, authors, and publisher of the Document as given on its Title Page, then add an item describing the Modified Version as stated in the previous sentence.
- J. Preserve the network location, if any, given in the Document for public access to a Transparent copy of the Document, and likewise the network locations given in the Document for previous versions it was based on. These may be placed in the "History" section. You may omit a network location for a work that was published at least four years before the Document itself, or if the original publisher of the version it refers to gives permission.
- K. For any section Entitled "Acknowledgements" or "Dedications", Preserve the Title of the section, and preserve in the section all the substance and tone of each of the contributor acknowledgements and/or dedications given therein.
- L. Preserve all the Invariant Sections of the Document, unaltered in their text and in their titles. Section numbers or the equivalent are not considered part of the section titles.
- M. Delete any section Entitled "Endorsements". Such a section may not be included in the Modified Version.
- N. Do not retitle any existing section to be Entitled "Endorsements" or to conflict in title with any Invariant Section.
- O. Preserve any Warranty Disclaimers.

If the Modified Version includes new front-matter sections or appendices that qualify as Secondary Sections and contain no material copied from the Document, you may at your option designate some or all of these sections as invariant. To do this, add their titles to the list of Invariant Sections in the Modified Version's license notice. These titles must be distinct from any other section titles. You may add a section Entitled "Endorsements", provided it contains nothing but endorsements of your Modified Version by various parties--for example, statements of peer review or that the text has been approved by an organization as the authoritative definition of a standard.

You may add a passage of up to five words as a Front-Cover Text, and a passage of up to 25 words as a Back-Cover Text, to the end of the list of Cover Texts in the Modified Version. Only one passage of Front-Cover Text and one of Back-Cover Text may be added by (or through arrangements made by) any one entity. If the Document already includes a cover text for the same cover, previously added by you or by arrangement made by the same entity you are acting on behalf of, you may not add another; but you may replace the old one, on explicit permission from the previous publisher that added the old one.

The author(s) and publisher(s) of the Document do not by this License give permission to use their names for publicity for or to assert or imply endorsement of any Modified Version.

5. COMBINING DOCUMENTS

You may combine the Document with other documents released under this License, under the terms defined in section 4 above for modified versions, provided that you include in the combination all of the Invariant Sections of all of the original documents, unmodified, and list them all as Invariant Sections of your combined work in its license notice, and that you preserve all their Warranty Disclaimers.

The combined work need only contain one copy of this License, and multiple identical Invariant Sections may be replaced with a single copy. If there are multiple Invariant Sections with the same name but different contents, make the title of each such section unique by adding at the end of it, in parentheses, the name of the original author or publisher of that section if known, or else a unique number. Make the same adjustment to the section titles in the list of Invariant Sections in the license notice of the combined work.

In the combination, you must combine any sections Entitled "History" in the various original documents, forming one section Entitled "History"; likewise combine any sections Entitled "Acknowledgements", and any sections Entitled "Dedications". You must delete all sections Entitled "Endorsements".

6. COLLECTIONS OF DOCUMENTS

You may make a collection consisting of the Document and other documents released under this License, and replace the individual copies of this License in the various documents with a single copy that is included in the collection, provided that you follow the rules of this License for verbatim copying of each of the documents in all other respects.

You may extract a single document from such a collection, and distribute it individually under this License, provided you insert a copy of this License into the extracted document, and follow this License in all other respects regarding verbatim copying of that document.

7. AGGREGATION WITH INDEPENDENT WORKS

A compilation of the Document or its derivatives with other separate and independent documents or works, in or on a volume of a storage or distribution medium, is called an "aggregate" if the copyright resulting from the compilation is not used to limit the legal rights of the compilation's users beyond what the individual works permit. When the Document is included in an aggregate, this License does not apply to the other works in the aggregate which are not themselves derivative works of the Document.

If the Cover Text requirement of section 3 is applicable to these copies of the Document, then if the Document is less than one half of the entire aggregate, the Document's Cover Texts may be placed on covers that bracket the Document within the aggregate, or the electronic equivalent of covers if the Document is in electronic form. Otherwise they must appear on printed covers that bracket the whole aggregate.

8. TRANSLATION

Translation is considered a kind of modification, so you may distribute translations of the Document under the terms of section 4. Replacing Invariant Sections with translations requires special permission from their copyright holders, but you may include translations of some or all Invariant Sections in addition to the original versions of these Invariant Sections. You may include a translation of this License, and all the license notices in the Document, and any Warranty Disclaimers, provided that you also include the original English version of this License and the original versions of those notices and disclaimers. In case of a disagreement between the translation and the original version of this License or a notice or disclaimer, the original version will prevail.

If a section in the Document is Entitled "Acknowledgements", "Dedications", or "History", the requirement (section 4) to Preserve its Title (section 1) will typically require changing the actual title.

9. TERMINATION

You may not copy, modify, sublicense, or distribute the Document except as expressly provided for under this License. Any other attempt to copy, modify, sublicense or distribute the Document is void, and will automatically terminate your rights under this License. However, parties who have received copies, or rights, from you under this License will not have their licenses terminated so long as such parties remain in full compliance.

10. FUTURE REVISIONS OF THIS LICENSE

The Free Software Foundation may publish new, revised versions of the GNU Free Documentation License from time to time. Such new versions will be similar in spirit to the present version, but may differ in detail to address new problems or concerns. See <https://www.gnu.org/copyleft/>.

Each version of the License is given a distinguishing version number. If the Document specifies that a particular numbered version of this License "or any later version" applies to it, you have the option of following the terms and conditions either of that specified version or of any later version that has been published (not as a draft) by the Free Software Foundation. If the Document does not specify a version number of this License, you may choose any version ever published (not as a draft) by the Free Software Foundation.

ADDENDUM: How to use this License for your documents

```
Copyright (c) YEAR YOUR NAME.
Permission is granted to copy, distribute and/or modify this document
under the terms of the GNU Free Documentation License, Version 1.2
or any later version published by the Free Software Foundation;
with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts.
A copy of the license is included in the section entitled "GNU
Free Documentation License".
```

If you have Invariant Sections, Front-Cover Texts and Back-Cover Texts, replace the "with...Texts." line with this:

```
with the Invariant Sections being LIST THEIR TITLES, with the
Front-Cover Texts being LIST, and with the Back-Cover Texts being LIST.
```

If you have Invariant Sections without Cover Texts, or some other combination of the three, merge those two alternatives to suit the situation.

If your document contains nontrivial examples of program code, we recommend releasing these examples in parallel under your choice of free software license, such as the GNU General Public License, to permit their use in free software.