

# Setting Up a FreeRADIUS Server

## WHAT?

FreeRADIUS is the open source RADIUS server implementation for AAA (Authentication, Authorization, and Accounting).

## WHY?

This article provides a complete overview of the FreeRADIUS server setup and basic FreeRADIUS configuration for testing.

## EFFORT

It takes 15 minutes to install and configure FreeRADIUS. You need up to an hour to fully understand the FreeRADIUS architecture and functionality.

## GOAL

Basic understanding of setting up and testing a FreeRADIUS server.

## REQUIREMENTS

- A virtual machine or instance to install FreeRADIUS.
- Another virtual machine on your network to test client functions.

Publication Date: 12 Dec 2024

## Contents

- 1 The FreeRADIUS concept 3

2	Installing the FreeRADIUS server	4
3	Creating test certificates on the server	4
4	Starting FreeRADIUS on the server	5
5	Adding a test client with a user on the server	5
6	Starting the FreeRADIUS daemon on the server	7
7	Testing authentication on the client	7
8	Troubleshooting FreeRADIUS	8
9	Legal Notice	9
A	GNU Free Documentation License	10

# 1 The FreeRADIUS concept

The RADIUS (Remote Authentication Dial-In User Service) protocol is a standard service for managing network access. FreeRADIUS is the open source RADIUS server implementation and the most widely used RADIUS server.

FreeRADIUS verifies users and clients and manages network access and operations. FreeRADIUS ensures secure communication between network devices and user authentication servers.

FreeRADIUS performs authentication, authorization and accounting (AAA) for very large businesses such as Internet service providers and cellular network providers, and is also popular for small networks. It authenticates users and devices, authorizes those users and devices for certain network services, and tracks the use of services for billing and auditing. You do not have to use all three of the AAA protocols, use only the ones you need.

RADIUS operates over a distributed architecture and runs separately from the Network Access Server (NAS). User access data is stored on a central RADIUS server that is available to multiple NAS devices. The NAS provides physical access to the network, such as a managed Ethernet switch or a wireless access point. FreeRADIUS verifies and manages network access and operations. FreeRADIUS ensures secure communication between network devices and user authentication servers. To set up a FreeRADIUS server, you must install, configure and define user accounts, and define and determine authentication and authorization for FreeRADIUS. After installing FreeRADIUS, you must test the function by integrating FreeRADIUS with the devices to be managed.




FIGURE 1: FREERADIUS ARCHITECTURE

This article includes an example that shows installing FreeRADIUS, creating a set of test certificates, starting the server, adding client server and user, testing authentication, and testing multiple clients.

## 2 Installing the FreeRADIUS server

The following example shows how to install a FreeRADIUS server. Ensure that you install the `freeradius-server` and `freeradius-server-utils` packages on a separate machine from your Network Access Server (NAS).

Install `freeradius-server` and `freeradius-server-utils`.

```
> sudo zypper install freeradius-server and freeradius-server-utils
```

## 3 Creating test certificates on the server

Certificates enable secure communication between the FreeRADIUS clients and the FreeRADIUS server.

To allow access to the server, certificate authentication is required. To test the authentication using FreeRADIUS, you can create test certificates. The following example shows how to create test certificates to test FreeRADIUS. Ensure that you remove the test certificates and use the correct certificates after testing FreeRADIUS.



### Note

The test certificates created are not suitable for production use.

Create a set of test certificates in `/etc/raddb/certs`.

```
> cd /etc/raddb/certs
./bootstrap
```

When you are satisfied with your testing and ready to create a production configuration, remove all the test certificates in `/etc/raddb/certs` and replace them with your own certificates.

## 4 Starting FreeRADIUS on the server

You must start FreeRADIUS on the server after installation.

### PROCEDURE 1: STARTING FREERADIUS

After the bootstrap is complete, start the server in debugging mode as a root user.

- To do this, run the following command:



#### Note

Start the FreeRADIUS server in debugging mode only for testing. Other than for testing, use **sudo systemctl start freeradius**

```
> sudo radiusd -X
[...]
```

Listening on auth address \* port 1812 bound to server default  
Listening on acct address \* port 1813 bound to server default  
Listening on auth address :: port 1812 bound to server default  
Listening on acct address :: port 1813 bound to server default  
Listening on auth address 127.0.0.1 port 18120 bound to server inner-tunnel  
Listening on proxy address \* port 54435  
Listening on proxy address :: port 58415  
Ready to process requests

The Listening and Ready to process requests appear when the server starts correctly.

## 5 Adding a test client with a user on the server

You can add a client and a user to test authentication for the FreeRADIUS server. The client is a client of the RADIUS server, such as a wireless access point or switch. The users are added in the user configuration file and the clients are added in the client configuration file. These configuration files are stored on the server where FreeRADIUS is installed.

The machines that can use the devices of the FreeRADIUS server are defined in the client.conf file.

## PROCEDURE 2: CONFIGURING USERS AND CLIENTS

Add the machines that can use the devices of the FreeRADIUS server and the users by using the following example:

1. Configure users in the authorization file, `/etc/raddb/mods-config/files/authorize`. To do this, open `/etc/raddb/mods-config/files/authorize` and uncomment the following lines:

```
bob   Cleartext-Password := "hello"
      Reply-Message := "Hello, %{User-Name}"

"john" Cleartext-Password := "newpassword"
      Service-Type = New-User,
      Framed-IP-Address = 190.155.2.50
```

2. Add a test client and user to test the authentication in `/etc/raddb/client.conf`.

```
vi /etc/raddb/client.conf
```

A test client, localhost, is provided in `/etc/raddb/client.conf`, with the secret `testing123`.

```
client private-networks {
    ipaddr      = 190.1.0/22
    secret      = testingabc-1
}
client common-network {
    ipaddr      = 191.1.0/27
    secret      = testingxyz
}
```

3. Add clients of the RADIUS server, such as a wireless access point, network switch, or another form of NAS.

Create a client configuration on your server by using the following example.

Uncomment the following entry in `/etc/raddb/client.conf` and use the IP address of your test client machine or access gateway instead of the given IP address.

```
client private-network-1 {
ipaddr      = 192.0.2.0/24
secret      = testing123-1
}
```

You must also configure the client to talk to the RADIUS server by using the IP address of the machine running the RADIUS server. The client must use the same secret as configured above in the client section.

4. On the client machine, install `freeradius-server-utils`.

```
> sudo zypper install freeradius-server and freeradius-server-utils
```

You can now add more users and configure databases.

Run one more login test from a different computer on your network.

## 6 Starting the FreeRADIUS daemon on the server

After adding client and user, you must start the FreeRADIUS daemon.

### PROCEDURE 3: STARTING THE FREERADIUS DAEMON

Start the FreeRADIUS daemon to provide authentication, authorization, and accounting (AAA) services in a network environment for network access control and network access management.

1. Start the FreeRADIUS daemon.

```
> sudo systemctl restart freeradius
```

2. Enable auto-start for FreeRADIUS on system boot up.

```
> sudo systemctl enable freeradius
```

## 7 Testing authentication on the client

You can test the authentication for the newly added user in FreeRADIUS.

### PROCEDURE 4: TESTING AUTHENTICATION

Test the authentication for the newly added user using the following example:

- Open a new terminal, and as an unprivileged user, use the `radtest` command to log in as the newly added user `bob`.

```
> radtest bob hello 127.0.0.1 0 testing123
```

```
Sent Access-Request Id 241 from 0.0.0.0:35234 to 127.0.0.1:1812 length 73
  User-Name = "bob"
  User-Password = "hello"
  NAS-IP-Address = 127.0.0.1
  NAS-Port = 0
  Message-Authenticator = 0x00
  Cleartext-Password = "hello"
Received Access-Accept Id 241 from 127.0.0.1:1812 to 0.0.0.0:0 length 20
```

After the authentication is successful, a login message appears in the terminal in which you started FreeRADIUS, as shown below.

```
(3) pap: Login attempt with password
    (3) pap: Comparing with "known good" Cleartext-Password
    (3) pap: User authenticated successfully
    (3)      [pap] = ok
    [...]
    (3) Sent Access-Accept Id 241 from 127.0.0.1:1812 to 127.0.0.1:35234
length 0
    (3) Finished request
    Waking up in 4.9 seconds.
    (3) Cleaning up request packet ID 241 with timestamp +889
```

The access request is successful and the authentication methods PAP, CHAP, MS-CHAPv1, MS-CHAPv2, PEAP, EAP-TTLS, EAP-GTC, EAP-MD5 work for the user bob.

## 8 Troubleshooting FreeRADIUS

There are several test users and test clients provided. Ensure that your server has the correct firewall settings. If your test logins fail, review all the output to understand the issues.

Possible troubleshooting methods are given below:

- Check FreeRADIUS logs in `/var/log/freeradius/radius.log` or `/var/log/radius/radius.log`.
- Check if FreeRADIUS is running.

```
systemctl status freeradius
```

If FreeRADIUS is not running, start FreeRADIUS.

```
systemctl start freeradius
```

If a FreeRADIUS server is already running, an error `Address already in use` appears. Stop that server before running the server in debugging mode.

If the server does not start, verify the output. The output includes the details about the errors. You can direct the output to a text file with `tee`:

```
radiusd -X | tee radiusd.text
```

- Check if the ports for FreeRADIUS in the firewall are open for communication.
- Check user authentication.

```
radtest username password localhost 0 testing123
```

- Verify client configuration. Ensure that the secret and IP in the client and the FreeRADIUS server match.
- Update FreeRADIUS software. Ensure that you use the latest stable version of FreeRADIUS.

When you are satisfied with your testing and ready to create a production configuration, remove all the test certificates in `/etc/raddb/certs` and replace them with your own certificates, comment out all the test users and clients, and stop `radiusd` by pressing `Ctrl-C`. Manage the `radiusd.service` with `systemctl`, just like any other service.

## 9 Legal Notice

Copyright© 2006–2024 SUSE LLC and contributors. All rights reserved.

Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.2 or (at your option) version 1.3; with the Invariant Section being this copyright notice and license. A copy of the license version 1.2 is included in the section entitled “GNU Free Documentation License”.

For SUSE trademarks, see <https://www.suse.com/company/legal/>. All other third-party trademarks are the property of their respective owners. Trademark symbols (®, ™ etc.) denote trademarks of SUSE and its affiliates. Asterisks (\*) denote third-party trademarks.

All information found in this book has been compiled with utmost attention to detail. However, this does not guarantee complete accuracy. Neither SUSE LLC, its affiliates, the authors, nor the translators shall be held liable for possible errors or the consequences thereof.

# A GNU Free Documentation License

Copyright (C) 2000, 2001, 2002 Free Software Foundation, Inc. 51 Franklin St, Fifth Floor, Boston, MA 02110-1301 USA. Everyone is permitted to copy and distribute verbatim copies of this license document, but changing it is not allowed.

## 0. PREAMBLE

The purpose of this License is to make a manual, textbook, or other functional and useful document "free" in the sense of freedom: to assure everyone the effective freedom to copy and redistribute it, with or without modifying it, either commercially or non-commercially. Secondly, this License preserves for the author and publisher a way to get credit for their work, while not being considered responsible for modifications made by others.

This License is a kind of "copyleft", which means that derivative works of the document must themselves be free in the same sense. It complements the GNU General Public License, which is a copyleft license designed for free software.

We have designed this License to use it for manuals for free software, because free software needs free documentation: a free program should come with manuals providing the same freedoms that the software does. But this License is not limited to software manuals; it can be used for any textual work, regardless of subject matter or whether it is published as a printed book. We recommend this License principally for works whose purpose is instruction or reference.

## 1. APPLICABILITY AND DEFINITIONS

This License applies to any manual or other work, in any medium, that contains a notice placed by the copyright holder saying it can be distributed under the terms of this License. Such a notice grants a world-wide, royalty-free license, unlimited in duration, to use that work under the conditions stated herein. The "Document", below, refers to any such manual or work. Any member of the public is a licensee, and is addressed as "you". You accept the license if you copy, modify or distribute the work in a way requiring permission under copyright law.

A "Modified Version" of the Document means any work containing the Document or a portion of it, either copied verbatim, or with modifications and/or translated into another language.

A "Secondary Section" is a named appendix or a front-matter section of the Document that deals exclusively with the relationship of the publishers or authors of the Document to the Document's overall subject (or to related matters) and contains nothing that could fall directly within that

overall subject. (Thus, if the Document is in part a textbook of mathematics, a Secondary Section may not explain any mathematics.) The relationship could be a matter of historical connection with the subject or with related matters, or of legal, commercial, philosophical, ethical or political position regarding them.

The "Invariant Sections" are certain Secondary Sections whose titles are designated, as being those of Invariant Sections, in the notice that says that the Document is released under this License. If a section does not fit the above definition of Secondary then it is not allowed to be designated as Invariant. The Document may contain zero Invariant Sections. If the Document does not identify any Invariant Sections then there are none.

The "Cover Texts" are certain short passages of text that are listed, as Front-Cover Texts or Back-Cover Texts, in the notice that says that the Document is released under this License. A Front-Cover Text may be at most 5 words, and a Back-Cover Text may be at most 25 words.

A "Transparent" copy of the Document means a machine-readable copy, represented in a format whose specification is available to the general public, that is suitable for revising the document straightforwardly with generic text editors or (for images composed of pixels) generic paint programs or (for drawings) some widely available drawing editor, and that is suitable for input to text formatters or for automatic translation to a variety of formats suitable for input to text formatters. A copy made in an otherwise Transparent file format whose markup, or absence of markup, has been arranged to thwart or discourage subsequent modification by readers is not Transparent. An image format is not Transparent if used for any substantial amount of text. A copy that is not "Transparent" is called "Opaque".

Examples of suitable formats for Transparent copies include plain ASCII without markup, Texinfo input format, LaTeX input format, SGML or XML using a publicly available DTD, and standard-conforming simple HTML, PostScript or PDF designed for human modification. Examples of transparent image formats include PNG, XCF and JPG. Opaque formats include proprietary formats that can be read and edited only by proprietary word processors, SGML or XML for which the DTD and/or processing tools are not generally available, and the machine-generated HTML, PostScript or PDF produced by some word processors for output purposes only.

The "Title Page" means, for a printed book, the title page itself, plus such following pages as are needed to hold, legibly, the material this License requires to appear in the title page. For works in formats which do not have any title page as such, "Title Page" means the text near the most prominent appearance of the work's title, preceding the beginning of the body of the text.

A section "Entitled XYZ" means a named subunit of the Document whose title either is precisely XYZ or contains XYZ in parentheses following text that translates XYZ in another language. (Here XYZ stands for a specific section name mentioned below, such as "Acknowledgements", "Dedications", "Endorsements", or "History".) To "Preserve the Title" of such a section when you modify the Document means that it remains a section "Entitled XYZ" according to this definition. The Document may include Warranty Disclaimers next to the notice which states that this License applies to the Document. These Warranty Disclaimers are considered to be included by reference in this License, but only as regards disclaiming warranties: any other implication that these Warranty Disclaimers may have is void and has no effect on the meaning of this License.

## 2. VERBATIM COPYING

You may copy and distribute the Document in any medium, either commercially or non-commercially, provided that this License, the copyright notices, and the license notice saying this License applies to the Document are reproduced in all copies, and that you add no other conditions whatsoever to those of this License. You may not use technical measures to obstruct or control the reading or further copying of the copies you make or distribute. However, you may accept compensation in exchange for copies. If you distribute a large enough number of copies you must also follow the conditions in section 3.

You may also lend copies, under the same conditions stated above, and you may publicly display copies.

## 3. COPYING IN QUANTITY

If you publish printed copies (or copies in media that commonly have printed covers) of the Document, numbering more than 100, and the Document's license notice requires Cover Texts, you must enclose the copies in covers that carry, clearly and legibly, all these Cover Texts: Front-Cover Texts on the front cover, and Back-Cover Texts on the back cover. Both covers must also clearly and legibly identify you as the publisher of these copies. The front cover must present the full title with all words of the title equally prominent and visible. You may add other material on the covers in addition. Copying with changes limited to the covers, as long as they preserve the title of the Document and satisfy these conditions, can be treated as verbatim copying in other respects.

If the required texts for either cover are too voluminous to fit legibly, you should put the first ones listed (as many as fit reasonably) on the actual cover, and continue the rest onto adjacent pages.

If you publish or distribute Opaque copies of the Document numbering more than 100, you must either include a machine-readable Transparent copy along with each Opaque copy, or state in or with each Opaque copy a computer-network location from which the general network-using public has access to download using public-standard network protocols a complete Transparent copy of the Document, free of added material. If you use the latter option, you must take reasonably prudent steps, when you begin distribution of Opaque copies in quantity, to ensure that this Transparent copy will remain thus accessible at the stated location until at least one year after the last time you distribute an Opaque copy (directly or through your agents or retailers) of that edition to the public.

It is requested, but not required, that you contact the authors of the Document well before redistributing any large number of copies, to give them a chance to provide you with an updated version of the Document.

#### 4. MODIFICATIONS

You may copy and distribute a Modified Version of the Document under the conditions of sections 2 and 3 above, provided that you release the Modified Version under precisely this License, with the Modified Version filling the role of the Document, thus licensing distribution and modification of the Modified Version to whoever possesses a copy of it. In addition, you must do these things in the Modified Version:

- A. Use in the Title Page (and on the covers, if any) a title distinct from that of the Document, and from those of previous versions (which should, if there were any, be listed in the History section of the Document). You may use the same title as a previous version if the original publisher of that version gives permission.
- B. List on the Title Page, as authors, one or more persons or entities responsible for authorship of the modifications in the Modified Version, together with at least five of the principal authors of the Document (all of its principal authors, if it has fewer than five), unless they release you from this requirement.
- C. State on the Title page the name of the publisher of the Modified Version, as the publisher.
- D. Preserve all the copyright notices of the Document.

- E. Add an appropriate copyright notice for your modifications adjacent to the other copyright notices.
- F. Include, immediately after the copyright notices, a license notice giving the public permission to use the Modified Version under the terms of this License, in the form shown in the Addendum below.
- G. Preserve in that license notice the full lists of Invariant Sections and required Cover Texts given in the Document's license notice.
- H. Include an unaltered copy of this License.
- I. Preserve the section Entitled "History", Preserve its Title, and add to it an item stating at least the title, year, new authors, and publisher of the Modified Version as given on the Title Page. If there is no section Entitled "History" in the Document, create one stating the title, year, authors, and publisher of the Document as given on its Title Page, then add an item describing the Modified Version as stated in the previous sentence.
- J. Preserve the network location, if any, given in the Document for public access to a Transparent copy of the Document, and likewise the network locations given in the Document for previous versions it was based on. These may be placed in the "History" section. You may omit a network location for a work that was published at least four years before the Document itself, or if the original publisher of the version it refers to gives permission.
- K. For any section Entitled "Acknowledgements" or "Dedications", Preserve the Title of the section, and preserve in the section all the substance and tone of each of the contributor acknowledgements and/or dedications given therein.
- L. Preserve all the Invariant Sections of the Document, unaltered in their text and in their titles. Section numbers or the equivalent are not considered part of the section titles.
- M. Delete any section Entitled "Endorsements". Such a section may not be included in the Modified Version.
- N. Do not retitle any existing section to be Entitled "Endorsements" or to conflict in title with any Invariant Section.
- O. Preserve any Warranty Disclaimers.

If the Modified Version includes new front-matter sections or appendices that qualify as Secondary Sections and contain no material copied from the Document, you may at your option designate some or all of these sections as invariant. To do this, add their titles to the list of Invariant Sections in the Modified Version's license notice. These titles must be distinct from any other section titles.

You may add a section Entitled "Endorsements", provided it contains nothing but endorsements of your Modified Version by various parties--for example, statements of peer review or that the text has been approved by an organization as the authoritative definition of a standard.

You may add a passage of up to five words as a Front-Cover Text, and a passage of up to 25 words as a Back-Cover Text, to the end of the list of Cover Texts in the Modified Version. Only one passage of Front-Cover Text and one of Back-Cover Text may be added by (or through arrangements made by) any one entity. If the Document already includes a cover text for the same cover, previously added by you or by arrangement made by the same entity you are acting on behalf of, you may not add another; but you may replace the old one, on explicit permission from the previous publisher that added the old one.

The author(s) and publisher(s) of the Document do not by this License give permission to use their names for publicity for or to assert or imply endorsement of any Modified Version.

## 5. COMBINING DOCUMENTS

You may combine the Document with other documents released under this License, under the terms defined in section 4 above for modified versions, provided that you include in the combination all of the Invariant Sections of all of the original documents, unmodified, and list them all as Invariant Sections of your combined work in its license notice, and that you preserve all their Warranty Disclaimers.

The combined work need only contain one copy of this License, and multiple identical Invariant Sections may be replaced with a single copy. If there are multiple Invariant Sections with the same name but different contents, make the title of each such section unique by adding at the end of it, in parentheses, the name of the original author or publisher of that section if known, or else a unique number. Make the same adjustment to the section titles in the list of Invariant Sections in the license notice of the combined work.

In the combination, you must combine any sections Entitled "History" in the various original documents, forming one section Entitled "History"; likewise combine any sections Entitled "Acknowledgements", and any sections Entitled "Dedications". You must delete all sections Entitled "Endorsements".

## 6. COLLECTIONS OF DOCUMENTS

You may make a collection consisting of the Document and other documents released under this License, and replace the individual copies of this License in the various documents with a single copy that is included in the collection, provided that you follow the rules of this License for verbatim copying of each of the documents in all other respects.

You may extract a single document from such a collection, and distribute it individually under this License, provided you insert a copy of this License into the extracted document, and follow this License in all other respects regarding verbatim copying of that document.

## 7. AGGREGATION WITH INDEPENDENT WORKS

A compilation of the Document or its derivatives with other separate and independent documents or works, in or on a volume of a storage or distribution medium, is called an "aggregate" if the copyright resulting from the compilation is not used to limit the legal rights of the compilation's users beyond what the individual works permit. When the Document is included in an aggregate, this License does not apply to the other works in the aggregate which are not themselves derivative works of the Document.

If the Cover Text requirement of section 3 is applicable to these copies of the Document, then if the Document is less than one half of the entire aggregate, the Document's Cover Texts may be placed on covers that bracket the Document within the aggregate, or the electronic equivalent of covers if the Document is in electronic form. Otherwise they must appear on printed covers that bracket the whole aggregate.

## 8. TRANSLATION

Translation is considered a kind of modification, so you may distribute translations of the Document under the terms of section 4. Replacing Invariant Sections with translations requires special permission from their copyright holders, but you may include translations of some or all Invariant Sections in addition to the original versions of these Invariant Sections. You may include a translation of this License, and all the license notices in the Document, and any Warranty Disclaimers, provided that you also include the original English version of this License and the original versions of those notices and disclaimers. In case of a disagreement between the translation and the original version of this License or a notice or disclaimer, the original version will prevail.

If a section in the Document is Entitled "Acknowledgements", "Dedications", or "History", the requirement (section 4) to Preserve its Title (section 1) will typically require changing the actual title.

## 9. TERMINATION

You may not copy, modify, sublicense, or distribute the Document except as expressly provided for under this License. Any other attempt to copy, modify, sublicense or distribute the Document is void, and will automatically terminate your rights under this License. However, parties who have received copies, or rights, from you under this License will not have their licenses terminated so long as such parties remain in full compliance.

## 10. FUTURE REVISIONS OF THIS LICENSE

The Free Software Foundation may publish new, revised versions of the GNU Free Documentation License from time to time. Such new versions will be similar in spirit to the present version, but may differ in detail to address new problems or concerns. See <https://www.gnu.org/copyleft/>.

Each version of the License is given a distinguishing version number. If the Document specifies that a particular numbered version of this License "or any later version" applies to it, you have the option of following the terms and conditions either of that specified version or of any later version that has been published (not as a draft) by the Free Software Foundation. If the Document does not specify a version number of this License, you may choose any version ever published (not as a draft) by the Free Software Foundation.

## ADDENDUM: How to use this License for your documents

```
Copyright (c) YEAR YOUR NAME.  
Permission is granted to copy, distribute and/or modify this document  
under the terms of the GNU Free Documentation License, Version 1.2  
or any later version published by the Free Software Foundation;  
with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts.  
A copy of the license is included in the section entitled "GNU  
Free Documentation License".
```

If you have Invariant Sections, Front-Cover Texts and Back-Cover Texts, replace the “with...Texts.” line with this:

```
with the Invariant Sections being LIST THEIR TITLES, with the
Front-Cover Texts being LIST, and with the Back-Cover Texts being LIST.
```

If you have Invariant Sections without Cover Texts, or some other combination of the three, merge those two alternatives to suit the situation.

If your document contains nontrivial examples of program code, we recommend releasing these examples in parallel under your choice of free software license, such as the GNU General Public License, to permit their use in free software.