

SUSE Linux Enterprise Server 15 SP1

安装快速入门

SUSE Linux Enterprise Server 15 SP1

本《快速入门》引导您逐步完成安装 SUSE® Linux Enterprise Server 15 SP1 的过程。

出版日期： September 29, 2024

目录

- 1 欢迎安装 SUSE Linux Enterprise Server 2
- 2 法律声明 28
- 3 GNU Free Documentation License 29

1 欢迎安装 SUSE Linux Enterprise Server

执行以下过程可在所有支持的硬件平台上安装本产品。这些过程假设您已成功引导进入/通过 IPL 进入安装系统。有关更详细的安装指导和部署策略，请参见《部署指南》。有关为了引导进入或通过 IPL 进入安装系统而需在特定平台上完成的准备工作，请参见前面所述指南的以下部分：

- 《部署指南》，第 2 章 “在 AMD64 和 Intel 64 上安装”
- 《部署指南》，第 3 章 “在 ARM AArch64 上安装”
- 《部署指南》，第 4 章 “在 IBM POWER 上安装”
- 《部署指南》，第 5 章 “在 IBM Z 上安装”

1.1 默认安装过程

从 SUSE Linux Enterprise Server 15 开始，安装媒体仅包含安装程序 - 一个用于安装、更新和注册 SUSE Linux Enterprise Server 的基于命令行的精简系统。在安装期间，您可以通过选择要基于安装程序安装的模块来添加功能。

默认的安装方式需要通过网络访问 SUSE Customer Center 或本地储存库镜像工具服务器，以检索模块的储存库数据。如果您想在不访问网络的情况下执行安装，还需要另一个安装媒体 “SLE-15-SP1-Packages 映像”。

要安装 SUSE Linux Enterprise Server，请从安装程序媒体引导进入或通过 IPL 进入安装程序，然后开始安装。

1.1.1.1 语言、键盘和产品选择



语言和键盘布局设置会根据您在引导屏幕上选择的语言进行初始化。如果您之前未更改默认设置，则语言为“英语（美国）”。如果需要，可在此处更改设置。使用键盘测试文本框可测试布局。


使用安装程序可以安装所有 SUSE Linux Enterprise 基础产品：

- SUSE Linux Enterprise Server 15 SP1（本文档已介绍）
- SUSE Linux Enterprise Desktop 15 SP1（参见 <https://www.suse.com/documentation/sled/> 中的安装指导）
- SUSE Linux Enterprise High Performance Computing 15 SP1
- SUSE Linux Enterprise Real Time 15 SP1（参见 <https://www.suse.com/documentation/slerte/> 中的安装指导）

- SUSE Linux Enterprise Server for SAP Applications 15 SP1 (参见 <https://www.suse.com/documentation/sles-for-sap/> 中的安装指导)
- SUSE Manager Server 4.0 (参见 <https://www.suse.com/documentation/suse-manager/> 中的安装指导)
- SUSE Manager Proxy 4.0 (参见 <https://www.suse.com/documentation/suse-manager/> 中的安装指导)
- SUSE Manager Retail Branch Server 4.0 (参见 <https://www.suse.com/documentation/suse-manager-for-retail/> 中的安装指导)


选择要安装的产品。您需有相应产品的注册代码。整篇文档假设您已选择 SUSE Linux Enterprise Server。单击下一步继续。

1.1.2 许可协议



阅读许可协议。此内容以您在引导屏幕上选择的语言显示。可以通过许可证语言下拉框获取翻译。您需要选中我接受许可证条款接受该协议，才能安装 SUSE Linux Enterprise Server。单击下一步继续。

1.1.3 网络设置



随后会进行系统分析，在此过程中，安装程序会探测储存设备，并尝试查找其他安装的系统。如果在开始安装期间已通过 DHCP 自动配置了网络，您将转到注册步骤。

如果尚未配置网络，则网络设置对话框将会打开。从列表中选择网络接口，然后使用编辑对其进行配置。也可以手动添加一个接口。有关详细信息，请参见《部署指南》，第 8 章“安装步骤”，第 8.6 节“网络设置”和《管理指南》，第 17 章“基本联网知识”，第 17.4 节“使用 YaST 配置网络连接”。如果您希望在不访问网络的情况下执行安装，请不做任何更改跳过此步骤，然后单击下一步继续。


1.1.4 IBM Z: 磁盘激活

如果不是在 IBM Z 硬件上安装，请跳过此步骤。



配置挂接的硬盘。选择 DASD、光纤通道挂接式 SCSI 磁盘 (zFCP) 或 iSCSI 来安装 SUSE Linux Enterprise Server。DASD 和 zFCP 配置按钮仅在挂接了相应设备时方可使用。单击下一步继续设置选定的磁盘类型。

1.1.5 注册



The image shows the registration screen for SUSE Linux Enterprise Server 15 SP1. The screen has a dark background with the SUSE logo in the top left. In the top right corner, there is a button labeled "网络配置 (w) ...". The main heading "注册" (Registration) is displayed in large green characters. Below it, the text "SUSE Linux Enterprise Server 15 SP1" and "请选择您首选的注册方法。" (Please select your preferred registration method.) are shown. There are three radio button options: 1. "通过 scc.suse.com 注册系统" (Register system via scc.suse.com) with sub-fields for "电子邮件地址 (E)" (Email address) and "注册码 (C)" (Registration code). 2. "Register System via local SMT Server" with a sub-field "本地注册服务器 URL (L)" (Local registration server URL) containing a dropdown menu with "https://smt.example.com". 3. "跳过注册 (s)" (Skip registration). At the bottom, there are three buttons: "帮助 (h)" (Help), "中止 (R)" (Abort), and "下一步 (N)" (Next).

要获取技术支持和产品更新，需要在 SUSE Customer Center 或本地注册服务器中注册并激活产品。在此阶段注册 SUSE Linux Enterprise Server 可让您立即获得访问更新储存库的权限。如此，您便可以将最新的更新和可用增补程序随系统一起安装。

注册时，将从注册服务器装载您下一步可能会安装的模块和扩展的储存库与依赖项。

如果您处于脱机状态，或想跳过注册，请激活跳过注册。遵照第 1.2 节 “安装但不注册” 中的指导继续安装。


要注册到 SUSE Customer Center 中，请输入与您的 SCC 帐户关联的电子邮件地址，以及 SUSE Linux Enterprise Server 的注册代码。如果您的组织提供了本地注册服务器，您也可以在该服务器中注册。激活通过本地 SMT 服务器注册系统，然后从下拉框中选择 URL，或者键入地址。



提示：在安装时安装产品增补程序

成功注册 SUSE Linux Enterprise Server 后，系统会在安装期间询问您是否安装最新的可用联机更新。如果您选择是，最新的包将随系统一起安装，如此便不必在安装后应用更新。建议激活此选项。

1.1.6 扩展和模块选择



成功注册系统后，安装程序会列出适用于 SUSE Linux Enterprise Server 的模块和扩展。模块是用于根据需要定制产品功能的组件。它们是免费提供的。扩展可在产品中添加功能。它们以订阅的形式提供，需要注册密钥，因此需付费才能使用。

有哪些模块或扩展可用取决于您在安装的第一步中选择的产品。有关模块及其生命周期的说明，请选择一个模块查看附带的文本。《《Modules and Extensions Quick Start》文章》和[发行说明 \(https://www.suse.com/releases/notes/x86_64/SUSE-SLES/15/#Intro.Module\)](https://www.suse.com/releases/notes/x86_64/SUSE-SLES/15/#Intro.Module) 中提供了更多详细信息。

模块的选择会间接影响安装范围，因为该选择定义了哪些软件源（储存库）可用于安装，以及可用于运行中的系统。

以下模块和扩展适用于 SUSE Linux Enterprise Server：

Basesystem 模块

此模块在安装程序的基础上添加一个基本系统。其他所有模块和扩展都需要此模块。只包含基础系统的安装其范围相当于旧版 SUSE Linux Enterprise Server 的最小系统安装模式。系统默认已选择安装此模块，不应将其取消选择。

依赖项：无

Containers 模块

包含容器的支持和工具。

依赖项：Basesystem

Desktop Applications 模块

向系统添加图形用户界面和最基本的桌面应用程序。

依赖项：Basesystem

Development Tools 模块

包含编译器（包括 `gcc`）以及编译和调试应用程序所需的库。取代了以前的 Software Development Kit (SDK)。

依赖项：Basesystem、Desktop Applications

Legacy 模块

包含旧版 SUSE Linux Enterprise Server 中提供的，但 SLES 15 SP1 中已弃用的包。从旧版产品迁移时，建议使用此模块。

依赖项：Basesystem、Server Applications

Public Cloud 模块

包含创建映像所需的全部工具，这些映像用于在云环境（例如 Amazon Web Services (AWS)、Microsoft Azure、Google Compute Platform 或 SUSE OpenStack Cloud）中部署 SUSE Linux Enterprise Server。

依赖项：Basesystem、Server Applications

Python 2 模块

SUSE Linux Enterprise 15 SP 1 使用 Python 版本 3。此模块包含 Python 2 运行时与模块。

依赖项：Basesystem

Server Applications Module

通过提供 DHCP 服务器、名称服务器或 Web 服务器等网络服务来添加服务器功能。系统默认已选择安装此模块；不建议将其取消选择。

依赖项：Basesystem

SUSE Cloud Application Platform Tools 模块

添加用来与 SUSE Cloud Application Platform 产品交互的工具。

依赖项：Basesystem

SUSE Enterprise Storage

向 SUSE Linux Enterprise Server 添加 Ceph 的分布式储存支持。需要单独的许可证密钥。

依赖项：Basesystem、Server Applications

SUSE Linux Enterprise High Availability Extension

向 SUSE Linux Enterprise Server 添加任务关键型设置的群集支持。此扩展需要单独的许可证密钥。

依赖项：Basesystem、Server Applications

SUSE Linux Enterprise Live Patching

添加无需关闭系统即可执行关键增补的支持。此扩展需要单独的许可证密钥。


依赖项：Basesystem、Server Applications

SUSE Linux Enterprise Workstation Extension

使用 SUSE Linux Enterprise Desktop 中与其他桌面应用程序（如办公套件、电子邮件客户端、图形编辑器等）类似的包和库，扩展 SUSE Linux Enterprise Server 的功能。使用该扩展可以将这两个产品相结合来打造功能完备的工作站。此扩展需要单独的许可证密钥。

依赖项：Basesystem、Desktop Applications

SUSE Package Hub

用于访问 openSUSE 社区维护的各个 SUSE Linux Enterprise Server 包。提供的这些包没有 L3 支持，且不影响 SUSE Linux Enterprise Server 的支持。有关详细信息，请参见 <https://packagehub.suse.com/> 。

依赖项：Basesystem

Transactional Server 模块

添加了对事务更新的支持。更新将以单个事务的形式统一应用到系统，或者全部都不应用。这种方式不会影响正在运行的系统。如果某项更新失败，或者成功应用的更新被视为不兼容或者存在其他错误，可以丢弃该更新，使系统立即恢复到以前的正常运行状态。

依赖项：Basesystem

Web and Scripting 模块

包含用于运行中 Web 服务器的包。

依赖项：Basesystem、Server Applications

某些模块需要已安装其他模块。因此，在选择某个模块时，可能会自动选择其他模块来满足依赖关系。

根据具体的产品，注册服务器可能会将模块和扩展标记为建议安装。系统会将建议的模块和扩展预先选为要加以注册和安装。如要避免安装这些建议的项目，请手动取消选择。

选择要安装的模块和扩展，然后单击下一步继续。如果您选择了一个或多个扩展，系统会提示您提供相应的注册代码。根据所做的选择，您可能还需要接受附加的许可协议。

1.1.7 附加产品



附加产品对话框可让您向 SUSE Linux Enterprise Server 添加不是由 SUSE Customer Center 提供的其他软件源（即“储存库”）。此类附加产品可以包括第三方产品和驱动程序，或适用于您系统的其他软件。



提示：在安装过程中添加驱动程序

您还可以通过附加产品对话框添加驱动程序更新储存库。<http://drivers.suse.com/> 上会提供 SUSE Linux Enterprise 的驱动程序更新。这些驱动程序已通过 SUSE SolidDriver Program 创建。

如果要跳过此步骤，请单击下一步继续。否则，请激活我要安装附加产品。请指定媒体类型、本地路径或托管储存库的网络资源，然后按照屏幕上的指导操作。

选中下载安装源描述文件可立即下载用于描述安装源的文件。如果不激活，系统将在安装启动后下载它们。单击下一步继续，并根据需要插入媒体。根据产品内容，可能必须接受附加许可协议。单击下一步继续。如果您选择了需要注册密钥的附加产品，在继续下一步之前，系统会要求您输入该密钥。

1.1.8 系统角色




可用的系统角色取决于所选的模块和扩展。例如，系统角色定义分区建议，以及要预先选定加以安装的软件模式集。请参考屏幕上的说明做出选择。选择角色，然后单击下一步继续。



提示：发行说明

从此步骤开始，可以通过选择发行说明在安装过程中的任一屏幕上查看发行说明。

1.1.9 建议的分区



查看系统建议的分区设置。如果需要，可以更改它们。您可以选择以下选项：

指导设置

启动可用来优化分区建议的向导。此处可用的选项取决于系统设置。如果系统包含多个硬盘，则您可以选择要使用哪个磁盘，以及要将根分区放到哪个位置。如果磁盘已包含分区，请决定是要去除分区还是调整分区的大小。

在后续步骤中，您还可以添加 LVM 支持和磁盘加密。您可以更改根分区的文件系统，并决定是否创建单独的主分区。

专家分区程序

打开专家分区程序，如《部署指南》，第 10 章“专家分区程序”，第 10.1 节“使用专家分区程序”中所述。此选项可让您完全控制分区设置，以及创建自定义设置。它面向的是专家用户。


要接受建议的设置而不做任何改动，请选择下一步继续。



提示：发行说明

从此步骤开始，可以通过选择发行说明在安装过程中的任一屏幕上查看发行说明。

1.1.10 时钟和时区



选择系统使用的时钟和时区。要手动调整时间或配置 NTP 服务器以保持时间的同步，请选择其他设置。有关详细信息，请参见《部署指南》，第 8 章“安装步骤”，第 8.12 节“时钟和时区”。单击下一步继续。

1.1.11 本地用户

要创建本地用户，请在用户的完整名称字段中输入姓氏和名称，在用户名字段中输入登录名，在口令字段中输入口令。

口令至少为 8 个字符，而且应包含大小写字母及数字。口令最长为 72 个字符，区分大小写。


出于安全考虑，强烈建议您不要启用自动登录。此外，也不应对系统管理员使用此口令，而应在安装的下一步中提供一个单独的 root 口令。

如果在包含旧版 Linux 安装的系统上安装，您可以从旧版安装导入用户数据。单击选择用户查看可用用户帐户的列表。选择一个或多个用户。

在集中管理用户的环境中（例如，通过 NIS 或 LDAP 进行管理），您可能想要跳过本地用户的创建过程。在这种情况下，请选择跳过用户创建。

单击下一步继续。

1.1.12 系统管理员 “root” 的身份验证



The screenshot shows the SUSE installer interface for the root user authentication step. The title is "系统管理员 'root' 的认证口令" (Authentication password for system administrator 'root'). The interface includes a warning "请不要忘记在此输入的内容。" (Don't forget the content entered here.), three input fields for "root 用户的口令 (P)", "确认口令 (P)", and "测试键盘布局 (T)", and a section for "导入 SSH 公钥" (Import SSH public key) with a dropdown menu showing "QEMU DVD-ROM (/dev/sr0)" and buttons for "刷新 (R)" and "浏览 (W) ...". At the bottom, there are buttons for "帮助 (H)", "发行说明 (L) ...", "中止 (R)", "后退 (B)", and "下一步 (N)".

键入系统管理员（称为 root 用户）的口令，或者提供公共 SSH 密钥。如果需要，您也可以同时使用这两种身份凭证。

由于 root 用户配备了众多的权限，因此请慎重选择口令。千万不要忘记 root 口令！您在此处输入之后，就不能检索该口令。




提示：口令和键盘布局

建议您只使用英语键盘上可用的字符。如果发生系统错误，或者您需要以救援模式启动系统时，本地化键盘可能会无法使用。

在某些情况下，最好是使用公共密钥通过 SSH 远程访问系统。在此屏幕中，您可以从 USB 记忆棒、CD/DVD ROM 甚至现有的分区中选择公共密钥（文件扩展名为 `.pub`）。有关详细信息，请参见《部署指南》，第 8 章“安装步骤”，第 8.14 节“系统管理员“root”的身份验证”。也可以稍后再添加公共 SSH 密钥（请参见《部署指南》，第 8 章“安装步骤”，第 8.14 节“系统管理员“root”的身份验证”，添加 root 用户的公共 SSH 密钥）。

单击下一步继续。

1.1.13 安装设置



使用安装设置屏幕查看并根据需要更改若干建议的安装设置。每个设置的当前配置都在此处列出。要进行更改，请单击标题。有些设置（如防火墙或 SSH）可以直接通过单击相应链接更改。



提示：远程访问

此处可更改的设置也可以日后在安装的系统中加以更改。但是，如果您在安装后需要马上进行远程访问，此时应该检查防火墙和 SSH 设置。

软件

安装范围由为此安装选择的模块和扩展定义。但是，根据您所做的选择，不一定会选中模块中提供的所有包加以安装。

单击软件会打开软件选择和系统任务屏幕，您可在此处选择或取消选择某些模式来更改软件选择。每个模式都包含特定功能（例如 KVM 主机服务器）所需的几个软件包。如果想查看要安装软件包的更为详细的选择，请选择细节切换到 YaST 软件管理器。有关详细信息，请参见《部署指南》，第 17 章“安装或删除软件”。

引导

此部分显示引导加载程序配置。建议您仅在确实需要时才更改默认设置。有关详细信息，请参见《管理指南》，第 12 章“引导加载程序 GRUB 2”。

防火墙和 SSH

默认情况下，系统会对为公共区域配置的所有网络接口启用防火墙。有关配置细节，请参见《Security and Hardening Guide》，第 22 章“Masquerading and Firewalls”，第 22.4 节“firewalld”。

SSH 服务默认处于启用状态，其端口 (22) 已打开。单击启用并打开可切换这些设置。请注意，如果 SSH 已禁用，则无法远程登录。

Kdump

如果发生内核崩溃，Kdump 可将内存映像（“内核转储”）保存到文件系统中。如此，您便可以通过调试转储文件来查找崩溃原因。Kdump 已预先配置好，默认处于启用状态。有关详细信息，请参见《System Analysis and Tuning Guide》，第 17 章“Kexec and Kdump”，第 17.7 节“Basic Kdump Configuration”。


默认 Systemd 目标

如果您已安装 Desktop Applications 模块，系统会引导进入支持网络、多用户和显示管理器的图形目标。如果您不需要通过显示管理器登录，请切换到多用户。

系统

单击系统可查看详细的硬件信息。在随后显示的屏幕中，还可以更改内核设置，有关更多信息，请参见《部署指南》，第 8 章 “安装步骤”，第 8.15.8 节 “系统”。

1.1.14 开始安装



在安装设置屏幕上确定了系统配置后，单击安装。根据您做的软件选择，您可能需要同意许可协议，安装确认屏幕才会弹出。到目前为止，我们还未对您的系统进行任何更改。当您再次单击安装后，安装过程即会开始。

1.1.15 安装过程



安装期间，细节选项卡中会显示详细的安装进度。SUSE Linux Enterprise Server 发行说明选项卡显示了重要信息；建议阅读这些信息。

安装例程完成后，计算机会重引导至安装的系统。登录并启动 YaST 以微调系统。如果您使用的不是图形桌面或者正通过远程方式工作，请参考《管理指南》，第 5 章“文本方式的 YaST”获得有关从终端使用 YaST 的信息。

1.2 安装但不注册

如果您在执行安装时未连接到注册服务器，则无法在安装期间注册您的系统。因而将无法从注册服务器接收模块和扩展的储存库配置。为了支持常规安装，SUSE 还提供了另一个安装媒体：SLE-15-SP1-Packages 映像。



注意：注册 SUSE Linux Enterprise Server

需要注册您的系统和扩展才能检索更新以及获得支持资格。如果在安装期间未注册，以后随时可以从运行中的系统上注册。要进行此操作，请运行 YaST > 产品注册。

要执行安装但不注册，请确保安装期间可以访问 SLE-15-SP1-Packages 映像的内容。将此映像复制到本地硬盘或可卸闪存盘，或者放置在本地网络中，即可实现此目的。请选择您的硬件支持的一种方法。



提示：将 SLE-15-SP1-Packages 映像中的数据复制到可卸闪存盘

要将该映像的内容复制到可卸闪存盘，请使用以下命令。

```
tux > sudo dd if=PATH_TO_IMAGE  
of=FLASH_STORAGE_PARTITION bs=4M && sync
```

需将 `PATH_TO_IMAGE` 替换为此映像文件的相对或绝对路径。需将 `FLASH_STORAGE_PARTITION` 替换为闪存设备上某个分区（通常只有一个）的路径。要识别设备及其分区，请插入设备，并使用下面的示例中所示的命令：

```
root # grep -Ff <(hwinfo --disk --short) <(hwinfo --usb --short)  
disk:  
    /dev/sdc                General USB Flash Disk  
root # fdisk -l /dev/sdc | grep -e "^/dev"  
/dev/sdc1 *                2048 31490047 31488000 15G 83 Linux
```

例如，在这种情况下，要使用的命令是：

```
dd if=/tmp/SLE-15-SP1-Packages-x86_64-DVD1.iso \  
of=/dev/sdc1 bs=4M && sync
```


确保设备上存在足够大（6 GB 或以上）的分区。此外，在运行 `dd` 命令时，不得装入该设备。请注意，分区中的所有数据都将被删除！

1.2.1 开始安装但不注册

安装遵循第 1.1 节“默认安装过程”中所述的相同工作流程，只是注册系统和添加模块/扩展的步骤有所不同。要开始安装，请执行第 1.1 节“默认安装过程”中的步骤第 1.1.1 节“语言、键盘和产品选择”至第 1.1.4 节“IBM Z：磁盘激活”。

1.2.2 跳过注册

在注册屏幕上，激活跳过注册。单击确定接受警告，然后单击下一步继续。




1.2.3 访问 SLE-15-SP1-Packages 映像



在附加产品对话框中，激活我要安装其他附加产品，并指定 SLE-15-SP1-Packages 映像的来源。选中下载储存库说明文件可立即下载用于描述储存库的文件。如果不激活，系统将在安装启动后下载它们。单击下一步继续。如果您之前选择 DVD 作为数据源，系统将提示您插入该媒体。

1.2.4 选择扩展和模块



在扩展和模块选择对话框中，需要选择一个产品、至少一个模块，并视需要选择一个或多个扩展。

SLE-15-SP1-Packages 映像包含所有 SUSE Linux Enterprise 产品的扩展和模块。请务必只选择下面所列的模块和扩展，否则系统最终可能安装失败，并且不能获得 SUSE 的支持。

产品

必须选择一个产品。选择 SLES15-SP1 15.1-0。

模块

模块会扩展 SUSE Linux Enterprise Server 的功能，并且是免费提供的。需要安装 Basesystem-Module 15.1-0。另外还建议您安装 Server-Applications-Module 15.1-0。请注意，大部分模块依赖于其他模块。在此步骤无法自动解决这些依赖关系。请务必手动解决依赖关系，否则后面安装将会失败。有关细节，请参见下面的列表。

Basesystem-Module 15.1-0: 此模块在安装程序的基础上添加一个基本系统。其他所有模块和扩展都需要此模块。只包含基础系统的安装其范围相当于旧版 SUSE Linux Enterprise Server 的最小系统安装模式。依赖项：无

Containers-Module 15.1-0: 包含容器的支持和工具。依赖项：Basesystem

Desktop-Applications-Module 15.1-0: 向系统添加图形用户界面和最基本的桌面应用程序。依赖项：Basesystem

Development-Tools-Module 15.1-0: 包含编译器（包括 gcc）以及编译和调试应用程序所需的库。

Legacy-Module 15.1-0: 包含旧版 SUSE Linux Enterprise Server 中提供的，但 SLES 15 SP1 中已弃用的包。从旧版 SLES 迁移时，建议使用此模块。依赖项：Basesystem、Server Applications

Public-Cloud-Module 15.1-0: 包含创建映像所需的全部工具，这些映像用于在云环境（例如 Amazon Web Services (AWS)、Microsoft Azure、Google Compute Platform 或 SUSE OpenStack Cloud）中部署 SUSE Linux Enterprise Server。依赖项：Basesystem、Server Applications

Python 2 模块 15.1-0: SUSE Linux Enterprise 15 SP 1 使用 Python 版本 3。此模块包含 Python 2 运行时与模块。依赖项：Basesystem

Server-Applications-Module 15.1-0: 通过提供 DHCP 服务器、名称服务器或 Web 服务器等网络服务来添加服务器功能。依赖项：Basesystem

Transactional Server 15.1-0: 添加了对事务更新的支持。更新将以单个事务的形式统一应用到系统，或者全部都不应用。这种方式不会影响正在运行的系统。如果某项更新失败，或者成功应用的更新被视为不兼容或者存在其他错误，可以丢弃该更新，使系统立即恢复到以前的正常运行状态。依赖项：Basesystem

Web-Scripting-Module 15.1-0: 包含用于运行中 Web 服务器的包。依赖项：Basesystem、Server Applications

扩展

选择扩展是可选的操作。扩展会向 SUSE Linux Enterprise Server 添加更多核心功能，这需要提供付费购买的注册代码。

请注意，扩展依赖于模块。在此步骤无法自动解决这些依赖关系。请务必手动解决依赖关系，否则后面安装将会失败。有关细节，请参见下面的列表。

SUSE Linux Enterprise High Availability Extension (SLEHA15-1 15.1-0): 向 SUSE Linux Enterprise Server 添加任务关键型设置的群集支持。选择 SLEHA15-1 15.1-0 可安装此扩展。依赖项：Basesystem、Server Applications

SUSE Linux Enterprise Workstation Extension (SLEWE15-1 15.1-0): 使用 SUSE Linux Enterprise Desktop 中与其他桌面应用程序（如办公套件、电子邮件客户端、图形编辑器等）类似的包和库，扩展 SUSE Linux Enterprise Server 的功能。使用该扩展可以将这两个产品相结合来打造功能完备的工作站。选择 SLEWE15-1 15.1-0 可安装此扩展。依赖项：Basesystem、Desktop Applications




警告：禁止的选项

请不要在 SUSE Linux Enterprise Server 中安装以下任何选项，否则系统最终可能会安装失败，且不能获得 SUSE 的支持。

- HPC-Module 15.1-0
- SAP-Applications-Module 15.1-0
- SLE-15-1-HPC 15.1-0
- SLE-15-1-RT 15.1-0
- SLE-15-1-SAP 15.1-0
- SLED15-1 15.1-0

选择完模块和扩展后，请单击下一步继续。

1.2.5 确认扩展和模块选择



选择安装的所有模块将列在附加产品安装对话框中。要更改列表，请使用添加或删除选项。使用添加时，可以选择性地添加其他附加产品。单击下一步继续安装。

1.2.6 完成安装

从现在起，安装将会按默认安装的路径进行。从第 1.1 节“默认安装过程”中的步骤第 1.1.8 节“系统角色”继续。

2 法律声明

版权所有 © 2006– 2024 SUSE LLC 和贡献者。保留所有权利。

根据 GNU 自由文档许可证 (GNU Free Documentation License) 版本 1.2 或 (根据您的选择) 版本 1.3 中的条款, 在此授予您复制、分发和/或修改本文档的许可权限; 本版权声明和许可证附带不可变部分。许可证版本 1.2 的副本包含在题为“GNU 自由文档许可证”的部分。

有关 SUSE 商标, 请参见 <http://www.suse.com/company/legal/>。所有其它第三方商标是其各自所有者的财产。商标符号 (®、™ 等) 代表 SUSE 及其附属公司的商标。星号 (*) 代表第三方商标。

本指南力求涵盖所有详细信息。但这并不确保本指南准确无误。SUSE LLC 及其附属公司、作者和译者对于可能出现的错误或由此造成的后果皆不承担责任。

GNU Free Documentation License

Copyright (C) 2000, 2001, 2002 Free Software Foundation, Inc. 51 Franklin St, Fifth Floor, Boston, MA 02110-1301 USA. Everyone is permitted to copy and distribute verbatim copies of this license document, but changing it is not allowed.

0. PREAMBLE

The purpose of this License is to make a manual, textbook, or other functional and useful document "free" in the sense of freedom: to assure everyone the effective freedom to copy and redistribute it, with or without modifying it, either commercially or non-commercially. Secondly, this License preserves for the author and publisher a way to get credit for their work, while not being considered responsible for modifications made by others.

This License is a kind of "copyleft", which means that derivative works of the document must themselves be free in the same sense. It complements the GNU General Public License, which is a copyleft license designed for free software.

We have designed this License to use it for manuals for free software, because free software needs free documentation: a free program should come with manuals providing the same freedoms that the software does. But this License is not limited to software manuals; it can be used for any textual work, regardless of subject matter or whether it is published as a printed book. We recommend this License principally for works whose purpose is instruction or reference.

1. APPLICABILITY AND DEFINITIONS

This License applies to any manual or other work, in any medium, that contains a notice placed by the copyright holder saying it can be distributed under the terms of this License. Such a notice grants a world-wide, royalty-free license, unlimited in duration, to use that work under the conditions stated herein. The "Document", below, refers to any such manual or work. Any member of the public is a licensee, and is addressed as "you". You accept the license if you copy, modify or distribute the work in a way requiring permission under copyright law.

A "Modified Version" of the Document means any work containing the Document or a portion of it, either copied verbatim, or with modifications and/or translated into another language.

A "Secondary Section" is a named appendix or a front-matter section of the Document that deals exclusively with the relationship of the publishers or authors of the Document to the Document's overall subject (or to related matters) and contains nothing that could fall directly within that overall subject. (Thus, if the Document is in part a textbook of mathematics, a Secondary Section may not explain any mathematics.) The relationship could be a matter of historical connection with the subject or with related matters, or of legal, commercial, philosophical, ethical or political position regarding them.

The "Invariant Sections" are certain Secondary Sections whose titles are designated, as being those of Invariant Sections, in the notice that says that the Document is released under this License. If a section does not fit the above definition of Secondary then it is not allowed to be designated as Invariant. The Document may contain zero Invariant Sections. If the Document does not identify any Invariant Sections then there are none.

The "Cover Texts" are certain short passages of text that are listed, as Front-Cover Texts or Back-Cover Texts, in the notice that says that the Document is released under this License. A Front-Cover Text may be at most 5 words, and a Back-Cover Text may be at most 25 words.

A "Transparent" copy of the Document means a machine-readable copy, represented in a format whose specification is available to the general public, that is suitable for revising the document straightforwardly with generic text editors or (for images composed of pixels) generic paint programs or (for drawings) some widely available drawing editor, and that is suitable for input to text formatters or for automatic translation to a variety of formats suitable for input to text formatters. A copy made in an otherwise Transparent file format whose markup, or absence of markup, has been arranged to thwart or discourage subsequent modification by readers is not Transparent. An image format is not Transparent if used for any substantial amount of text. A copy that is not "Transparent" is called "Opaque".

Examples of suitable formats for Transparent copies include plain ASCII without markup, Texinfo input format, LaTeX input format, SGML or XML using a publicly available DTD, and standard-conforming simple HTML, PostScript or PDF designed for human modification. Examples of transparent image formats include PNG, XCF and JPG. Opaque formats include proprietary formats that can be read and edited only by proprietary word processors, SGML or XML for which the DTD and/or processing tools are not generally available, and the machine-generated HTML, PostScript or PDF produced by some word processors for output purposes only.

The "Title Page" means, for a printed book, the title page itself, plus such following pages as are needed to hold, legibly, the material this License requires to appear in the title page. For works in formats which do not have any title page as such, "Title Page" means the text near the most prominent appearance of the work's title, preceding the beginning of the body of the text.

A section "Entitled XYZ" means a named subunit of the Document whose title either is precisely XYZ or contains XYZ in parentheses following text that translates XYZ in another language. (Here XYZ stands for a specific section name mentioned below, such as "Acknowledgements", "Dedications", "Endorsements", or "History".) To "Preserve the Title" of such a section when you modify the Document means that it remains a section "Entitled XYZ" according to this definition.

The Document may include Warranty Disclaimers next to the notice which states that this License applies to the Document. These Warranty Disclaimers are considered to be included by reference in this License, but only as regards disclaiming warranties: any other implication that these Warranty Disclaimers may have is void and has no effect on the meaning of this License.

2. VERBATIM COPYING

You may copy and distribute the Document in any medium, either commercially or non-commercially, provided that this License, the copyright notices, and the license notice saying this License applies to the Document are reproduced in all copies, and that you add no other conditions whatsoever to those of this License. You may not use technical measures to obstruct or control the reading or further copying of the copies you make or distribute. However, you may accept compensation in exchange for copies. If you distribute a large enough number of copies you must also follow the conditions in section 3.

You may also lend copies, under the same conditions stated above, and you may publicly display copies.

3. COPYING IN QUANTITY

If you publish printed copies (or copies in media that commonly have printed covers) of the Document, numbering more than 100, and the Document's license notice requires Cover Texts, you must enclose the copies in covers that carry, clearly and legibly, all these Cover Texts: Front-Cover Texts on the front cover, and Back-Cover Texts on the back cover. Both covers must also clearly and legibly identify you as the publisher of these copies. The front cover must present the full title with all words of the title equally prominent and visible. You may add other material on the covers in addition. Copying with changes limited to the covers, as long as they preserve the title of the Document and satisfy these conditions, can be treated as verbatim copying in other respects.

If the required texts for either cover are too voluminous to fit legibly, you should put the first ones listed (as many as fit reasonably) on the actual cover, and continue the rest onto adjacent pages.

If you publish or distribute Opaque copies of the Document numbering more than 100, you must either include a machine-readable Transparent copy along with each Opaque copy, or state in or with each Opaque copy a computer-network location from which the general network-using public has access to download using public-standard network protocols a complete Transparent copy of the Document, free of added material. If you use the latter option, you must take reasonably prudent steps, when you begin distribution of Opaque copies in quantity, to ensure that this Transparent copy will remain thus accessible at the stated location until at least one year after the last time you distribute an Opaque copy (directly or through your agents or retailers) of that edition to the public.

It is requested, but not required, that you contact the authors of the Document well before redistributing any large number of copies, to give them a chance to provide you with an updated version of the Document.

4. MODIFICATIONS

You may copy and distribute a Modified Version of the Document under the conditions of sections 2 and 3 above, provided that you release the Modified Version under precisely this License, with the Modified Version filling the role of the Document, thus licensing distribution and modification of the Modified Version to whoever possesses a copy of it. In addition, you must do these things in the Modified Version:

- A. Use in the Title Page (and on the covers, if any) a title distinct from that of the Document, and from those of previous versions (which should, if there were any, be listed in the History section of the Document). You may use the same title as a previous version if the original publisher of that version gives permission.
- B. List on the Title Page, as authors, one or more persons or entities responsible for authorship of the modifications in the Modified Version, together with at least five of the principal authors of the Document (all of its principal authors, if it has fewer than five), unless they release you from this requirement.
- C. State on the Title page the name of the publisher of the Modified Version, as the publisher.
- D. Preserve all the copyright notices of the Document.
- E. Add an appropriate copyright notice for your modifications adjacent to the other copyright notices.
- F. Include, immediately after the copyright notices, a license notice giving the public permission to use the Modified Version under the terms of this License, in the form shown in the Addendum below.
- G. Preserve in that license notice the full lists of Invariant Sections and required Cover Texts given in the Document's license notice.
- H. Include an unaltered copy of this License.
- I. Preserve the section Entitled "History", Preserve its Title, and add to it an item stating at least the title, year, new authors, and publisher of the Modified Version as given on the Title Page. If there is no section Entitled "History" in the Document, create one stating the title, year, authors, and publisher of the Document as given on its Title Page, then add an item describing the Modified Version as stated in the previous sentence.

- J. Preserve the network location, if any, given in the Document for public access to a Transparent copy of the Document, and likewise the network locations given in the Document for previous versions it was based on. These may be placed in the "History" section. You may omit a network location for a work that was published at least four years before the Document itself, or if the original publisher of the version it refers to gives permission.
- K. For any section Entitled "Acknowledgements" or "Dedications", Preserve the Title of the section, and preserve in the section all the substance and tone of each of the contributor acknowledgements and/or dedications given therein.
- L. Preserve all the Invariant Sections of the Document, unaltered in their text and in their titles. Section numbers or the equivalent are not considered part of the section titles.
- M. Delete any section Entitled "Endorsements". Such a section may not be included in the Modified Version.
- N. Do not retitle any existing section to be Entitled "Endorsements" or to conflict in title with any Invariant Section.
- O. Preserve any Warranty Disclaimers.

If the Modified Version includes new front-matter sections or appendices that qualify as Secondary Sections and contain no material copied from the Document, you may at your option designate some or all of these sections as invariant. To do this, add their titles to the list of Invariant Sections in the Modified Version's license notice. These titles must be distinct from any other section titles.

You may add a section Entitled "Endorsements", provided it contains nothing but endorsements of your Modified Version by various parties—for example, statements of peer review or that the text has been approved by an organization as the authoritative definition of a standard.

You may add a passage of up to five words as a Front-Cover Text, and a passage of up to 25 words as a Back-Cover Text, to the end of the list of Cover Texts in the Modified Version. Only one passage of Front-Cover Text and one of Back-Cover Text may be added by (or through arrangements made by) any one entity. If the Document already includes a cover text for the same cover, previously added by you or by arrangement made by the same entity you are acting on behalf of, you may not add another; but you may replace the old one, on explicit permission from the previous publisher that added the old one.

The author(s) and publisher(s) of the Document do not by this License give permission to use their names for publicity for or to assert or imply endorsement of any Modified Version.

5. COMBINING DOCUMENTS

You may combine the Document with other documents released under this License, under the terms defined in section 4 above for modified versions, provided that you include in the combination all of the Invariant Sections of all of the original documents, unmodified, and list them all as Invariant Sections of your combined work in its license notice, and that you preserve all their Warranty Disclaimers.

The combined work need only contain one copy of this License, and multiple identical Invariant Sections may be replaced with a single copy. If there are multiple Invariant Sections with the same name but different contents, make the title of each such section unique by adding at the end of it, in parentheses, the name of the original author or publisher of that section if known, or else a unique number. Make the same adjustment to the section titles in the list of Invariant Sections in the license notice of the combined work.

In the combination, you must combine any sections Entitled "History" in the various original documents, forming one section Entitled "History"; likewise combine any sections Entitled "Acknowledgements", and any sections Entitled "Dedications". You must delete all sections Entitled "Endorsements".

6. COLLECTIONS OF DOCUMENTS

You may make a collection consisting of the Document and other documents released under this License, and replace the individual copies of this License in the various documents with a single copy that is included in the collection, provided that you follow the rules of this License for verbatim copying of each of the documents in all other respects.

You may extract a single document from such a collection, and distribute it individually under this License, provided you insert a copy of this License into the extracted document, and follow this License in all other respects regarding verbatim copying of that document.

7. AGGREGATION WITH INDEPENDENT WORKS

A compilation of the Document or its derivatives with other separate and independent documents or works, in or on a volume of a storage or distribution medium, is called an "aggregate" if the copyright resulting from the compilation is not used to limit the legal rights of the compilation's users beyond what the individual works permit. When the Document is included in an aggregate, this License does not apply to the other works in the aggregate which are not themselves derivative works of the Document.

If the Cover Text requirement of section 3 is applicable to these copies of the Document, then if the Document is less than one half of the entire aggregate, the Document's Cover Texts may be placed on covers that bracket the Document within the aggregate, or the electronic equivalent of covers if the Document is in electronic form. Otherwise they must appear on printed covers that bracket the whole aggregate.

8. TRANSLATION

Translation is considered a kind of modification, so you may distribute translations of the Document under the terms of section 4. Replacing Invariant Sections with translations requires special permission from their copyright holders, but you may include translations of some or all Invariant Sections in addition to the original versions of these Invariant Sections. You may include a translation of this License, and all the license notices in the Document, and any Warranty Disclaimers, provided that you also include the original English version of this License and the original versions of those notices and disclaimers. In case of a disagreement between the translation and the original version of this License or a notice or disclaimer, the original version will prevail.

If a section in the Document is Entitled "Acknowledgements", "Dedications", or "History", the requirement (section 4) to Preserve its Title (section 1) will typically require changing the actual title.

9. TERMINATION

You may not copy, modify, sublicense, or distribute the Document except as expressly provided for under this License. Any other attempt to copy, modify, sublicense or distribute the Document is void, and will automatically terminate your rights under this License. However, parties who have received copies, or rights, from you under this License will not have their licenses terminated so long as such parties remain in full compliance.

10. FUTURE REVISIONS OF THIS LICENSE

The Free Software Foundation may publish new, revised versions of the GNU Free Documentation License from time to time. Such new versions will be similar in spirit to the present version, but may differ in detail to address new problems or concerns. See <http://www.gnu.org/copyleft/>.

Each version of the License is given a distinguishing version number. If the Document specifies that a particular numbered version of this License "or any later version" applies to it, you have the option of following the terms and conditions either of that specified version or of any later version that has been published (not as a draft) by the Free Software Foundation. If the Document does not specify a version number of this License, you may choose any version ever published (not as a draft) by the Free Software Foundation.

ADDENDUM: How to use this License for your documents

```
Copyright (c) YEAR YOUR NAME.  
Permission is granted to copy, distribute and/or modify this document  
under the terms of the GNU Free Documentation License, Version 1.2  
or any later version published by the Free Software Foundation;  
with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts.  
A copy of the license is included in the section entitled "GNU  
Free Documentation License".
```

If you have Invariant Sections, Front-Cover Texts and Back-Cover Texts, replace the "with...Texts." line with this:

```
with the Invariant Sections being LIST THEIR TITLES, with the  
Front-Cover Texts being LIST, and with the Back-Cover Texts being LIST.
```

If you have Invariant Sections without Cover Texts, or some other combination of the three, merge those two alternatives to suit the situation.

If your document contains nontrivial examples of program code, we recommend releasing these examples in parallel under your choice of free software license, such as the GNU General Public License, to permit their use in free software.