

## SUSE Linux Enterprise Desktop 15 SP1

# インストールクイックスタート

## SUSE Linux Enterprise Desktop 15 SP1

このクイックスタートでは、SUSE® Linux Enterprise Desktop 15 SP1のインストールについて順を追って説明します。

発行日: September 08, 2022

## 目次

- 1 SUSE Linux Enterprise Desktopへようこそ 2
- 2 保証と著作権 27
- 3 GNU Free Documentation License 27

# 1 SUSE Linux Enterprise Desktopへようこそ

サポートされているすべてのハードウェアプラットフォームに製品をインストールするには、次の手順に従います。インストールシステムが正常にブートしていることが前提になります。インストール手順と展開計画の詳細については、『Deployment Guide』を参照してください。インストールシステムをブートするのに必要な準備については、『Deployment Guide』、第2章「Installation on AMD64 and Intel 64」を参照してください。

## 1.1 デフォルトのインストール手順

SUSE Linux Enterprise Desktop 15以降のインストールメディアには、インストーラのみが収録されています。これは、SUSE Linux Enterprise Desktopのインストール、更新、登録用の最小限のコマンドラインベースシステムです。インストール時には、インストーラ上にインストールするモジュールを選択することにより、機能を追加できます。

デフォルトのインストールでは、SUSEカスタマーセンターまたはローカルのRepository Mirroring Toolサーバからモジュール用のリポジトリデータを取得するために、ネットワークへのアクセスを必要とします。ネットワークへのアクセスなしでインストールを実行する場合は、2つ目のインストールメディア (SLE-15-SP1-Packagesイメージ)が必要になります。




SUSE Linux Enterprise Desktopをインストールするには、インストーラメディアからインストーラをブートしてインストールを開始します。

### 1.1.1 言語、キーボード、および製品選択



言語およびキーボード配列設定は、ブート画面で選択した言語で初期化されています。デフォルトを変更していない場合は、英語(米国)になります。必要に応じて、ここで設定を変更します。キーボードテストテキストボックスを使用して、この配列をテストします。


インストーラを使用して、次のSUSE Linux Enterpriseの基本製品をインストールできます。

- SUSE Linux Enterprise Server 15 SP1 (インストール手順については、<https://www.suse.com/documentation/sles/> を参照)
- SUSE Linux Enterprise Desktop 15 SP1 (ここで説明)
- SUSE Linux Enterprise High Performance Computing 15 SP1
- SUSE Linux Enterprise Real Time 15 SP1 (インストール手順については、<https://www.suse.com/documentation/slerte/> を参照)
- SUSE Linux Enterprise Server for SAP Applications 15 SP1 (インストール手順については、<https://www.suse.com/documentation/sles-for-sap/> を参照)

- SUSE Manager Server 4.0 (インストール手順については、<https://www.suse.com/documentation/suse-manager/> を参照)
- SUSE Manager Proxy 4.0 (インストール手順については、<https://www.suse.com/documentation/suse-manager/> を参照)
- SUSE Manager Retail Branch Server 4.0 (インストール手順については、<https://www.suse.com/documentation/suse-manager-for-retail/> を参照)


インストールする製品を選択します。それぞれの製品の登録コードが必要です。このドキュメントでは、SUSE Linux Enterprise Desktopを選択したものと想定されます。次へで続行します。

### 1.1.2 使用許諾契約



ライセンス契約をお読みください。これは、ブート画面で選択した言語で表示されます。訳文は、License Language (ライセンス言語)ドロップダウンボックスを選択して表示できます。SUSE Linux Enterprise Desktopをインストールするには、はい、ライセンスに同意しますをオンにして契約に同意する必要があります。次へで続行します。

### 1.1.3 ネットワーク設定



システムの分析が実行されます。インストーラはストレージデバイスを検索し、他のインストール済みシステムの検出を試みます。インストールを開始する際にDHCPを介してネットワークが自動設定された場合は、登録ステップに移動します。

ネットワークがまだ設定されていない場合は、ネットワークの設定ダイアログが開きます。リストからネットワークインタフェースを選択し、編集をクリックして設定します。または、追加をクリックして、インタフェースを手動で追加します。詳細については、『Deployment Guide』、第4章「Installation Steps」、4.5項「Network Settings」と『管理ガイド』、第17章「ネットワークの基礎」、17.4項「YaSTによるネットワーク接続の設定」を参照してください。ネットワークへのアクセスなしでインストールしたい場合は、変更を加えずにこのステップをスキップし、次へで続行します。

## 1.1.4 登録

テクニカルサポート情報や製品のアップデートを入手するには、SUSEカスタマーセンターまたはローカル登録サーバで製品を登録してアクティブ化する必要があります。この段階でSUSE Linux Enterprise Desktopを登録すると、アップデートリポジトリへのアクセス権もただちに得られます。これにより、利用できる最新のアップデートとパッチを使用してシステムをインストールできるようになります。登録時には、モジュールおよび拡張機能(次のステップでインストール可能)のリポジトリと依存関係が登録サーバからロードされます。

ネットワークに接続していない場合または登録をスキップする場合は、登録を行わずに飛ばすを有効にします。[1.2項「登録なしのインストール」](#)の手順に従って、インストールを続行します。

SUSEカスタマーセンターで登録するには、SCCアカウントに関連付けられている電子メールアドレスと、SUSE Linux Enterprise Desktopの登録コードを入力します。組織がローカル登録サーバを提供している場合は、代わりにそこで登録することもできます。ローカルSMTサーバを使用してシステムを登録するを有効にした後、ドロップダウンボックスからURLを選択するかアドレスを入力します。



## 注記: リポジトリを信頼する


ハードウェアによっては、ハードウェアドライバを含むリポジトリが登録中に追加されることがあります。この場合、これらのリポジトリを信頼するよう求められます。



## ヒント: インストール時に製品パッチをインストールする

SUSE Linux Enterprise Desktopが正しく登録された後、インストール中に、利用可能な最新のオンラインアップデートをインストールするかどうかを尋ねられます。はいを選択すると、システムは、最新パッケージとともにインストールされ、インストール後にアップデートを適用する必要がなくなります。このオプションを有効にすることをお勧めします。

### 1.1.5 拡張機能とモジュールの選択



システムが正しく登録された後、SUSE Linux Enterprise Desktopで使用可能なモジュールと拡張機能が一覧表示されます。モジュールとは、ユーザのニーズに合わせて製品を構築できるコンポーネントのことで、無償で提供されています。拡張機能は、製品に特定の機能を追加します。拡張機能はサブスクリプションとして提供されており、有料登録キーを必要とします。

提供されるモジュールまたは拡張機能は、このインストールの最初のステップで選択した製品に応じて異なります。モジュールとそのライフサイクルの説明については、モジュールを選択した後に表示されるテキストを参照してください。詳細については、項目「Modules and Extensions Quick Start」およびリリースノート ([https://www.suse.com/releasenotes/x86\\_64/SUSE-SLES/15/#Intro.Module](https://www.suse.com/releasenotes/x86_64/SUSE-SLES/15/#Intro.Module)) を参照してください。

モジュールの選択はインストールの範囲に間接的な影響を与えます。インストール環境と実働システムでどのソフトウェアソース(リポジトリ)を使用できるかが定義されるからです。

SUSE Linux Enterprise Desktopでは、次のモジュールと拡張機能が提供されています。

### Basesystem Module

このモジュールは、インストーラ上に基本システムを追加します。これは、他のすべてのモジュールと拡張機能が必要とします。基本システムのみを含むインストールの範囲は、上述のSUSE Linux Enterprise Desktopバージョンの「最小限のシステム」におけるインストールパターンと似ています。このモジュールは、デフォルトでインストール用に選択されており、選択解除してはなりません。

依存関係: なし

### Desktop Applications Module

システムにグラフィカルユーザインタフェースと重要なデスクトップアプリケーションを追加します。このモジュールはデフォルトでインストール用に選択されており、これを選択解除することはお勧めしていません。

依存関係: Basesystem

### Development Tools Module

アプリケーションのコンパイルとデバッグに必要とされるコンパイラ( `gcc` を含む)およびライブラリが含まれます。以前のソフトウェア開発キット(SDK)を置き換えます。

依存関係: Basesystem、Desktop Applications

### Python 2 Module

SUSE Linux Enterprise 15 SP 1ではPythonバージョン3を使用します。このモジュールには、Python 2ランタイムおよびモジュールが含まれます。これはデフォルトでインストール用に選択されており、これを選択解除することはお勧めしていません。

依存関係: Basesystem

### SUSE Cloud Application Platform Tools Module



SUSE Cloud Application Platform製品とのやり取りを可能にするツールを追加します。


依存関係: Basesystem

### SUSE Linux Enterprise Workstation Extension

オフィススイートやマルチメディアソフトウェア(例: ミュージックプレーヤ、ビデオプレーヤ)などの追加デスクトップツールが含まれます。この拡張機能はSUSE Linux Enterprise Desktopサブスクリプションに含まれ、デフォルトでインストール用に選択されており、これを選択解除することはお勧めしていません。

依存関係: Basesystem、Desktop Applications

### SUSE Package Hub

openSUSEコミュニティが管理しているSUSE Linux Enterprise Desktopパッケージへのアクセスを提供します。これらのパッケージはL3サポートなしで配布されるため、SUSE Linux Enterprise Desktopのサポート可能性に影響を与えることはありません。詳細については、<https://packagehub.suse.com/> を参照してください。

依存関係: Basesystem

一部のモジュールでは、他のモジュールをインストールする必要がある生じます。そのため、モジュールを選択すると、この依存関係を満たすために他のモジュールが自動的に選択される場合があります。

製品によっては、特定のモジュールと拡張機能に登録サーバが推奨マークを付けている場合もあります。推奨されたモジュールと拡張機能は、登録およびインストールのために事前選択されます。これらの推奨項目をインストールしないときは、手動で選択を解除します。

インストールするモジュールと拡張機能を選択し、次へで続行します。1つ以上の拡張機能を選択した場合、それぞれの登録コードの入力が求められます。選択内容によっては、別の使用許諾契約の受諾が必要な場合があります。

## 1.1.6 アドオン製品



アドオン製品ダイアログを使用して、SUSEカスタマーセンターで提供されていない他のソフトウェアソース(「リポジトリ」)をSUSE Linux Enterprise Desktopに追加できます。このようなアドオン製品には、サードパーティの製品や、ご使用のシステム用のドライバまたは追加ソフトウェアなどがあります。




### ヒント: インストール中にドライバを追加する

アドオン製品ダイアログを使用して、ドライバアップデートリポジトリを追加することもできます。SUSE Linux Enterpriseのドライバのアップデートは<http://drivers.suse.com/>に用意されています。これらのドライバは、SUSE SolidDriverプログラムを使用して作成されています。

このステップをスキップする場合は、次へで続行します。スキップしない場合は、アドオン製品をインストールするをオンにします。メディアタイプ、ローカルパス、またはリポジトリをホストしているネットワークリソースを指定して、画面の指示に従います。

リポジトリを記述するファイルを今すぐダウンロードするには、リポジトリの説明をダウンロードをオンにします。オフの場合、ファイルはインストールの開始後にダウンロードされます。次へで続行し、必要な場合はメディアを挿入します。製品のコンテンツによっては、追加のライセンス契約に同意しなければならない場合があります。次へで続行します。登録キーを必要とするアドオン製品を選択した場合は、次のステップに進む前に登録キーの入力を求められます。

### 1.1.7 システムの役割



どのシステム役割を使用できるかは、選択したモジュールと拡張機能にかかっています。システム役割は、パーティションの推奨設定や、インストール用に事前選択されるソフトウェアパターンのセットなどを定義します。選択する際には、画面上の説明を参照してください。役割を選択し、次へで続行します。



#### ヒント: リリースノート

これ以降の手順では、リリースノートを選択することで、インストールプロセスのどの画面からでもリリースノートを参照できます。

## 1.1.8 推奨のパーティション



システムによって推奨されたパーティションの設定を確認します。必要に応じて設定を変更します。次の選択肢があります。

### ガイド付き設定

パーティションの推奨設定を調整できるウィザードを起動します。ここで使用可能なオプションは、システムの設定に応じて異なります。複数のハードディスクが存在する場合、どのディスクを使用してどこにルートパーティションを配置するかを選択できます。ディスク内にすでにパーティションが存在する場合は、そのパーティションを削除するか、サイズ変更してください。後続の手順では、LVMサポートとディスク暗号化の機能を追加することもできます。ルートパーティション用のファイルシステムを変更して、別個のホームパーティションを作成するかどうかを決定できます。

### Expert Partitioner (エキスパートパーティショナ)

エキスパートパーティショナを開きます。『Deployment Guide』、第6章「Expert Partitioner」、6.1項「Using the Expert Partitioner」を参照してください。これにより、パーティション設定を全面的に制御して、カスタム設定を作成できます。これは、熟練者向けのオプションです。


推奨設定を変更せずにそのまま使用の場合は、次へを選択して続行します。



## ヒント: リリースノート

これ以降の手順では、リリースノートを選択することで、インストールプロセスのどの画面からでもリリースノートを参照できます。

### 1.1.9 時計とタイムゾーン



システムで使用する時計とタイムゾーンを選択します。時刻を手動で調整したり、時刻同期用のNTPサーバを設定したりするには、その他の設定を選択します。詳細については、『Deployment Guide』、第4章「Installation Steps」、4.11項「Clock and Time Zone」を参照してください。次へで続行します。

### 1.1.10 ローカルユーザ

ローカルユーザ

● 新しいユーザの作成 (C)

ユーザのフルネーム (F)

ユーザ名 (U)

パスワード (P)

パスワードの確認 (Q)

☐ このパスワードをシステム管理者用のものとしても使用する (S)

☐ 自動ログイン (A)

○ ユーザの作成を行わずに飛ばす (S)

ヘルプ (H) リリースノート (L)... 中止 (R) 戻る (B) 次へ (N)

ローカルユーザを作成するため、ユーザのフルネームフィールドに姓と名を入力します。ユーザ名フィールドにログイン名を入力し、パスワードフィールドにパスワードを入力します。

パスワードは8文字以上の長さとし、大文字、小文字、および数字を組み合わせる必要があります。パスワードは最長72文字で、大文字と小文字が区別されます。


セキュリティ上の理由から、自動ログインは有効に「しない」ことを強くお勧めします。また、このパスワードをシステム管理者用のものとしても使用するも有効に「しない」で、インストールの次のステップで別の root パスワードを指定することをお勧めします。

以前のLinuxインストールが見つかったシステムにインストールする場合は、以前のインストールからユーザデータを取り込むことができます。使用可能なユーザアカウントのリストについては、ユーザの選択をクリックしてください。1つまたは複数の項目を選択します。

(たとえばNISまたはLDAPによって)ユーザが一元的に管理される環境では、ローカルユーザの作成を行わずに飛ばしたい場合があります。この場合は、ユーザの作成を行わずに飛ばすを選択します。

次へで続行します。

### 1.1.11 システム管理者向け「root」認証



The screenshot shows the SUSE logo in the top left corner. The main heading is "システム管理者 'root' の認証" (System Administrator 'root' Authentication). Below this, there are several input fields and buttons:

- A warning message: "ここで入力したパスワードを忘れないようにしてください。" (Please do not forget the password entered here.)
- A label "root ユーザのパスワード (P)" followed by a password input field.
- A label "パスワードの確認 (F)" followed by a confirmation password input field.
- A label "キーボードレイアウトのテスト (I)" followed by a keyboard layout test input field.
- A section titled "SSH 公開鍵の取り込み" (SSH Public Key Import) containing:
  - A dropdown menu showing "QEMU DVD-ROM (/dev/sr0)" with a "更新 (R)" (Refresh) button next to it.
  - A "参照 (H)..." (Browse...) button.
- At the bottom, there are four buttons: "ヘルプ (H)" (Help), "リリースノート (L)..." (Release Notes...), "中止 (R)" (Cancel), and "次へ (N)" (Next).

システム管理者(root ユーザと呼ばれる)のパスワードを入力するか、SSH公開鍵を提供します。希望する場合は、両方使用することができます。

root ユーザには莫大な権限が与えられているため、パスワードは慎重に選択する必要があります。root パスワードは忘れないようにしてください。ここで入力した後は、このパスワードを訂正することはできません。





## ヒント: パスワードとキーボードレイアウト

英語キーボードで利用できる文字のみを使用することをお勧めします。システムエラーが発生した場合やレスキューモードでシステムを起動する必要がある場合は、ローカライズしたキーボードを使用できないことがあります。

公開鍵を使用したSSHを介してシステムにリモートにアクセスすることを希望する場合があります。この画面では、USBスティック、CD/DVD ROM、または既存のパーティションから公開鍵(ファイル拡張子 .pub)を選択できます。詳細については、『Deployment Guide』、第4章「Installation Steps」、4.13項「Authentication for the System Administrator “root”」を参照してください。後で、SSH公開鍵を追加することもできます(『Deployment Guide』、第4章「Installation Steps」、4.13項「Authentication for the System Administrator “root”」、Adding a Public SSH Key for User rootを参照してください)。

次へで続行します。



## 1.1.12 インストールの設定



インストール設定画面を使用して、推奨されているインストール設定を確認し、必要に応じて設定を変更します。各設定に対して現在の設定が表示されます。変更するには、見出しをクリックします。ファイアウォールやSSHなど一部の設定は、それぞれのリンクをクリックして直接変更できます。



### ヒント: リモートアクセス

ここで変更可能な設定は、後で、インストールされたシステムから随時変更することもできます。ただし、インストール後すぐにリモートアクセスが必要な場合は、ファイアウォールとSSHの各設定をクリックする必要があります。

### ソフトウェア

インストールのスコープは、このインストール環境用に選択したモジュールと拡張機能によって定義されます。ただし、選択した内容によっては、モジュールで提供されているパッケージの一部がインストール用に選択されないことがあります。

ソフトウェアをクリックするとソフトウェアの選択およびシステムタスク画面が開き、パターンを選択または選択解除することでソフトウェアの選択内容を変更できます。各パターンには、特定の機能に必要なソフトウェアパッケージが多数含まれています(KVMホストサーバなど)。インストールするソフトウェアパッケージに基づいてさらに細かく選択するには、詳細を選択してYaSTソフトウェアマネージャに切り替えます。詳細については、『Deployment Guide』、第16章「Installing or Removing Software」を参照してください。

## 起動

このセクションにはブートローダの設定が表示されます。デフォルト値を変更するのは、本当に必要な場合のみにすることをお勧めします。詳細については、『管理ガイド』、第12章「ブートローダ GRUB 2」を参照してください。

## ファイアウォールとSSH

公開ゾーン用に設定されているすべてのネットワークインタフェースでは、デフォルトでファイアウォールが有効になっています。設定の詳細については、『Security and Hardening Guide』、第23章「Masquerading and Firewalls」、23.4項「firewalld」を参照してください。

SSHサービスはデフォルトでは有効で、そのポート(22)は開いています。これらの設定を切り替えるには、有効にするおよび開くをクリックします。SSHが無効な場合、リモートログインはできないことに注意してください。

## Kdump

Kdumpは、カーネルがクラッシュした場合に備えてメモリイメージ(「コアダンプ」)をファイルシステムに保存します。これにより、ダンプファイルをデバッグしてクラッシュの原因を特定できます。Kdumpはデフォルトで、事前設定済み、および有効になっています。詳細については、『System Analysis and Tuning Guide』、第17章「Kexec and Kdump」、17.7項「Basic Kdump Configuration」を参照してください。


## 既定のsystemdターゲット

SUSE Linux Enterprise Desktopは、グラフィカルデスクトップにデフォルトでブートされます。デスクトップシステムをコマンドラインから実行するメリットはないので、この設定はそのまま使用することをお勧めします。

## システム

システムをクリックして、詳細なハードウェア情報を参照します。表示される画面でカーネル設定を変更することもできます。詳細については、『Deployment Guide』、第4章「Installation Steps」、4.14.7項「System」を参照してください。

### 1.1.13 インストールの開始



インストール設定画面でシステムの設定を完了したら、インストールするをクリックします。ソフトウェアの選択内容によっては、インストールの確認画面が表示される前にライセンス契約に同意しなければならない場合があります。この段階では、システムはまだ変更されていません。もう一度インストールするをクリックすると、インストールプロセスが開始されます。

### 1.1.14 インストールプロセス



インストール中は、詳細タブに詳しい進行状況が表示されます。SUSE Linux Enterprise Desktop Release Notes (SUSE Linux Enterprise Desktopリリースノート)タブには、重要な情報が表示されるので、これらの情報を読むことをお勧めします。

インストールルーチンが完了すると、コンピュータが再起動され、インストールされたシステムが起動します。ログインしてYaSTを起動し、システムを微調整します。グラフィカルデスクトップを使用していない場合、またはリモートから作業している場合、ターミナルからYaSTを使用する方法については、『管理ガイド』、第5章「テキストモードのYaST」を参照してください。

## 1.2 登録なしのインストール

登録サーバに接続せずにインストールを実行すると、インストール中にシステムを登録することはできません。つまり、モジュールと拡張機能用のリポジトリ設定を登録サーバから受信することはできません。通常のインストールを可能にするため、SUSEでは、SLE-15-SP1-Packagesイメージという2つ目のインストールメディアを提供しています。



## 注記: SUSE Linux Enterprise Desktopの登録

システムと拡張機能は、登録しないとアップデートとサポートの対象になりません。インストール時に登録していない場合は、後で稼働中のシステムから行うことができます。これは、YaST › 製品の登録の順に選択して実行します。

登録なしのインストールを実行するには、インストール中にSLE-15-SP1-Packagesイメージのコンテンツにアクセスできるようにしておきます。これは、このイメージをローカルハードディスクやリムーバブルフラッシュディスクにコピーしたり、ローカルネットワークで公開したりすることによって可能です。ご使用のハードウェアでサポートされている方法を選択してください。



## ヒント: SLE-15-SP1-Packagesイメージからリムーバブルフラッシュディスクにデータをコピーする

イメージのコンテンツをリムーバブルフラッシュディスクにコピーするには、次のコマンドを使用します。

```
tux > sudo dd if=PATH_TO_IMAGE
      of=FLASH_STORAGE_PARTITION bs=4M && sync
```

PATH\_TO\_IMAGE は、このイメージファイルへの相対パスまたは絶対パスで置き換えます。FLASH\_STORAGE\_PARTITION は、フラッシュデバイスのパーティション(通常は1つだけです)へのパスで置き換えます。デバイスとそのパーティションを識別するには、そのデバイスを挿入してから、次の例のコマンドを使用します。

```
root # grep -Ff <(hwinfo --disk --short) <(hwinfo --usb --short)
disk:
  /dev/sdc          General USB Flash Disk
root # fdisk -l /dev/sdc | grep -e "^/dev"
/dev/sdc1 *        2048 31490047 31488000 15G 83 Linux
```

この場合、使用コマンドは次のようになります。

```
dd if=/tmp/SLE-15-SP1-Packages-x86_64-DVD1.iso \
  of=/dev/sdc1 bs=4M && sync
```


このデバイスに十分なサイズ(6GB以上)のパーティションが存在することを確認してください。また、dd コマンドを実行しているときは、このデバイスをマウントしないでください。さもないと、パーティション上のデータがすべて消去されてしまいます。

## 1.2.1 登録なしのインストールの開始

1.1項「デフォルトのインストール手順」と同じワークフローに沿ってインストールされますが、システムの登録手順や、モジュールまたは拡張機能の追加手順は異なります。インストールを開始するには、1.1項「デフォルトのインストール手順」の1.1.1項「言語、キーボード、および製品選択」から1.1.3項「ネットワーク設定」までの手順を実行します。

## 1.2.2 登録を行わずに飛ばす

登録画面で、登録を行わずに飛ばすを有効にします。OKをクリックして警告を受け入れ、次へで続行します。



### 1.2.3 SLE-15-SP1-Packagesイメージへのアクセス



アドオン製品ダイアログで、追加のアドオン製品をインストールするを有効にし、SLE-15-SP1-Packagesイメージのソースを指定します。リポジトリを記述するファイルを今すぐダウンロードするには、リポジトリの説明をダウンロードをオンにします。この項目をオフにすると、インストールを開始してからファイルがダウンロードされます。次へで続行します。データソースとしてDVDを選択した場合、メディアの挿入が求められます。



## 1.2.4 拡張機能とモジュールの選択



拡張とモジュールの選択ダイアログで、製品と少なくとも1つのモジュール、および必要に応じて1つ以上の拡張機能を選択する必要があります。

SLE-15-SP1-Packagesイメージには、SUSE Linux Enterpriseの全製品に対応する拡張機能とモジュールが含まれています。以下のモジュールと拡張機能だけを選択してください。そうでないと、システムをインストールできないだけでなく、SUSEのサポート対象から除外される可能性があります。

### 製品

製品の選択は必須です。SLED15-SP1 15.1-0を選択します。

### モジュール

モジュールはSUSE Linux Enterprise Desktopの機能を拡張し、無償で提供されています。Basesystem-Module 15.1-0のインストールは必須です。Desktop-Applications-Module 15.1-0のインストールもお勧めします。

ほとんどのモジュールは他のモジュールに依存しています。ここで、これらの依存関係を自動的に特定することはできません。依存関係の特定は手動で行ってください。そうでないと、後でインストールに失敗してしまいます。詳細については、次のリストを参照してください。



Basesystem-Module 15.1-0. このモジュールは、インストーラ上に基本システムを追加します。これは、他のすべてのモジュールと拡張機能が必要とします。基本システムのみを含むインストールの範囲は、上述のSUSE Linux Enterprise Desktopバージョンの「最小限のシステム」におけるインストールパターンと似ています。依存関係: なし

Desktop-Applications-Module 15.1-0. システムにグラフィカルユーザインタフェースと重要なデスクトップアプリケーションを追加します。依存関係: Basesystem

Development-Tools-Module 15.1-0. アプリケーションのコンパイルとデバッグに必要とされるコンパイラ( `gcc` を含む)およびライブラリが含まれます。

Python 2 Module 15.1-0. SUSE Linux Enterprise 15 SP 1ではPythonバージョン3を使用します。このモジュールには、Python 2ランタイムおよびモジュールが含まれます。依存関係: Basesystem

### SUSE Linux Enterprise Workstation Extension (SLEWE15-1 15.1-0)

オフィススイートやマルチメディアソフトウェア(例: ミュージックプレーヤ、ビデオプレーヤ)などの追加デスクトップツールが含まれます。SUSE Linux Enterprise Desktop用のSUSE Linux Enterprise Workstation Extensionは無償で提供されており、追加の登録コードは不要です。SLEWE15-1 15.1-0をインストールすることをお勧めします。




### 警告: 禁止されている選択

SUSE Linux Enterprise Desktopには、次のモジュールや拡張機能をインストールしないでください。そうでないと、システムをインストールできないだけでなく、SUSEのサポート対象から除外されてしまいます。

- Containers-Module 15.1-0
- HPC-Module 15.1-0
- Legacy-Module 15.1-0
- Live-Patching 15.1-0
- Public-Cloud-Module 15.1-0
- SAP-Applications-Module 15.1-0
- SLE-15-1-HPC 15.1-0
- SLE-15-1-RT 15.1-0
- SLE-15-1-SAP 15.1-0
- SLEHA15-1 15.1-0
- SLES15-1 15.1-0
- Server-Applications-Module 15.1-0
- Web-Scripting-Module 15.1-0

モジュールと拡張機能を選択したら、次へで続行します。

### 1.2.5 拡張機能とモジュールの選択の確認



インストール用に選択したすべてのモジュールは、アドオン製品のインストールダイアログに一覧表示されます。このリストを変更するには、追加または削除オプションを使用します。追加を使用すると、任意で他のアドオン製品を追加することができます。インストールを続行するには、次へを選択します。

### 1.2.6 インストールの最終処理

ここからのインストール手順は、デフォルトのインストールの場合と同様です。1.1項「デフォルトのインストール手順」の1.1.7項「システムの役割」の手順に進みます。

## 2 保証と著作権

Copyright © 2006– 2022 SUSE LLC and contributors. All rights reserved.

この文書は、GNUフリー文書ライセンスのバージョン1.2または(オプションとして)バージョン1.3の条項に従って、複製、頒布、および/または改変が許可されています。ただし、この著作権表示およびライセンスは変更せずに記載すること。ライセンスバージョン1.2のコピーは、「GNUフリー文書ライセンス」セクションに含まれています。

SUSEの商標については、<http://www.suse.com/company/legal/> を参照してください。その他の製品名および会社名は、各社の商標または登録商標です。商標記号(®、™など)は、SUSEおよび関連会社の商標を示します。アスタリスク(\*)は、第三者の商標を示します。

本書のすべての情報は、細心の注意を払って編集されています。しかし、このことは絶対に正確であることを保証するものではありません。SUSE LLC、その関係者、著者、翻訳者のいずれも誤りまたはその結果に対して一切責任を負いかねます。

### GNU Free Documentation License

Copyright (C) 2000, 2001, 2002 Free Software Foundation, Inc. 51 Franklin St, Fifth Floor, Boston, MA 02110-1301 USA. Everyone is permitted to copy and distribute verbatim copies of this license document, but changing it is not allowed.

#### 0. PREAMBLE

The purpose of this License is to make a manual, textbook, or other functional and useful document "free" in the sense of freedom: to assure everyone the effective freedom to copy and redistribute it, with or without modifying it, either commercially or non-commercially. Secondly, this License preserves for the author and publisher a way to get credit for their work, while not being considered responsible for modifications made by others.

This License is a kind of "copyleft", which means that derivative works of the document must themselves be free in the same sense. It complements the GNU General Public License, which is a copyleft license designed for free software.

We have designed this License to use it for manuals for free software, because free software needs free documentation: a free program should come with manuals providing the same freedoms that the software does. But this License is not limited to software manuals; it can be used for any textual work, regardless of subject matter or whether it is published as a printed book. We recommend this License principally for works whose purpose is instruction or reference.

#### 1. APPLICABILITY AND DEFINITIONS

This License applies to any manual or other work, in any medium, that contains a notice placed by the copyright holder saying it can be distributed under the terms of this License. Such a notice grants a world-wide, royalty-free license, unlimited in duration, to use that work under the conditions stated herein. The "Document", below, refers to any such manual or work. Any member of the public is a licensee, and is addressed as "you". You accept the license if you copy, modify or distribute the work in a way requiring permission under copyright law.

A "Modified Version" of the Document means any work containing the Document or a portion of it, either copied verbatim, or with modifications and/or translated into another language.

A "Secondary Section" is a named appendix or a front-matter section of the Document that deals exclusively with the relationship of the publishers or authors of the Document to the Document's overall subject (or to related matters) and contains nothing that could fall directly within that overall subject. (Thus, if the Document is in part a textbook of mathematics, a Secondary Section may not explain any mathematics.) The relationship could be a matter of historical connection with the subject or with related matters, or of legal, commercial, philosophical, ethical or political position regarding them.

The "Invariant Sections" are certain Secondary Sections whose titles are designated, as being those of Invariant Sections, in the notice that says that the Document is released under this License. If a section does not fit the above definition of Secondary then it is not allowed to be designated as Invariant. The Document may contain zero Invariant Sections. If the Document does not identify any Invariant Sections then there are none.

The "Cover Texts" are certain short passages of text that are listed, as Front-Cover Texts or Back-Cover Texts, in the notice that says that the Document is released under this License. A Front-Cover Text may be at most 5 words, and a Back-Cover Text may be at most 25 words.

A "Transparent" copy of the Document means a machine-readable copy, represented in a format whose specification is available to the general public, that is suitable for revising the document straightforwardly with generic text editors or (for images composed of pixels) generic paint programs or (for drawings) some widely available drawing editor, and that is suitable for input to text formatters or for automatic translation to a variety of formats suitable for input to text formatters. A copy made in an otherwise Transparent file format whose markup, or absence of markup, has been arranged to thwart or discourage subsequent modification by readers is not Transparent. An image format is not Transparent if used for any substantial amount of text. A copy that is not "Transparent" is called "Opaque".

Examples of suitable formats for Transparent copies include plain ASCII without markup, Texinfo input format, LaTeX input format, SGML or XML using a publicly available DTD, and standard-conforming simple HTML, PostScript or PDF designed for human modification. Examples of transparent image formats include PNG, XCF and JPG. Opaque formats include proprietary formats that can be read and edited only by proprietary word processors, SGML or XML for which the DTD and/or processing tools are not generally available, and the machine-generated HTML, PostScript or PDF produced by some word processors for output purposes only.

The "Title Page" means, for a printed book, the title page itself, plus such following pages as are needed to hold, legibly, the material this License requires to appear in the title page. For works in formats which do not have any title page as such, "Title Page" means the text near the most prominent appearance of the work's title, preceding the beginning of the body of the text.

A section "Entitled XYZ" means a named subunit of the Document whose title either is precisely XYZ or contains XYZ in parentheses following text that translates XYZ in another language. (Here XYZ stands for a specific section name mentioned below, such as "Acknowledgements", "Dedications", "Endorsements", or "History".) To "Preserve the Title" of such a section when you modify the Document means that it remains a section "Entitled XYZ" according to this definition.

The Document may include Warranty Disclaimers next to the notice which states that this License applies to the Document. These Warranty Disclaimers are considered to be included by reference in this License, but only as regards disclaiming warranties: any other implication that these Warranty Disclaimers may have is void and has no effect on the meaning of this License.

## 2. VERBATIM COPYING

You may copy and distribute the Document in any medium, either commercially or non-commercially, provided that this License, the copyright notices, and the license notice saying this License applies to the Document are reproduced in all copies, and that you add no other conditions whatsoever to those of this License. You may not use technical measures to obstruct or control the reading or further copying of the copies you make or distribute. However, you may accept compensation in exchange for copies. If you distribute a large enough number of copies you must also follow the conditions in section 3.

You may also lend copies, under the same conditions stated above, and you may publicly display copies.

## 3. COPYING IN QUANTITY

If you publish printed copies (or copies in media that commonly have printed covers) of the Document, numbering more than 100, and the Document's license notice requires Cover Texts, you must enclose the copies in covers that carry, clearly and legibly, all these Cover Texts: Front-Cover Texts on the front cover, and Back-Cover Texts on the back cover. Both covers must also clearly and legibly identify you as the publisher of these copies. The front cover must present the full title with all words of the title equally prominent and visible. You may add other material on the covers in addition. Copying with changes limited to the covers, as long as they preserve the title of the Document and satisfy these conditions, can be treated as verbatim copying in other respects.

If the required texts for either cover are too voluminous to fit legibly, you should put the first ones listed (as many as fit reasonably) on the actual cover, and continue the rest onto adjacent pages.

If you publish or distribute Opaque copies of the Document numbering more than 100, you must either include a machine-readable Transparent copy along with each Opaque copy, or state in or with each Opaque copy a computer-network location from which the general network-using public has access to download using public-standard network protocols a complete Transparent copy of the Document, free of added material. If you use the latter option, you must take reasonably prudent steps, when you begin distribution of Opaque copies in quantity, to ensure that this Transparent copy will remain thus accessible at the stated location until at least one year after the last time you distribute an Opaque copy (directly or through your agents or retailers) of that edition to the public.

It is requested, but not required, that you contact the authors of the Document well before redistributing any large number of copies, to give them a chance to provide you with an updated version of the Document.

## 4. MODIFICATIONS

You may copy and distribute a Modified Version of the Document under the conditions of sections 2 and 3 above, provided that you release the Modified Version under precisely this License, with the Modified Version filling the role of the Document, thus licensing distribution and modification of the Modified Version to whoever possesses a copy of it. In addition, you must do these things in the Modified Version:

- A. Use in the Title Page (and on the covers, if any) a title distinct from that of the Document, and from those of previous versions (which should, if there were any, be listed in the History section of the Document). You may use the same title as a previous version if the original publisher of that version gives permission.
- B. List on the Title Page, as authors, one or more persons or entities responsible for authorship of the modifications in the Modified Version, together with at least five of the principal authors of the Document (all of its principal authors, if it has fewer than five), unless they release you from this requirement.
- C. State on the Title page the name of the publisher of the Modified Version, as the publisher.
- D. Preserve all the copyright notices of the Document.
- E. Add an appropriate copyright notice for your modifications adjacent to the other copyright notices.
- F. Include, immediately after the copyright notices, a license notice giving the public permission to use the Modified Version under the terms of this License, in the form shown in the Addendum below.
- G. Preserve in that license notice the full lists of Invariant Sections and required Cover Texts given in the Document's license notice.
- H. Include an unaltered copy of this License.
- I. Preserve the section Entitled "History", Preserve its Title, and add to it an item stating at least the title, year, new authors, and publisher of the Modified Version as given on the Title Page. If there is no section Entitled "History" in the Document, create one stating the title, year, authors, and publisher of the Document as given on its Title Page, then add an item describing the Modified Version as stated in the previous sentence.
- J. Preserve the network location, if any, given in the Document for public access to a Transparent copy of the Document, and likewise the network locations given in the Document for previous versions it was based on. These may be placed in the "History" section. You may omit a network location for a work that was published at least four years before the Document itself, or if the original publisher of the version it refers to gives permission.
- K. For any section Entitled "Acknowledgements" or "Dedications", Preserve the Title of the section, and preserve in the section all the substance and tone of each of the contributor acknowledgements and/or dedications given therein.
- L. Preserve all the Invariant Sections of the Document, unaltered in their text and in their titles. Section numbers or the equivalent are not considered part of the section titles.

- M. Delete any section Entitled "Endorsements". Such a section may not be included in the Modified Version.
- N. Do not retitle any existing section to be Entitled "Endorsements" or to conflict in title with any Invariant Section.
- O. Preserve any Warranty Disclaimers.

If the Modified Version includes new front-matter sections or appendices that qualify as Secondary Sections and contain no material copied from the Document, you may at your option designate some or all of these sections as invariant. To do this, add their titles to the list of Invariant Sections in the Modified Version's license notice. These titles must be distinct from any other section titles.

You may add a section Entitled "Endorsements", provided it contains nothing but endorsements of your Modified Version by various parties—for example, statements of peer review or that the text has been approved by an organization as the authoritative definition of a standard.

You may add a passage of up to five words as a Front-Cover Text, and a passage of up to 25 words as a Back-Cover Text, to the end of the list of Cover Texts in the Modified Version. Only one passage of Front-Cover Text and one of Back-Cover Text may be added by (or through arrangements made by) any one entity. If the Document already includes a cover text for the same cover, previously added by you or by arrangement made by the same entity you are acting on behalf of, you may not add another; but you may replace the old one, on explicit permission from the previous publisher that added the old one.

The author(s) and publisher(s) of the Document do not by this License give permission to use their names for publicity for or to assert or imply endorsement of any Modified Version.

## 5. COMBINING DOCUMENTS

You may combine the Document with other documents released under this License, under the terms defined in section 4 above for modified versions, provided that you include in the combination all of the Invariant Sections of all of the original documents, unmodified, and list them all as Invariant Sections of your combined work in its license notice, and that you preserve all their Warranty Disclaimers.

The combined work need only contain one copy of this License, and multiple identical Invariant Sections may be replaced with a single copy. If there are multiple Invariant Sections with the same name but different contents, make the title of each such section unique by adding at the end of it, in parentheses, the name of the original author or publisher of that section if known, or else a unique number. Make the same adjustment to the section titles in the list of Invariant Sections in the license notice of the combined work.

In the combination, you must combine any sections Entitled "History" in the various original documents, forming one section Entitled "History"; likewise combine any sections Entitled "Acknowledgements", and any sections Entitled "Dedications". You must delete all sections Entitled "Endorsements".

## 6. COLLECTIONS OF DOCUMENTS

You may make a collection consisting of the Document and other documents released under this License, and replace the individual copies of this License in the various documents with a single copy that is included in the collection, provided that you follow the rules of this License for verbatim copying of each of the documents in all other respects.

You may extract a single document from such a collection, and distribute it individually under this License, provided you insert a copy of this License into the extracted document, and follow this License in all other respects regarding verbatim copying of that document.

## 7. AGGREGATION WITH INDEPENDENT WORKS

A compilation of the Document or its derivatives with other separate and independent documents or works, in or on a volume of a storage or distribution medium, is called an "aggregate" if the copyright resulting from the compilation is not used to limit the legal rights of the compilation's users beyond what the individual works permit. When the Document is included in an aggregate, this License does not apply to the other works in the aggregate which are not themselves derivative works of the Document.

If the Cover Text requirement of section 3 is applicable to these copies of the Document, then if the Document is less than one half of the entire aggregate, the Document's Cover Texts may be placed on covers that bracket the Document within the aggregate, or the electronic equivalent of covers if the Document is in electronic form. Otherwise they must appear on printed covers that bracket the whole aggregate.

## 8. TRANSLATION

Translation is considered a kind of modification, so you may distribute translations of the Document under the terms of section 4. Replacing Invariant Sections with translations requires special permission from their copyright holders, but you may include translations of some or all Invariant Sections in addition to the original versions of these Invariant Sections. You may include a translation of this License, and all the license notices in the Document, and any Warranty Disclaimers, provided that you also include the original English version of this License and the original versions of those notices and disclaimers. In case of a disagreement between the translation and the original version of this License or a notice or disclaimer, the original version will prevail.

If a section in the Document is Entitled "Acknowledgements", "Dedications", or "History", the requirement (section 4) to Preserve its Title (section 1) will typically require changing the actual title.

## 9. TERMINATION

You may not copy, modify, sublicense, or distribute the Document except as expressly provided for under this License. Any other attempt to copy, modify, sublicense or distribute the Document is void, and will automatically terminate your rights under this License. However, parties who have received copies, or rights, from you under this License will not have their licenses terminated so long as such parties remain in full compliance.

## 10. FUTURE REVISIONS OF THIS LICENSE

The Free Software Foundation may publish new, revised versions of the GNU Free Documentation License from time to time. Such new versions will be similar in spirit to the present version, but may differ in detail to address new problems or concerns. See <http://www.gnu.org/copyleft/ 7>.

Each version of the License is given a distinguishing version number. If the Document specifies that a particular numbered version of this License "or any later version" applies to it, you have the option of following the terms and conditions either of that specified version or of any later version that has been published (not as a draft) by the Free Software Foundation. If the Document does not specify a version number of this License, you may choose any version ever published (not as a draft) by the Free Software Foundation.

#### ADDENDUM: How to use this License for your documents

```
Copyright (c) YEAR YOUR NAME.  
Permission is granted to copy, distribute and/or modify this document  
under the terms of the GNU Free Documentation License, Version 1.2  
or any later version published by the Free Software Foundation;  
with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts.  
A copy of the license is included in the section entitled "GNU  
Free Documentation License".
```

If you have Invariant Sections, Front-Cover Texts and Back-Cover Texts, replace the "with...Texts." line with this:

```
with the Invariant Sections being LIST THEIR TITLES, with the  
Front-Cover Texts being LIST, and with the Back-Cover Texts being LIST.
```

If you have Invariant Sections without Cover Texts, or some other combination of the three, merge those two alternatives to suit the situation.

If your document contains nontrivial examples of program code, we recommend releasing these examples in parallel under your choice of free software license, such as the GNU General Public License, to permit their use in free software.