



SUSE Multi-Linux Manager 5.1

Reference Guide

Chapter 1. 序文

Reference + SUSE Multi-Linux Manager 5.1

This document is divided into several sections:

- **Web UI Reference:** Organized to mirror the structure of the SUSE Multi-Linux Manager Web UI, this section allows you to quickly find relevant information while navigating the interface.
- **spacecmd Reference:** A comprehensive guide to the **spacecmd** command-line interface. It includes an **alphabetized list** of all available commands along with their correct usage.
- **Command Line Tools:** An overview of the various **command-line utilities** available in SUSE Multi-Linux Manager, helping you streamline administrative tasks.

発行日: 2025-12-12

+ + + + + + + + + + + + + + + + + + +

Copyright © 2011–2025 SUSE LLC and contributors. All rights reserved. この文書は、GNUフリー文書ライセンスのバージョン1.2または(オプションとして)バージョン1.3の条項に従って、複製、頒布、および/または改変が許可されています。ただし、この著作権表示およびライセンスは変更せずに記載すること。ライセンスバージョン1.2のコピーは、**Legal > License**セクションに含まれています。

SUSEの商標については、<https://www.suse.com/company/legal/>を参照してください。その他の第三者のすべての商標は、各社の所有に帰属します。商標記号(®、™など)は、SUSEおよび関連会社の商標を示します。アスタリスク(*)は、第三者の商標を示します。本書のすべての情報は、細心の注意を払って編集されています。しかし、このことは絶対に正確であることを保証するものではありません。SUSE LLC、その関係者、著者、翻訳者のいずれも誤りまたはその結果に対して一切責任を負いかねます。

Contents

| | |
|----------------------------------------------|----|
| 1. 序文 | 1 |
| 2. WebUI Reference | 13 |
| 2.1. Home Menu | 13 |
| 2.1.1. Home Overview | 13 |
| 2.1.2. 通知メッセージ | 13 |
| 2.1.3. User Account Menu | 13 |
| 2.1.4. My Preferences | 14 |
| 2.1.5. My Organization | 15 |
| 2.2. Systems Menu | 16 |
| 2.2.1. Systems List | 17 |
| 2.2.2. システムグループ | 19 |
| 2.2.3. システムセットマネージャ | 20 |
| 2.2.4. Bootstrapping | 23 |
| 2.2.5. プロキシ設定 | 24 |
| 2.2.6. Advanced Search | 24 |
| 2.2.7. アクティベーションキー | 25 |
| 2.2.8. Stored Profiles | 25 |
| 2.2.9. カスタムシステム情報 | 25 |
| 2.2.10. Autoinstallation Menu | 25 |
| 2.2.11. 仮想ホストマネージャ | 27 |
| 2.3. System Details | 27 |
| 2.3.1. 概要 | 28 |
| 2.3.2. ソフトウェア | 32 |
| 2.3.3. 設定 | 35 |
| 2.3.4. Provisioning | 36 |
| 2.3.5. Groups | 37 |
| 2.3.6. Audit | 37 |
| 2.3.7. States | 38 |
| 2.3.8. Formula | 39 |
| 2.3.9. Ansible | 40 |
| 2.3.10. Events | 41 |
| 2.3.11. プロキシ | 41 |
| 2.4. Salt Menu | 42 |
| 2.4.1. キー | 42 |
| 2.4.2. リモートコマンド | 42 |
| 2.4.3. Formula カタログ | 42 |
| 2.5. Images Menu | 43 |
| 2.5.1. Image List | 43 |
| 2.5.2. Images Build | 43 |
| 2.5.3. Images Profiles | 44 |
| 2.5.4. Images Stores | 44 |
| 2.6. Patches Menu | 44 |
| 2.6.1. Patch Details | 44 |
| 2.6.2. Patch List | 45 |
| 2.6.3. Advanced Search for Patches | 46 |
| 2.6.4. Manage Patches | 47 |
| 2.6.5. Clone Patches | 47 |
| 2.7. Software Menu | 48 |
| 2.7.1. Channel Details | 48 |
| 2.7.2. Channel List Menu | 49 |
| 2.7.3. Package Search | 50 |
| 2.7.4. Manage Menu | 51 |
| 2.7.5. Distribution Channel Mapping | 52 |
| 2.8. Content Lifecycle Management Menu | 52 |
| 2.8.1. Projects | 53 |
| 2.8.2. フィルタ | 53 |
| 2.9. Audit Menu | 53 |

| | |
|--------------------------------------------------------------------------------------------|-----------|
| 2.9.1. CVE 監査 | 53 |
| 2.9.2. サブスクリプションマッチング | 54 |
| 2.9.3. OpenSCAP Menu | 57 |
| 2.10. Configuration Menu | 58 |
| 2.10.1. Configuration Overview | 59 |
| 2.10.2. チャンネル | 60 |
| 2.10.3. ファイル | 62 |
| 2.10.4. Systems Menu | 63 |
| 2.11. Schedule Menu | 64 |
| 2.11.1. Pending Actions | 64 |
| 2.11.2. 定期的なアクション | 65 |
| 2.11.3. Completed Actions | 65 |
| 2.11.4. Failed Actions | 66 |
| 2.11.5. Archived Actions | 67 |
| 2.11.6. Action Chains | 67 |
| 2.11.7. メンテナンスウィンドウ | 67 |
| 2.12. Users Menu | 67 |
| 2.12.1. User Details | 67 |
| 2.12.2. User List | 69 |
| 2.12.3. System Group Configuration | 70 |
| 2.13. Admin Menu | 70 |
| 2.13.1. セットアップウィザード | 70 |
| 2.13.2. 組織 | 72 |
| 2.13.3. ユーザー | 72 |
| 2.13.4. PAYG | 72 |
| 2.13.5. Manager Configuration | 72 |
| 2.13.6. Task Schedules | 75 |
| 2.13.7. タスクエンジンの状態 | 75 |
| 2.13.8. Show Tomcat Logs | 75 |
| 2.14. Help Menu | 76 |
| 2.14.1. ドキュメンテーション | 76 |
| 2.14.2. Release Notes | 76 |
| 2.14.3. API Menu | 76 |
| 3. spacecmd Reference | 77 |
| 3.1. Configuring spacecmd | 77 |
| 3.1.1. Setup spacecmd credentials | 77 |
| 3.1.2. spacecmd quiet mode | 78 |
| 3.1.3. spacecmd help | 78 |
| 3.2. help | 79 |
| 3.3. history | 82 |
| 3.4. Troubleshooting spacecmd | 82 |
| 3.4.1. Creating a distribution where spacecmd sets localhost instead of FQDN | 82 |
| 3.4.2. spacecmd not accepting commands or options | 82 |
| 3.4.3. spacecmd caching problems | 83 |
| 3.5. spacecmd Functions | 83 |
| 3.5.1. アクティベーションキー | 83 |
| 3.5.2. api | 88 |
| 3.5.3. clear | 89 |
| 3.5.4. clear_caches | 89 |
| 3.5.5. configchannel | 89 |
| 3.5.6. cryptokey | 92 |
| 3.5.7. custominfo | 93 |
| 3.5.8. ディストリビューション | 93 |
| 3.5.9. errata | 94 |
| 3.5.10. filepreservation | 96 |
| 3.5.11. get | 97 |
| 3.5.12. group | 97 |
| 3.5.13. kickstart | 99 |
| 3.5.14. list_proxies | 106 |
| 3.5.15. login | 106 |

| | |
|-------------------------------------------------------------|------------|
| 3.5.16. logout | 106 |
| 3.5.17. org | 106 |
| 3.5.18. パッケージ | 108 |
| 3.5.19. proxy_container_config | 109 |
| 3.5.20. repo | 111 |
| 3.5.21. report | 112 |
| 3.5.22. scap | 114 |
| 3.5.23. スケジュール | 114 |
| 3.5.24. snippet | 117 |
| 3.5.25. ソフトウェアチャンネル | 118 |
| 3.5.26. ssm | 123 |
| 3.5.27. システム | 124 |
| 3.5.28. toggle | 137 |
| 3.5.29. user | 138 |
| 3.5.30. whoami | 140 |
| 3.5.31. whoamitalkingto | 140 |
| 3.5.32. Miscellaneous Help Topics | 141 |
| 4. Command Line Tools | 142 |
| 4.1. Synchronization CLI Tools | 142 |
| 4.1.1. Synchronize SCC Repositories With mgr-sync | 143 |
| 4.1.2. Synchronize Repositories with spacewalk-repo-sync | 144 |
| 4.1.3. 同期のトラブルシューティング | 145 |
| 4.2. Channel Management CLI Tools | 146 |
| 4.2.1. Manage Channels with spacewalk-remove-channel | 146 |
| 4.3. Bootstrapping Command Line Tools | 147 |
| 5. GNU Free Documentation License | 148 |

Chapter 2. WebUI Reference

2.1. Home Menu

The **Home** section is a dashboard that contains a summary of your current SUSE Multi-Linux Manager status, including tasks, client information, and critical security updates.

2.1.1. Home Overview

The **Home › Overview** section is a dashboard that contains a summary of your current SUSE Multi-Linux Manager status, including tasks, client information, and critical security updates.

2.1.2. 通知メッセージ




The **Home › Notification Messages** section shows all current messages produced by SUSE Multi-Linux Manager. By default, messages will remain current for thirty days. After this period, messages are deleted whether or not they are marked as read.

To see unread messages, navigate to the **Unread Messages** tab. To see all messages, navigate to the **All Messages** tab.

Click [**Refresh**] to update the list.

Perform bulk actions by checking messages in the list. Click [**Delete selected messages**] to bulk delete messages. Click [**Mark selected as read**] to bulk read messages.

表 1. Notification Message Severity Statuses

| Icon | Description | Example |
|-------------------------------------------------------------------------------------|-------------|----------------------------------------|
|  | Information | Client onboarding has failed. |
|  | Warning | Channel synchronization has completed. |
|  | Error | Channel synchronization has failed. |

2.1.3. User Account Menu

The **Home › User Account** section allows you to change user account preferences.

2.1.3.1. My Account

The **Home › User Account › My Account** section allows you to change user account preferences.

Modify your personal information, such as name, password, and title from the **Home › User Account › My Account** page. To modify this information, make the changes in the appropriate text fields and click the [**Update**] button at the bottom.

If you forget your password or username, navigate to Web UI sign in page, click [**About**], and click [**Lookup Login/Password**]. Enter the username or email address, and click [**Send Password**] or [**Send Login**] to have the missing information sent to you.

2.1.3.2. Addresses

The **Home** > **User Account** > **Addresses** section allows you set your mailing, billing, and shipping addresses, and associated phone numbers.

Click [**Fill in this address**] or [**Edit this address**] below the address to be modified or added, make your changes, and click [**Update**].

2.1.3.3. Change Email

The **Home** > **User Account** > **Change Email** section allows you to set the email SUSE Multi-Linux Manager sends notifications to.

Enter your new email address and click the [**Update**] button. Invalid email addresses, including those ending in **@localhost** are filtered and rejected.

If you would like to receive email notifications about patch alerts or daily summaries for your systems, ensure you have checked the **Receive email notifications** option in **Home** > **My Preferences** section.

2.1.3.4. Account Deactivation

The **Home** > **User Account** > **Account Deactivation** section allows you to cancel your SUSE Multi-Linux Manager user account.

When you click [**Deactivate Account**] your user account will be deleted, you will be signed out, and you will not be able to sign back in.

If you do this by accident, you will need to contact your SUSE Multi-Linux Manager Administrator to reactivate your user account.



- If you are the only SUSE Multi-Linux Manager Administrator for your organization, you can not deactivate your account.

2.1.4. My Preferences

The **Home** > **My Preferences** section allows you to configure SUSE Multi-Linux Manager Web UI options.

表 2. Home Preferences

| Option | Description | Default |
|--------------------|-----------------------------------------------------------------------------------------|---------|
| Email Notification | Receive email for client and Taskomatic notifications, including a daily summary email. | Checked |

| Option | Description | Default |
|-----------------------------------------|---------------------------------------------------------------------------------------------|--------------------------|
| SUSE Multi-Linux Manager List Page Size | Maximum number of items that can appear in a list on a single page. | 25 entries |
| "Overview" Start Page | Select the information panes to display on the Home › Overview page. | All checked |
| Time Zone | Set your local timezone. | System timezone |
| Interface Language | Set the language to use in the Web UI. | Default language |
| Style Theme | Set the style theme to use in the Web UI. | susemanager-light |
| CSV Files | Select whether to use comma or semi-colon delimiters when producing downloadable CSV files. | Comma |

For information about changing the default preferences, see **Administration › Users**.

2.1.5. My Organization

The **Home › My Organization** section allows you to configure your current organization.

For more information about organizations, see **Administration › Organizations**.

2.1.5.1. Organization Configuration

The **Home › My Organization › Configuration** section allows you to configure your current organization.

表 3. Organization Configuration Options

| Option | Description | Default |
|--------------------------------------|-----------------------------------------------------------------------------------------------|-----------|
| Enable staging contents | For clients in this organization, allow content staging by default. | Unchecked |
| Enable Errata E-mail Notifications | For users in this organization, send email notifications when errata (patches) are available. | Checked |
| Enable Upload of Detailed SCAP Files | Allow detailed SCAP content files to be uploaded for auditing. | Unchecked |
| Allow Deletion of SCAP Results | Allow SCAP results to be deleted after the audit is complete. | Checked |

| Option | Description | Default |
|-----------------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------|---------|
| Allow Deletion After | The number of days after an SCAP audit is complete, that results can be deleted. | 90 days |
| Synchronize patches on Content Lifecycle Management build | Controls whether the patch attributes and affected packages should be synchronized to cloned patches when building a content Project | Checked |

- コンテンツステージングの詳細については、**Administration** › **Content-staging**を参照してください。
- For more information about OpenSCAP, see **Administration** › **Openscap**.
- For more information about organizations, see **Administration** › **Organizations**.
- For more information about Content Lifecycle Management, see **Administration** › **Content-lifecycle**.

2.1.5.2. Organization Trusts

The **Home** › **My Organization** › **Organization Trusts** section shows the trusts that you have established within your organization. This section also shows the channels that are available to other users through trusts.

For more information about organization trusts, see **Administration** › **Organizations**.

2.1.5.3. Organization Configuration Channels

The **Home** › **My Organization** › **Configuration Channels** section shows the configuration channels available within your organization. Configuration channels can be created in the SUSE Multi-Linux Manager Web UI by navigating to **Configuration** › **Channels**. Apply configuration channels to your organization using the SUSE Multi-Linux Manager Web UI.

For more information about organizations, see **Administration** › **Organizations**.

2.2. Systems Menu

The **Systems** section allows you to manage your client systems.

The **Systems** menu contains submenu entries in the left navigation bar and as its overview page displays the **Systems** › **System List** › **All** listing with all client systems registered to the SUSE Multi-Linux Manager Server.

This listing contains information about the clients, including available software updates, extra packages (otherwise often referenced as non-compliant packages), and the base channel they are subscribed to.

All the submenu entries:

- [System List - Reference › Systems](#)
- [System Groups - Reference › Systems](#)
- [System Set Manager - Reference › Systems](#)
- [Bootstrapping - Reference › Systems](#)
- [Proxy Configuration - Reference › Systems](#)
- [Advanced Search - Reference › Systems](#)
- [Activation Keys - Reference › Systems](#)
- [Stored Profiles - Reference › Systems](#)
- [Custom System Info - Reference › Systems](#)
- [Autoinstallation - Reference › Systems](#)
- [`Virtual Host Managers - Reference › Systems`](#)

Click the name of a client to go to that client system's **Details** overview page and all its tabs and subtabs. For more information about the **System Details** overview page in the Web UI, see [Reference › Systems](#).

Check a client to add it to the system set manager. For more information about the system set manager, see [Client-configuration › System-set-manager](#).

Click [[Add Systems](#)] to go to [Systems › Bootstrapping](#). For more about bootstrapping new clients, see [Reference › Systems](#).

For more information about managing clients, see [Client-configuration › Client-config-overview](#).

2.2.1. Systems List

The [Systems › System List](#) section lists all clients available in your SUSE Multi-Linux Manager environment.

For more information about managing clients, see [Client-configuration › Client-config-overview](#).

The [Systems › System List](#) section is split into submenus:

2.2.1.1. すべて

The [Systems › System List › All](#) section lists every client that you have permission to manage.

2.2.1.2. Physical Systems

The [Systems › System List › Physical Systems](#) section lists every client that is installed on physical hardware.

2.2.1.3. Unprovisioned Systems

The **Systems › System List › Unprovisioned Systems** section lists every bare metal client that the SUSE Multi-Linux Manager Server is aware of, but has not yet been registered.

For more information about bare metal clients, see **Client-configuration › Autoinst-intro**.

2.2.1.4. Out of Date

The **Systems › System List › Out of Date** section lists every client that has available updates.

For more information about managing client updates, see **Client-configuration › Package-management**.

2.2.1.5. Requiring Reboot

The **Systems › System List › Requiring Reboot** section lists every client that requires rebooting.

2.2.1.6. Non Compliant

The **Systems › System List › Non Compliant** section lists every client that has non-compliant packages installed. Packages are considered non-compliant if they have been installed from a source other than SUSE Multi-Linux Manager. In the list, the **Extra Packages** column shows the number of non-compliant packages on the client. If there is at least one non-compliant package, you can click the number to display listings of those non-compliant packages per system.

2.2.1.7. Without System Type

The **Systems › System List › Without System Type** section lists every client that does not have a base system type recorded.

For more information about system types, see **Client-configuration › System-types**.

2.2.1.8. Ungrouped

The **Systems › System List › Ungroups** section lists every client that is not assigned to a system group.

For more information about system groups, see **Client-configuration › System-groups**.

2.2.1.9. 無効

The **Systems › System List › Inactive** section lists every client that has not checked in with the the SUSE Multi-Linux Manager Server in 24 hours or more.

サーバへのクライアント接続の詳細については、**Client-configuration › Contact-methods-intro**を参照してください。

For more information on troubleshooting inactive clients, see **Administration › Troubleshooting**.

2.2.1.10. Recently Registered

The **Systems** › **System List** › **Recently Registered** section lists every client that has registered within a given period. Select the period to view from the **View systems registered** field.

2.2.1.11. プロキシ

The **Systems** › **System List** › **Proxy** section lists every client that is registered as a proxy.

2.2.1.12. Duplicate Systems

The **Systems** › **System List** › **Duplicate Systems** section lists clients that share IP addresses, host names, or MAC addresses. Use the tabs to compare clients.

2.2.1.13. System Currency

The **Systems** › **System List** › **System Currency** section lists all clients with information about available updates, and provides a currency score for each. You can use the currency score to determine in which order clients should be updated. A score with a larger number indicates that a client is not current, and might require critical updates.

2.2.1.14. システムの種類

The **Systems** › **System List** › **System Types** section lists every client, their base system type, add-on system type, and base channel. It also gives a count of clients of each system type.

For more information about system types, see **Client-configuration** › **System-types**.

2.2.2. システムグループ

The **Systems** › **System Groups** section displays the list of system groups in your organization.

Click the name of a group to work with it, or to add or delete clients in the group.

The list shows an icon if there are updates available for any of the clients in the group. Click the icon to see more information about the updates available.

表 4. Update Status Icons

| Icon | Description | Action Required |
|------|-------------------------|------------------------------------------------------------------|
| ☑ | No applicable updates | All clients in this group are up to date |
| ⚠ | Updates available | One or more clients have updates ready to install |
| ❗ | Security updates needed | One or more clients have security updates that must be installed |

| Icon | Description | Action Required |
|------|----------------|----------------------------------------------------|
| ? | Status unknown | Displaying status of available updates is disabled |

For more information about system groups, see [Client-configuration > System-groups](#).

2.2.3. システムセットマネージャ

The **Systems > System Set Manager** section allows you to manage clients that you have added to the system set manager.

システムセットマネージャの詳細については、[Client-configuration > System-set-manager](#)を参照してください。

2.2.3.1. System Set Manager Overview

The **Systems > System Set Manager > Overview** section allows you to manage clients that you have added to the system set manager (SSM). You can also access this page by clicking the **systems selected** icon in the top menu bar.

For more information about SSM, see [Client-configuration > System-set-manager](#).

The **Systems > Systems Set Manager** menu is split into tabs:

2.2.3.1.1. 概要

This section provides quick access to all the of the SSM tabs.

2.2.3.1.2. システム

This section lists all clients currently in the SSM. It provides information about the updates available, when the client last checked in, the registered base channel, and system type. Click the client name to see more information.

2.2.3.1.3. パッチ

This section lists all patches available for upgrade on clients currently in the SSM. Click the number in the **Affected** column to see which clients a patch applies to. To perform upgrades, check the patches to apply and click [\[Apply Patches \]](#).

For more information about patch management, see [Client-configuration > Patch-management](#).

2.2.3.1.4. パッケージ

This section is split into subtabs.

The **Packages > Upgrade** subtab lists all packages available for upgrade on clients currently in the SSM. To perform upgrades, check the packages to upgrade and click [\[Upgrade Selected Packages \]](#).

The **Packages › Install** subtab allows you to install new packages on all clients currently in the SSM. To install packages, click the base channel that contains the package, check the packages to install, and click [**Install Selected Packages**].

The **Packages › Remove** subtab allows you to remove packages from all clients currently in the SSM. If clients in the SSM have different versions of a package installed, multiple versions are available in the list. To remove packages, select the packages to remove, and click [**Remove Selected Packages**].

For more information about package management, see **Client-configuration › Package-management**.

2.2.3.1.5. Groups

This section lists all system groups clients currently available in your organization. Click [**Create Group**] to create a new system group. For each group in the list, check **Add** to add all clients in the SSM to the group, check **Remove** to remove all clients in the SSM from the group, or check **No Change** to leave group assignments as they are. Click [**Alter Membership**] to change group assignments.

For more information about system groups, see **Client-configuration › System-groups**.

2.2.3.1.6. チャンネル

This section lists all base channels clients currently subscribed to by clients currently in the SSM. You can change all clients subscribed to a current base channel to a new base channel, by selecting the new base channel and following the prompts.

For more information about software channels, see **Client-configuration › Channels**.

For more information about using the SSM to change base channels, see **Client-configuration › System-set-manager**.

2.2.3.1.7. 設定

This section is split into subtabs.

The **Configuration › Deploy Files** subtab lists all configuration files available for deployment. Click the number in the **Systems** column to see which clients are currently subscribed to the configuration file. To assign a configuration file to the clients currently in the SSM, check the configuration file, and click [**Schedule File Deploy**].

The **Configuration › Compare Files** subtab lists all configuration files available for comparison. This compares the configuration file deployed on a client with the configuration file stored on the SUSE Multi-Linux Manager Server. Click the number in the **Systems** column to see which clients are currently subscribed to the configuration file. To compare configuration files, check the configuration files to compare, and click [**Schedule File Comparison**].

The **Configuration › Subscribe to Channels** subtab lists all configuration channels available for subscription. To subscribe the clients in the SSM to a new configuration channel, check the configuration channel, click [**Continue**], and follow the prompts.

The **Configuration › Unsubscribe from Channels** subtab lists all configuration channels clients in the SSM are currently subscribed to. To unsubscribe the clients in the SSM from a configuration channel, check the configuration channel and click [**Unsubscribe Systems**].

The **Configuration › Enable Configuration** subtab lists clients in the SSM that are capable of using configuration management, but have not yet been enabled. To enable clients in the SSM to use configuration management, check the client and click [**Enable Configuration Management**].

設定管理の詳細については、**Client-configuration › Configuration-management**を参照してください。

2.2.3.1.8. Provisioning

This section is split into subtabs.

The **Provisioning › Autoinstallation** subtab lists all clients in the SSM available for autoinstallation, with their base channel. To schedule autoinstallation, select an autoinstallable type, click [**Continue**] and follow the prompts.

The **Provisioning › Power Management Configuration** subtab allows you to configure power management for the clients in the SSM. For more information about power management, see **Client-configuration › Power-management**.

The **Provisioning › Power Operations** subtab allows you to power on, power off, or reboot the clients in the SSM. For more information about power management, see **Client-configuration › Power-management**.

For more information about autoinstallation, see **Client-configuration › Autoinst-intro**.

2.2.3.1.9. States

For Salt clients, the **States › Highstate** subtab allows you to apply the highstate to all clients in the SSM.

2.2.3.1.10. Audit

For more information about auditing, see **Administration › Auditing**.

2.2.3.1.11. Misc

This section is split into subtabs.

The **Misc › Preferences** subtab allows you to configure the custom information, system types, and system preferences for the clients in the SSM.

The **Misc › Hardware** subtab allows you to schedule a hardware profile refresh for the clients in the SSM.

The **Misc › Software** subtab allows you to schedule a package profile refresh for the clients in the SSM.

The **Misc › Remote Command** subtab allows you to schedule a remote command to be executed on the clients in the SSM.

The **Misc › Custom Values** subtab allows you to set or remove custom key values for the clients in the SSM.

The **Misc › Reboot** subtab allows you to schedule a reboot for the clients in the SSM.

The **Misc › Transfer** subtab allows you to move clients in the SSM to a new organization.

The **Misc › Delete** subtab allows you to delete the system profiles of clients in the SSM.

2.2.3.2. System Set Manager Task Log

The **Systems › System Set Manager › Task Log** section shows all actions applied to clients that you have added to the system set manager (SSM). The SSM Task Log lists all actions performed against clients currently in SSM. Click an entry to see more information about the action.

This section is divided into tabs:

The **All** tab lists all actions that have been performed. The **In Progress** tab lists all actions that are currently in progress. The **Completed** tab lists all actions that have been completed.

For more information about SSM, see **Client-configuration › System-set-manager**.

2.2.4. Bootstrapping

The **Systems › Bootstrapping** section allows you to register a single Salt client.

表 5. Bootstrap Options

| Option | Description | Default |
|-----------------------|--------------------------------------------------------------------------------------------------------|----------|
| Host | The hostname of the client to be registered | - |
| SSH port | The port on the client that allows SSH access | 22 |
| User | The user name to use to log in to the client | root |
| Authentication Method | Choose Password for simple authentication, or SSH Private Key to use SSH authentication. | Password |
| Password | The password to use to log in to the client | - |
| SSH Private Key | Upload the SSH Private Key to use to log in to the client | - |

| Option | Description | Default |
|--------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------|-----------|
| SSH Private Key Passphrase | The passphrase for the SSH Private Key, or leave blank for no password. | - |
| Activation Key | The activation key to use to register the client. Leave blank to use the universal default activation key, or select None for no activation key. | None |
| Proxy | The proxy to which the client should be registered. Leave blank if you are not using a proxy. | None |
| Disable SSH strict host key checking | Automatically adds the host key to the known hosts file | Checked |
| Manage system completely via SSH | Uses only the SSH contact method | Unchecked |



SSH秘密鍵は、ブートストラッププロセス中のみ保存されます。秘密鍵は、ブートストラップが完了するとすぐにSUSE Multi-Linux Managerサーバから削除されます。

When you have completed the details of the client you want to register, click [**Bootstrap**]. When the client has completed registering, navigate to **Systems > System List** to see details.

For more information about bootstrapping, see **Client-configuration > Registration-webui**.

2.2.5. プロキシ設定

The **Systems > Proxy Configuration** section allows you to configure proxy clients.

2.2.6. Advanced Search

The **Systems > Advanced Search** section allows you to perform global searches within your SUSE Multi-Linux Manager environment. Searches can include network information, hardware devices, location, activity, packages, details, DMI information, and hardware.

Type your search term in the **Search For** field. Select the criterion to search by, use the radio buttons to specify whether you want to query all systems or only those in the **System Set Manager**, and click the [**Search**] button. Check **Invert Result** to list only results that do not match the specified criteria.

When you add a distribution, synchronize channels, or register a client, it can take several minutes for it to be indexed and appear in search results. To force a rebuild of the search index, use this command at the command prompt:

```
rhncleanindex
```

2.2.7. アクティベーションキー

The **Systems › Activation Keys** section lists the current activation keys for your organization.

The universal default activation key, if set, is automatically used for all clients registered to your organization, unless you specify a different activation key.

The list of activation keys shows the name and description for each key, and how many times the key has been used. It also shows if the key is currently enabled for your organization. Click the key description to see more information about the activation key.

Click [**Update Activation Keys**] to refresh the list with recent changes.

Click [**Create Key**] to create a new activation key.

アクティベーションキーの詳細については、**Client-configuration › Activation-keys**を参照してください。

2.2.8. Stored Profiles

The **Systems › Stored Profiles** section lists the stored profiles for your organization. Profiles can be used to compare packages installed on clients.

Click the name of a profile to see more information about the packages in the profile, or to edit the name or description.

For more information about using profiles to compare packages, see **Client-configuration › Package-management**.

2.2.9. カスタムシステム情報

The **Systems › Custom System Info** section lists the custom system information available to clients in your organization.

Click [**Create Key**] to create a new custom system key. Click the key label to see more information, and to edit the value.

For more information about custom system information, see **Client-configuration › Custom-info**.

2.2.10. Autoinstallation Menu

The **Systems › Autoinstallation** section allows you to manage clients for autoinstallation.

For more information about autoinstallation, see **Client-configuration › Autoinst-intro**.

2.2.10.1. Autoinstallation Overview

The **Systems › Autoinstallation › Overview** section displays an overview of your autoinstallation settings, including clients that are autoinstalling, or scheduled to be autoinstalled.

The **Systems › Details › Overview** subtab is split into sections:

Autoinstallation Summary

This section lists the AutoYaST and Kickstart profiles currently available, and the number of clients installed with each profile.

Autoinstallation Actions

This section provides links to actions related to autoinstallation. You can also access these using the **Systems › Autoinstallation** menu.

Systems Currently Autoinstalling

This section lists all clients that are currently autoinstalling, along with their status.

Systems Scheduled to be Autoinstalled

This section lists all clients that are scheduled for autoinstallation, along with their status.

Click [**Create Kickstart Profile**] to create a new Kickstart profile. Click [**Upload Kickstart/AutoYaST File**] to upload a new autoinstallation file.

For more information about autoinstallation, see **Client-configuration › Autoinst-intro**.

2.2.10.2. 自動インストールプロファイル

The **Systems › Autoinstallation › Profiles** section lists all profiles currently available. The list includes information about if the profile is active, the distribution it is based on, and if it being managed with SUSE Multi-Linux Manager.

Click the name of a profile to see more information.

Click [**Create Kickstart Profile**] to create a new Kickstart profile. Click [**Upload Kickstart/AutoYaST File**] to upload a new autoinstallation file.

For more information about autoinstallation profiles, see **Client-configuration › Autoinst-profiles**.

2.2.10.3. GPG and SSL Keys

The **Systems › Autoinstallation › GPG and SSL Keys** section lists all GPG public keys and SSL certificates currently available. Click the name of a key to see more information.

Click [**Create Stored Key/Cert**] to store a new GPG key or SSL certificate.

For more information about GPG keys and SSL certificates, see **Client-configuration › Gpg-keys**.

2.2.10.4. ディストリビューション

The **Systems › Autoinstallation › Distributions** section lists the available autoinstallable distributions.

Click the distribution name to see more information. Click [**Create Distribution**] to create a new

autoinstallable distribution.

For more information about autoinstallable distributions, see **Client-configuration › Autoinst-distributions**.

2.2.10.5. File Preservation

The **Systems › Autoinstallation › File Preservation** section allows you to store lists of files, to use them in Kickstart profiles later on.

Click [**Create File Preservation List**] to create a new list.

For more information about Kickstart file preservation, see **Client-configuration › Autoinst-profiles**.

2.2.10.6. Autoinstallation Snippets

The **Systems › Autoinstallation › Autoinstallation Snippets** section allows you to store code snippets, to use them in autoinstallation profiles later on.

Click [**Create Snippet**] to create a new code snippet.

For more information about autoinstallation profiles using these code snippets, see **Client-configuration › Autoinst-profiles**.

2.2.11. 仮想ホストマネージャ

The **Systems › Virtual Host Managers** section lists the active virtual host managers (VHMs).

VHMs can be used to collect private or public cloud instances and organize them into virtualization groups.

For more information about VHMs, see **Client-configuration › Vhm**.

2.3. System Details

The **System Details** section allows you to manage the details for a chosen client. To get to this section, click the name of a client anywhere throughout the Web UI to see the relevant **System Details** page for the client.

The **System Details** section is divided into tabs and subtabs. Each tab and some subtabs have own sections in this document.

The **Systems › Details › Overview** subtab is displayed by default. Which tabs are available is dependent on the **system type** of the client you have selected. Most often, the following are available:

- **Details** - xref:reference:systems/system-details/sd-details.adoc
- **Software** - xref:reference:systems/system-details/sd-software.adoc

- **Configuration** - xref:reference:systems/system-details/sd-configuration.adoc
- **Provisioning** - xref:reference:systems/system-details/sd-provisioning.adoc
- **Groups** - xref:reference:systems/system-details/sd-groups.adoc
- **Audit** - xref:reference:systems/system-details/sd-audit.adoc
- **States** - xref:reference:systems/system-details/sd-states.adoc
- **Formulas** - xref:reference:systems/system-details/sd-formulas.adoc
- **Recurring Actions** - xref:reference:systems/system-details/sd-recurring-actions.adoc
- **Events** - xref:reference:systems/system-details/sd-events.adoc

For more information about managing clients, see **Client-configuration** › **Client-config-overview**.

2.3.1. 概要

The **Systems** › **Details** › **Overview** section shows a summary of information about the selected client, including the current system status. This subtab is displayed by default when you click the name of a client anywhere throughout the Web UI.

Click [**Delete System**] to delete the system profile. Deleting a system profile will not destroy or remove the client, but you will no longer be able to manage it with SUSE Multi-Linux Manager. If you delete a system profile by mistake, you can re-register the client using bootstrap.

The **Systems** › **Details** › **Overview** subtab is split into sections:

2.3.1.1. System Status

The section shows the current status of the client. If no action is required for this client, the status is **System is up to date**.

If the client has new software ready for installation, the status is **Software Updates Available**, along with details of updates. Apply updates by navigating to **System Details** › **Packages**.

2.3.1.2. System Info

This section shows general information about the client.

表 6. System Info Columns

| Column Name | Description | Conditions |
|-------------|---------------------------------------------------------------------------|----------------------------------------------|
| Hostname | The hostname used by the client with the SUSE Multi-Linux Manager Server. | - |
| FQDN | The fully qualified domain name of the client. | Shown only if it differs from the host name. |
| IP address | The IPv4 IP address of the client. | - |

| Column Name | Description | Conditions |
|------------------------------------|------------------------------------------------------------------------------------------|-----------------------------------------------------|
| IPv6 address | The IPv6 IP address of the client. | - |
| Minion ID | The minion ID of the client. | Salt clients only. |
| Virtualization | The type of virtualization used by the client. | Virtualized clients only. |
| UUID | The universally unique identifier. | - |
| Kernel | The kernel currently in use on the client. | - |
| SUSE Multi-Linux Manager System ID | A unique identifier generated by SUSE Multi-Linux Manager when the client is registered. | - |
| Activation key | The activation key used to register the client. | Remains blank if the client has not been activated. |
| Installed products | Software products currently installed on the client. | - |

For more information about system locks, see **Client-configuration › System-locking**.

2.3.1.3. Subscribed Channels

This section shows the base and child software channels this client is subscribed to.

Click [**Alter Channel Subscriptions**] to change the channel subscriptions for this client. Click a channel name to go to the **Channel Details** tab.

For more information about channels, see **Client-configuration › Channels**.

2.3.1.4. System Events

This section shows the most recent system events for this client.

表 7. System Events Columns

| Column Name | Description |
|-------------|-------------------------------------------------------------------------------------------------|
| Checked in | The time that the client last successfully checked in with the SUSE Multi-Linux Manager Server. |
| Registered | The time that the client registered with SUSE Multi-Linux Manager. |
| Last booted | The time that the client was most recently started or rebooted. |

Click [**Schedule system reboot**] to set a time for the client to reboot. The reboot will occur when the

client next checks in with the SUSE Multi-Linux Manager Server after the scheduled time. For more on task scheduling, see **Administration › Task-schedules**.

2.3.1.5. System Properties

This section shows further information about the client.

表 8. System Properties Columns

| Column Name | Description |
|----------------------|----------------------------------------------------------------------------------------------------------------------------------------|
| System types | Lists the system type applied to the client. Client type is Salt |
| Notifications | Lists the current notification options for this client. |
| Contact method | The method used by this client to communicate with the SUSE Multi-Linux Manager Server. |
| Auto patch update | Indicates if the client is receiving patches automatically. |
| Maintenance Schedule | Specifies which maintenance schedule is assigned to this client. |
| System name | The system name of the client. By default, this is the host name, but it can be changed. |
| Description | General information about the client. By default, this is automatically gathered when the client is registered, but it can be changed. |
| Location | The physical location of the client. By default, this is not set, but it can be added. |

接続メソッドの詳細については、**Client-configuration › Contact-methods-intro**を参照してください。

Click [**Edit These Properties**] to go to **System Details › Details › Properties** subtab.

2.3.1.6. プロパティ

The **Systems › Details › Properties** section allows you to edit details about the selected client, including the system name and details.

表 9. Edit System Details Settings

| Setting Name | Description | Default Setting |
|--------------|---------------------------------------------------------------------------|-----------------------------|
| System Name | The name of the system to use within the SUSE Multi-Linux Manager Web UI. | The hostname of the client. |

| Setting Name | Description | Default Setting |
|---------------------|--------------------------------------------------------------------------------------------------------|---------------------------------------------------------------------------------------------------------------------|
| Base System Type | The type of base system used by the client. | Shown for information only, you cannot edit this. |
| Add-on System Types | Check additional system types to add features such as build hosts, or monitoring. | Only available system types for this client are shown. |
| Notifications | Check to receive notifications of updates or patches, and to include this client in the daily summary. | Checked. |
| Auto Patch Update | Check to have available patches automatically applied. | Unchecked. |
| Description | This field can contain any text you want. | The operating system, release, and architecture of the system when it first registered to SUSE Multi-Linux Manager. |
| Facility Address | The physical location of the client. | Blank |

2.3.1.7. Remote Command

The **Systems › Details › Remote Command** section allows you to run commands remotely on the selected client.

Before doing so, you must first configure the system to accept such commands. For more information about using remote commands, see **Administration › Actions**.

2.3.1.8. Reactivation

The **Systems › Details › Reactivation** section allows you to generate reactivation keys for the selected client. Reactivation keys can be used once only to re-register the client and regain all SUSE Multi-Linux Manager settings.

For more information about reactivation keys, see **Client-configuration › Activation-keys**.

2.3.1.9. Hardware

The **Systems › Details › Hardware** section shows detailed hardware information about the selected client, including architecture, networking, and memory.

Click **[Schedule Hardware Refresh]** to update this page with the latest hardware information. To change the primary network interface on the client, select the correct interface in the **Primary Network Interface** field in the **Networking** section. For clients with multiple fully qualified domain names (FQDNs) configured, change the primary FQDN by selecting it in the **Primary FQDN** field in the **Networking** section. Click **[Update Properties]** to save your changes.



Refreshing hardware information happens once a month automatically when the **system-profile-refresh** taskomatic job runs.

2.3.1.10. Transfer

The **Systems › Details › Transfer** section allows you to move clients between organizations. Clients can only belong to one organization at any time.



You will need to establish trust between organizations when you want to move clients. For more information, see **Administration › Organizations**.

To move a client to a different organization, select the name of the organization in the **Organization Name** field, and click [**Migrate System**].



When you move a client to a different organization, channel assignments, system group membership, custom data values, configuration channels, reactivation keys, and snapshots are deleted from the system configuration. You will need to set these values again when the move is complete.

2.3.1.11. メモ

The **Systems › Details › Notes** section lists notes about the selected client.

Click [**Create Note**] to create a new note. Give your note a subject, and add any details you require. Click [**Create**] to save the note.

Notes are listed in the table with a time stamp of when they were last edited. Click the subject of a note to edit or delete it.

2.3.1.12. Custom Info

The **Systems › Details › Custom Info** section lists the custom system information that has been applied to the selected client.

Click [**Create Value**] to apply a new custom system key to the client. Click the key label to see more information, and to edit the value.

For more information about custom system information, see **Client-configuration › Custom-info**.

2.3.2. ソフトウェア

The **Systems › Software** section allows you to manage software on the selected client.

2.3.2.1. パッチ

The **Systems › Software › Patches** section displays a list of all patches currently available to the selected client.

To apply a patch, check it in the list and click [**Apply Patches**] to schedule the installation. The **Status**

column in the list shows whether an update has been scheduled. Click the status for more information about the action.

For more information about patching, see **Client-configuration › Patch-management**.

2.3.2.2. パッケージ

The **Systems › Software › Packages** section allows you to manage packages on the selected client.

Click [**Update Package List**] to refresh the list of available packages.

The **Systems › Software › Packages** tab is split into subtabs:

List/Remove

Lists all packages currently installed on the selected client. Click the name of a package to see more information. To uninstall packages, check the package in the list and click [**Remove Packages**].

アップグレード

Lists packages that have newer versions available. Click the name of a package to see more information. To upgrade packages, check the package in the list and click [**Upgrade Packages**]. Any EULAs will be accepted automatically.

Install

Lists packages that are available for installation on the selected client. Click the name of a package to see more information. To install packages, check the package in the list and click [**Install Selected Packages**]. Any EULAs will be accepted automatically.

プロファイル

Compare packages installed on the selected client with a stored profile, or with packages installed on another client. When the comparison is made, you can choose to modify the selected client to match. To compare with a stored profile, select the profile and click [**Compare**]. To compare with another client, select the client name and click [**Compare**].

Non Compliant

Lists packages that are installed on the selected client, but are not available in any of the subscribed software channels.

For more information about packages, see **Client-configuration › Package-management**.

2.3.2.3. AppStreams

The **Systems › Software › AppStreams** section allows you to manage the list of enabled AppStream modules on the selected client.



The **Systems › Software › AppStreams** tab is only available if the client has any AppStream channels assigned.

The page lists all the AppStream modules that are currently available to the client. After modifying the

selection of enabled modules, click **[Apply Changes]** to schedule an action to update the selection on the client.

For more information about managing AppStreams on a client, see **Client-configuration › Appstreams**.

2.3.2.4. ソフトウェアチャンネル

The **Systems › Software › Software Channels** section allows you to manage the software channels on the current client. For more information about software channels, see **Client-configuration › Channels**.

The **Systems › Software › Software Channels** subtab is split into sections:

2.3.2.4.1. ベースチャンネル

This section shows the base channel the current client is subscribed to, as well as any other available base channels.

Click the chain icon next to a base channel to see more information about the channel. Change the base channel subscription by selecting the new base channel, and click **[Next]** to schedule the change.

The child channels associated with the base channel are populated in the **Child Channels** section. Mandatory child channels are pre-selected. Toggle the **include recommended** switch to also select recommended child channels.



デフォルトでは、クローンベンダチャンネルは元のベンダチャンネルと一致し、依存関係を自動的に選択します。 `/etc/rhn/rhn.conf`に次のオプションを追加することにより、クローンチャンネルの自動選択を無効にできます。

```
java.cloned_channel_auto_selection = false
```

In general, channel pre-selection is necessary to avoid problems with missing dependencies for a given channel but it only works flawlessly for vendor channels. For cloned channels, SUSE Multi-Linux Manager relies on the channel label to define dependencies and use it in auto selection. This heuristic sometimes lead to either selecting unnecessary child channels or overlooking some essential ones. Users should exercise caution and pay attention in such case that correct channels are selected.

For Salt clients, apply the highstate after changing software channels.

2.3.2.4.2. 子チャンネル

This section shows the software product and child channels associated with the currently selected base channel.

Hover over the information icon next to the channel name to see channel requirements. Click the chain icon next to a base channel to see more information about the channel.

Child channels are can be either recommended or mandatory. Mandatory child channels must be installed for the selected client to use the associated base channel. Recommended child channels should be installed to provide additional packages. All other child channels are optional.

Check the child channels you want to install, and click **[Next]** to schedule the change.

2.3.2.5. 製品移行

The **Systems > Software > Product Migration** section allows you to upgrade clients to the latest service pack of their underlying operating system. Product migration also allows you to migrate openSUSE Leap to the corresponding SLE SP level or clients such as Red Hat Enterprise Linux, or CentOS to SUSE Liberty Linux. Check the product version you want to upgrade the client to, and click **[Select Channels]**.

For more information about service pack upgrades, see **Client-configuration > Client-upgrades-product-migration**.

2.3.3. 設定

The **Systems > Configuration** section allows you to manage the configuration files for the selected client. Configuration files are distributed with a configuration channel.

設定チャンネルの詳細については、**Client-configuration > Configuration-management**を参照してください。

The **Systems > Configuration** tab is split into subtabs:

2.3.3.1. 概要

The **Systems > Configuration > Overview** subtab is split into sections:

Configuration Overview

This section contained the total number of available configuration files, and channel subscriptions. Click the name of a configuration file or channel to see more information. Click **[Subscribe to channels]** to subscribe to additional configuration channels.

Recent Events

This section shows when the configuration channels was most recently deployed on the selected client. It also shows the most recent time that a comparison was performed.

Configuration Actions

This section allows you to deploy or to compare configuration channels on the selected client.

2.3.3.2. View Files

The **Systems > Configuration > View Files** subtab is split into subtabs for centrally managed, and locally managed configuration files.

The **Centrally-Managed Files** and **Locally-Managed Files** subtabs both show a list of all available configuration files. Click **[View]** to see details about the configuration file. Click **[Compare]** to compare the configuration file to other files, or to various revisions of itself. Click the configuration channel name to see more information about the channel that contains this configuration file. Click the revision number to see additional details about the configuration file.

2.3.3.3. Deploy Files

The **Systems › Configuration › Deploy Files** shows a list of available configuration files that can be deployed on the selected client.

2.3.3.4. Compare Files

The **Systems › Configuration › Compare Files** shows a list of available configuration files that can be compared to SUSE Multi-Linux Manager managed configuration files. Check the configuration file to compare and click **[Compare Files]** to schedule a comparison. Click the revision number to see additional details about the configuration file. Click the configuration channel name to see more information about the channel that contains this configuration file.

2.3.3.5. 設定チャンネルの管理

The **Systems › Configuration › Manage Configuration** subtab is split into subtabs:

List/Unsubscribe from Channels

This section shows the list of currently subscribed channels. To unsubscribe the selected client from a configuration channel, check the channel, and click **[Unsubscribe]**. Click the configuration channel name to see more information about the channel that contains this configuration file.

Subscribe to Channels

This section shows the list of configuration channels that are available for the selected client to subscribe to. To subscribe the selected client to a configuration channel, check the channel, and click **[Continue]**.

View/Modify Rankings

This section shows the currently subscribed configuration channels, in ranked order. Where settings conflicts occur between configuration channels, channels closer to the top of the list take precedence. To complete subscription to a configuration channel, review the rankings, adjust as necessary using the up and down arrows, and click **[Update Channel Rankings]**.

2.3.4. Provisioning

The **Systems › Provisioning** section allows you to manage provisioning for the selected client. This includes managing and scheduling autoinstallation and booting the selected client.

The **Systems › Provisioning** tab is split into subtabs:

2.3.4.1. 自動インストール

This section displays a list of the available autoinstallation profiles for the selected client. Select a time and date for autoinstallation to re-install the client.

For more information about autoinstallation, see **Client-configuration › Autoinst-intro**.

2.3.4.2. 電源管理

This section allows you to power on, power off, and reboot the selected client.

This feature uses either the IPMI or Redfish protocol and is managed using a Cobbler profile. The selected client must have a power management controller supporting one of these protocols. For Redfish, ensure you can establish a valid SSL connection between the client and the SUSE Multi-Linux Manager Server.

Complete the details for the power management server, and click the appropriate button for the action to take. Click **[Get status]** to determine if the client is currently running. Click **[Save only]** to save the details without taking any action.

Click **[Remove Cobbler System Profile]** to remove the current client's system profile from Cobbler. For more information about unattended provisioning with Cobbler, see **Client-configuration › Autoinst-unattended**.

For more information about power management, see **Client-configuration › Power-management**.

2.3.5. Groups

The **Systems › Groups** section shows the system groups the selected client is assigned to.

The **Systems › Groups** subtab is split into sections:

For more information about system groups, see **Client-configuration › System-groups**.

2.3.5.1. List/Leave

This section lists all groups that the selected client belongs to.

Click the group name to see more information about the system group. To remove the selected client from a system group, check the group, and click **[Leave Selected Groups]**.

2.3.5.2. 参加

This section lists all groups that are available for the selected client to subscribe to.

Click the group name to see more information about the system group. To join a system group, check the group, and click **[Join Selected Groups]**.

2.3.6. Audit

The **Systems › Audit** section displays the results of OpenSCAP scans that you have performed on the selected client.

The Security Certification and Authorization Package (SCAP) is a standardized compliance checking solution for enterprise-level Linux infrastructures. SUSE Multi-Linux Manager uses OpenSCAP to implement the SCAP specifications.

For more information about OpenSCAP, see **Administration › Openscap**.

The **Systems › Audit** subtab is split into sections:

2.3.6.1. List Scans

This section displays the results of openSCAP scans that have been performed on the selected client.

The table columns on this page are:

表 10. OpenSCAP Scan Results

| Name | Description |
|-------------------|----------------------------------------------------------------------|
| Xccdf Test Result | The name of the test result |
| Diff | FIXME |
| Completed | The time that the scan was completed |
| Compliance | The unweighted pass/fail ratio |
| P | The number of checks that passed |
| F | The number of checks that failed |
| E | The number of errors that occurred |
| U | The number of checks with an unknown status |
| N | The number of checks that were not applicable to the selected client |
| K | The number of checks not run |
| S | The number of checks that were not selected |
| I | The number of checks that have information available for review |
| X | The number of checks that reported a status of fixed |
| Total | The total number of checks run |

Click the name of a scan test result to see details about the result.

2.3.6.2. スケジュール

This section allows you to schedule a scan for the selected client.

2.3.7. States

The **Systems › States** section allows you to manage Salt states on the selected client. States provide

configuration templates for Salt clients. Applying the highstate applies all outstanding Salt states. This is only available for Salt clients.

For more information about Salt states, see **Specialized-guides › Salt**.

The **Systems › States** subtab is split into sections:

2.3.7.1. Highstate

This section provides details of the highstate for the selected client. It includes a state summary for the selected client, showing a list of states, formulas, and configuration channels. To schedule a time to apply the highstate, select the date and time and click **[Apply Hightstate]**. Toggle the **[Test mode]** switch to test the highstate before you apply it.

2.3.7.2. パッケージ

This section allows you to manage package states for the selected client. Package states determine which packages and versions should be installed on the selected client.

Use the search tool to search for the package you want to change. To set the package state to install the package, select **Installed** as the new state. To always upgrade the package to the latest version, select **latest**. Click **[Save]** to save the changes to the state. Click **[Apply changes]** to apply the new package state to the selected client.

Use the **Changes** subtab to see what changes will occur on the selected client when this state is applied.

2.3.7.3. Configuration Channels

This section allows you to manage configuration channels for the selected client.

Use the search tool to search for the configuration channel you want to manage. This section shows the list of configuration channels that are available for the selected client to subscribe to. To subscribe the selected client to a configuration channel, check the channel, and click **[Apply]**.

Use the **Changes** subtab to see what changes will occur on the selected client when this state is applied.

設定チャンネルの詳細については、**Client-configuration › Configuration-management**を参照してください。

2.3.8. Formula

The **Systems › Formulas** section allows you to manage Salt formulas on the selected client. This is only available for Salt clients.

This section lists all currently installed formulas. Check the formulas you want to apply, and click **[Save]**. When a formula is applied, it will create a new subtab. Navigate to the subtab to configure the formula on the selected client. After most formula actions, you will need to apply the highstate to pick up the changes.

For more information about formulas, see **Specialized-guides › Salt**.

2.3.9. Ansible

The **System Details** › **Ansible** tab allows you to use the Ansible features on the Control Node system.

The tab is split into the following subtabs:

Control Node

Fields for defining playbook directories and paths to inventory files on your Ansible Control Node.

Playbooks

Lists all playbooks in the defined paths. You can click a playbook to display its details or to schedule its execution.

Inventories

Lists all inventory files in the defined paths. Clicking an inventory file in the list introspects its contents.

For more information, see **Administration** › **Ansible-integration**.

2.3.9.1. 定期的なアクション

The **Systems** › **Recurring Actions** section allows you to manage recurring actions on the selected client. You can schedule an arbitrary set of Salt states or the highstate to be executed at desired intervals. This is only available for Salt clients.

For more information about Salt states, see **Specialized-guides** › **Salt**.

現在、SUSE Multi-Linux Managerは、次のアクションタイプを定期的なアクションとしてサポートしています。

- **Highstate:** Execute the highstate.
- **Custom state:** Execute a set of custom states. A custom state can be either an internal state provided by SUSE Multi-Linux Manager, or a configuration channel created by a user.

設定チャンネルの詳細については、**Client-configuration** › **Configuration-management**を参照してください。

2.3.9.1.1. Creating Recurring Actions

To create new schedules, click the **[Create]** icon on the top right corner. Choose a supported action type, give your recurring schedule a name, select a time and day for it to recur, and click **[Create Schedule]**. Toggle the **[Test mode]** switch to test the highstate before you apply it.

2.3.9.1.2. Recurring Action Details

View the details about an action from the action list. In the **Actions** column, click the **[Details]** icon for the action you are interested in.

2.3.9.1.3. Disabling Recurring Actions

Disabling an action stops the action recurring, but does not delete it. To disable a recurring action toggle the **Active** switch off. Enable them again by toggling the **Active** switch on. Disabled recurring actions remain in the list, but are not executed.

2.3.9.1.4. Editing Recurring Actions

In the **Actions** column, click the **[Edit]** icon for the action you want to change. On the **Schedule Recurring Action** page, the existing properties are pre-filled. Make your changes, and click **[Update Schedule]**.

2.3.9.1.5. Deleting Recurring Actions

Deleting an action permanently removes it. To start using the action again, you will need to create a new action. In the **Actions** column, click the **[Delete]** icon for the action you want to delete, and confirm the deletion.

For more information about recurring actions, see **Administration > Actions**.

2.3.10. Events

The **Systems > Events** section shows past, current, and scheduled actions for the selected client.

For more information about actions, see **Administration > Actions**.

The **Systems > Event** tab is split into subtabs:

2.3.10.1. Pending

This section shows actions that are scheduled, but have not yet started.

Click the name of an action to see more information. To cancel an action, check the action and click **[Cancel Selected Events]**.

2.3.10.2. History

This section shows actions that have been completed on the selected client.

Click the summary of an action to see more information.

2.3.11. プロキシ

The **Systems > System List > Proxy** section shows all clients connected to the selected client as a proxy. This is only available when the selected client is registered to SUSE Multi-Linux Manager as a proxy.

For more information about setting up a proxy, see **Installation-and-upgrade > Install-proxy**.

2.4. Salt Menu

The **Salt** section displays details of your Salt clients. You can use this menu to perform remote commands or define a state catalog for your Salt clients.

For more information about using Salt with SUSE Multi-Linux Manager, see **Specialized-guides › Salt**.

2.4.1. キー

The **Salt › Keys** section displays the key fingerprints of your current Salt clients.

Key fingerprints are exchanged between the SUSE Multi-Linux Manager Server and Salt clients to verify the identity of the server and the client. This prevents Salt clients from connecting to the wrong server.

Click [**Refresh**] to update the list. Click the name of a client to go to **Systems › Details** for that client.

表 11. Salt Keys List Columns

| Column | Description |
|-------------|-------------------------------------------------------------------------------------------------------------------------------------------------|
| Name | Name of the Salt client. |
| Fingerprint | Key fingerprint of the Salt client. |
| State | The status of the key exchange: accepted indicates that the client key has been verified by the SUSE Multi-Linux Manager Server. |
| Actions | Click the Delete icon to delete the client key from the server. Clients that have had their key deleted will need to be onboarded again. |

2.4.2. リモートコマンド

The **Salt › Remote Commands** section allows you to perform remote commands on one or more of your Salt clients. Remote commands allows you to issue commands to individual Salt clients, or to all clients that match a search term.

For more information about remote commands, see **Administration › Actions**.

2.4.3. Formula カタログ

The **Salt › Formula Catalog** section allows you to see which formulas are currently installed on your SUSE Multi-Linux Manager Server, and are available to be used on your Salt clients. Install and configure formulas by navigating to **Systems › Details** for the client you want to configure, and navigate to the **Formulas** tab.

For more information about SUSE Multi-Linux Manager formulas, see **Specialized-guides › Salt**.

2.5. Images Menu

The **Images** › **Image List** section displays your current operating system images.

For more information about images, see **Administration** › **Image-management**.

2.5.1. Image List

The **Images** › **Image List** section displays your current operating system images.

Click **[Import]** to import a new Docker image. You can only import new images created from a Docker image using this mechanism. To import images based on Kiwi instead, see **Administration** › **Image-management**.

Click **[Refresh]** to update the list.

Perform bulk actions by checking images in the list. Click **[Delete]** to bulk delete images.

表 12. Image List Columns

| Column | Description |
|----------------------|-------------------------------------------------------------------------------------------------------|
| Name | Name of the image. |
| Version and Revision | Version and revision of the image. |
| Updates | Any updates that are currently available for the image. |
| Patches and Packages | Any patches or packages that are currently available for the image. |
| Build | The current status of the build: Built , Scheduled , Building or Failed . |
| Last Modified | The time and date the image was last modified. |

For more information about images, see **Administration** › **Image-management**.

2.5.2. Images Build

The **Images** › **Build** section allows you to build operating system images for installing on clients.

表 13. Image Build Options

| Option | Description | Default |
|---------------|------------------------------------------------------------------------------------------------|---------|
| Image Profile | Select the image profile to use.
Manage image profiles at Images › Profiles . | Blank. |

| Option | Description | Default |
|------------|-----------------------------------------------------|-------------------------------|
| Build Host | Select the build host for the new image. | Blank. |
| Earliest | Schedule the time and date for the build to begin. | Current system time and date. |
| Add to | Select which action chain to add the build task to. | New action chain. |

Built images are listed in **Images › Image List**.

For more information about images, see **Administration › Image-management**.

2.5.3. Images Profiles

The **Images › Profiles** section displays your current image profiles.

Click **[Create]** to create a new image profile. Click **[Refresh]** to update the list.

Perform bulk actions by checking profiles in the list. Click **[Delete]** to bulk delete profiles.

For more information about images, see **Administration › Image-management**.

2.5.4. Images Stores

The **Images › Stores** section displays your current image stores.

Click **[Create]** to create a new image store. Click **[Refresh]** to update the list.

Perform bulk actions by checking images in the list. Click **[Delete]** to bulk delete image stores.

For more information about images, see **Administration › Image-management**.

2.6. Patches Menu

The **Patches** menu helps you find and manage available patches for your clients.

For more information about patching, see **Client-configuration › Patch-management**.

2.6.1. Patch Details

The **Patches › Patch List › Patch Details** section displays the details of a selected patch. Click the advisory number of a patch in the **Patch List** to see more information about the patch.

This section is divided into tabs.

2.6.1.1. 詳細

The **Details** tab shows the patch report provided by SUSE.

In the **Affected Channels** section, all channels that contain the affected package are listed. Click the channel name to go to **Software › Channel Details**.

For security patches, additional information is shown about the vulnerability, including the CVE and OVAL details.

If available, the original advisory provided by the vendor of the patch is shown in the section **Vendor Advisory**.

For more information about SUSE Update Advisories, see <https://www.suse.com/support/update/>.

2.6.1.2. パッケージ

The **Packages** tab provides links to each of the updated packages by channel. Click the name of a package to go to **Software › Channel Details**.

2.6.1.3. 影響を受けるシステム

The **Affected Systems** tab provides a list of installed clients that the patch affects. You can install updates from this tab.

Click the name of a client to go to **Systems › System Details**.

Each client in the list shows the current status of the patch on that client. This column identifies only the most recent action. Click the name of a status in the list to go to the **Action Details** page.

表 14. Client Update Status Icons

| Description | Action Required | N/A |
|----------------------------------------------|--------------------------------------------|----------------------------------------------------------------------|
| Check the status manually. | Pending | The client will be updated at the next synchronization. |
| Picked Up | The client is in the progress of updating. | Completed |
| The client successfully installed the patch. | Failed | The client attempted to install the patch, but encountered an error. |





2.6.2. Patch List

2.6.2.1. Relevant Patches

The **Patches › Patch List › Relevant** section displays a list of all patches released by SUSE that apply to your installed clients.

Each patch in the list shows a patch type, an advisory number, a short description, the number of clients in your network affected, and the date the patch was last updated. Click the advisory number to see more information about the patch. For more information about the **Patches › Patch List › Patch Details** section, see [xref:reference:patches/patch-details.adoc](#)

表 15. Patch Status Icons

| Icon | Description | Action Required |
|-----------------------------------------------------------------------------------|----------------------------------|-----------------|
|  | Bug fix | Recommended |
|  | Product enhancement advisory | Optional |
|  | Security update | Essential |
|  | Affects package management stack | Recommended |







To receive email when new patches are available, navigate to **Home › My Preferences** and check **Receive email notifications**.

2.6.2.2. All Patches

The **Patches › Patch List › All** section displays a list of all patches released by SUSE. Not all of the patches will apply to your clients.

Each patch in the list shows a patch type, an advisory number, a short description, the number of clients in your network affected, and the date the patch was last updated. Click the advisory number to see more information about the patch.

表 16. Patch Status Icons

| Icon | Description | Action Required |
|-------------------------------------------------------------------------------------|----------------------------------|-----------------|
|  | Bug fix | Recommended |
|  | Product enhancement advisory | Optional |
|  | Security update | Essential |
|  | Affects package management stack | Recommended |

For more information about patching, see **Client-configuration › Patch-management**.

2.6.3. Advanced Search for Patches

The **Patches › Advanced Search** section allows you to use advanced criteria to search for patches.

You can search for patches by looking for your search term in different fields:

表 17. Patch Advanced Search Options

| Option | Description | Example |
|----------------|-------------------------------------------------|----------------------|
| All Fields | Search in all fields | glibc |
| Patch Advisory | Search within the name or label fields | slessp1-glibc |
| Package Name | Search within the package name field only | kernel |
| CVE | Search within the CVE name or number field only | CVE-2006-4535 |

You can also search within different types of patches, or within a range of issue dates.

For more information about patching, see **Client-configuration › Patch-management**.

2.6.4. Manage Patches

The **Patches › Manage Patches** section shows you all custom patches.

Each patch in the list shows a patch type, an advisory name, a short description, and the date the patch was last updated. Click the advisory name to go to **Patches › Patch List › Patch Details** for the patch.

To create a new patch, click [**Create Patch**]. To delete a patch, select it in the list, and click [**Delete Patches**].



If you use SUSE Multi-Linux Manager with a proxy, manage patches only on the SUSE Multi-Linux Manager Server. The SUSE Multi-Linux Manager Proxy will receive updates from the server directly. If you manage patches on a proxy, the servers will be unable to synchronize correctly.

For more information about patching, see **Client-configuration › Patch-management**.

2.6.5. Clone Patches

The **Patches › Clone Patches** section allows you to create copies of existing patches to distribute to your clients.

To clone a patch, the patch must apply to one of your existing software channels. If the patch was part of a software channel that was cloned, then you can clone the patch from the cloned channel.

See all patches that are available for cloning by selecting the channel name in the **View patches potentially applicable to:** field, and click [**View**]. From the list, check the patch to clone, and click [**Clone Patch**]. You need to confirm the details to perform the clone.

2.7. Software Menu

The **Software** section allows you to view and manage software channels, repositories, and packages.

For more information about software channels, see **Client-configuration › Channels**.

2.7.1. Channel Details

The **Software › Channel List › Channel Details** section displays the details of a selected channel. Click the name of a channel in the **Channel List** to see more information about the channel.

This section is divided into tabs.

2.7.1.1. 詳細

The **Details** tab shows the basic channel details, including a description of the channel, and the dates it was last modified and built. This tab also provides contact information for the maintainer of the product and the GPG key details, where available.

2.7.1.2. Managers

The **Managers** tab shows which users are authorized to manage the selected channel. The list shows the username, real name, and email address of the channel manager, as well as the current status of the user.

Organization and Channel administrators can manage any channel. SUSE Multi-Linux Manager Administrators can change roles for specific users by clicking the username.

For more information about user management, see **Administration › Users**.

2.7.1.3. パッチ

The **Patches** tab shows all available patches for packages in the selected channel. The list displays the advisory type, names, synopsis, and the date the patch was last updated. Click the advisory name to go to the **Patch Details** page.

For more information about managing patches and packages, see **Client-configuration › Patch-management**.

2.7.1.4. パッケージ

The **Packages** tab shows all packages in the selected channel. The list shows the package name, summary, and the provider of the package. Click the package name to go to the **Package Details** page.

For more information about managing patches and packages, see **Client-configuration › Patch-management**.

2.7.1.5. Subscribed Systems

The **Subscribed Systems** tab shows the clients currently subscribed to the selected channel. The list shows the client name and type. Check a client in the list to add it to the system set manager. Click the client name to go to the **System Details** page.

システムセットマネージャの詳細については、**Client-configuration** › **System-set-manager**を参照してください。

2.7.1.6. Target Systems

The **Target Systems** tab shows the clients eligible for subscription to the selected channel. This tab is only available if the selected channel is a child channel. The list shows the client name and type, and the associated base channel.

To subscribe a client to the selected channel, check the client in the list, and click **[Confirm]**.

For more information about software channels, see **Client-configuration** › **Channels**.

2.7.1.7. AppStreams

The **AppStreams** tab is only visible for modular channels and it shows all the available modules in the channel. The list shows the module name and the streams available for the module. The default stream for each module is indicated with a highlighted color.

For more information about AppStreams and how to use them, see [administration:content-lifecycle-examples.pdf](#).

2.7.2. Channel List Menu

The **Software** › **Channel List** section allows you to view and manage software channels and packages on your clients.

For more information about software channels, see **Client-configuration** › **Channels**.

The **Software** › **Channel List** › **All** section displays a list of all software channels that are available to your organization.

Each software channel in the list shows a channel name, a provider, the number of packages and patches in the channel, and the number of clients currently subscribed to the channel. Click the plus sign next to the name of a parent channel to expand the entry and see all the related child channels. Click the channel name to see more information about the channel.

Within the **Software** › **Channel List** section you can select which subset of channels you would like to see by navigating to tabs, or the sub-menu items.

表 18. Channel List Filters

| Filter | Description |
|-------------|--------------------------------------------------------------------------------|
| All | All channels available to your organization. |
| SUSE | Channels provided by SUSE. |
| Popular | Channels most subscribed to by clients in your organization. |
| My Channels | Software channels that belong to your organization, including custom channels. |
| Shared | Channels shared with others in the organizational trust. |
| Retired | Channels that have reached end-of-life and no longer receive updates. |

For more information about software channels, see **Client-configuration › Channels**.

2.7.3. Package Search

The **Software › Package Search** section allows you to search all packages.

Enter your search term in the **Search For** field.

表 19. What to Search Options

| Option | Description |
|----------------------|---------------------------------------------------------------------------------------------|
| Free form | Performs a general search. Use keywords with this option to perform more specific searches. |
| Name only | Searches only in the names of packages. |
| Name and Summary | Searches within the name and one-line summary of packages. |
| Name and Description | Searches within names and long descriptions of packages. |

Check the **Channels relevant to your systems** option to search only channels available for your existing clients. Check the **Specific channel you have access to** option to search within a specific channel. Check the **Packages of a specific architecture** to search only for a particular hardware architecture.

You can perform more specific searches by using keywords in the **Search For** field and selecting the **Free Form** option.

表 20. Keyword Search Options

| Keyword | Description | Example |
|-------------|------------------------------------|-------------------------|
| name | Search package names | name:SUSE |
| version | Search for a package version | version:15 |
| filename | Search within package file names | filename:sles |
| description | Search within the long description | description:java |
| summary | Search within the one-line summary | summary:java |
| arch | Search for a package architecture | arch:x86_64 |

For example, if you want to search all SUSE Linux Enterprise packages that include **java** in the description and the summary, use this search:

```
summary:java and description:java
```

For more information about software channels, see **Client-configuration › Channels**.

2.7.4. Manage Menu

The **Software › Manage** section allows you to manage custom channels, packages, and repositories.

カスタムチャンネルの詳細については、**Administration › Custom-channels**を参照してください。

2.7.4.1. Manage Channels

The **Software › Manage › Channels** section allows you to manage custom channels.

Click [**Create Channel**] to create a new custom channel.

To clone an existing channel, click [**Clone Channel**] and select the channel to clone. You can choose to clone channel with or without all current patches, or select specific patches for inclusion.

カスタムチャンネルの詳細については、**Administration › Custom-channels**を参照してください。

2.7.4.2. Manage Packages

The **Software › Manage › Packages** section allows you to manage packages that are owned by your organization.

Select a channel from the drop-down box to see all packages related to that channel. If you have administration privileges within your organization, you can also delete packages.

- Orphaned packages are packages that are synchronized by SUSE Multi-Linux Manager, but not associated with a software channel. For handling those packages, see [client-](#)

[configuration:package-management.pdf](#).

- カスタムチャンネルの詳細については、**Administration** › **Custom-channels**を参照してください。

2.7.4.3. Manage Repositories

The **Software** › **Manage** › **Repositories** section allows you to manage custom or third-party package repositories and link the repositories to an existing channel.

Click [**Create Repository**] to create a new repository.

カスタムリポジトリおよびチャンネルの詳細については、**Administration** › **Custom-channels**を参照してください。

2.7.5. Distribution Channel Mapping

The **Software** › **Distribution Channel Mapping** section lists your defined default base channels. When you register a client for the first time, they will automatically be assigned to these software channels, in accordance with their architecture and operating system. Default channel mappings can be edited, but not deleted.

Click [**Create Distribution Channel Mapping**] to create a new channel map.

表 21. Distribution Channel Mapping Columns

| Column | Description |
|-----------------------|----------------------------------------------------------------------|
| Operating System | The client operating system this mapping applies to. |
| Release | The operating system release this mapping applies to. |
| Architecture | The client system architecture architecture this mapping applies to. |
| Channel Label | The label of the channel. |
| Organization Specific | Checked if this mapping applies only to the current organization. |

For more information about software channels, see **Client-configuration** › **Channels**.

2.8. Content Lifecycle Management Menu

In the **Content Lifecycle** section, you can customize and test packages before updating production clients.

コンテンツライフサイクル管理では、ソフトウェアチャンネルをソースとして選択し、必要に応じて環境に合わせて調整して、運用クライアントにインストールする前に徹底的にテストすることができます。

For more information about content lifecycle management, see **Administration › Content-lifecycle**.

2.8.1. Projects

In the **Content Lifecycle › Projects** section, you can create new content lifecycle management projects, and edit existing projects.

For more information about content lifecycle management, see **Administration › Content-lifecycle**.

2.8.2. フィルタ

In the **Content Lifecycle › Filters** section, you can create various types of filters. With the filters you control the content that is used when a content lifecycle project is built.

For more information about content lifecycle management, see **Administration › Content-lifecycle**.

2.9. Audit Menu

The **Audit** menu provides access to features for managing security updates on your clients. Audit tasks include finding and updating clients with the latest CVE patches, subscription matching, and managing OpenSCAP scans.

2.9.1. CVE 監査







The **Audit › CVE Audit** section shows you which CVEs have been applied to your clients. A CVE (common vulnerabilities and exposures) is a fix for a publicly known security vulnerability. It is important that you apply CVEs to your clients as soon as they become available.

Each CVE contains an identification number, a description of the vulnerability, and links to further information. CVE identification numbers use the form **CVE-YEAR-XXXX**.

Clients are listed with a patch status icon.

表 22. Patch Status Icons

| Icon | Description | Action Required |
|------|---------------------------------------------------------------------------------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------|
| ❗ | Affected, patches are not released for the CVE. | The client is affected by a vulnerability for which a patch has not yet been released. |
| ❗ | Affected, patches were released for the CVE but SUSE Multi-Linux Manager can't find them in any of the relevant channels. | The client is affected by a vulnerability that received a patch, but SUSE Multi-Linux Manager is unable to locate any of the patches in relevant channels. |

| Icon | Description | Action Required |
|-------------------------------------------------------------------------------------|-------------------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|  | Affected, only partial patches are available for the CVE. | The client is affected by a vulnerability and SUSE Multi-Linux Manager has patches for it, but applying the patches will only fix some of the vulnerable packages. |
|  | Affected, patches are available in channels that are not assigned | The client is affected by a vulnerability and SUSE Multi-Linux Manager has patches for it, but the channels offering the patches are not assigned to the client. |
|  | Affected, patches are available in a product migration target | The client is affected by a vulnerability and SUSE Multi-Linux Manager has patches for it, but applying the patch requires migrating the product to a newer version. |
|  | Affected, at least one patch is available in an assigned channel | The client is affected by the vulnerability and SUSE Multi-Linux Manager has patches available in a channel that is directly assigned to the client. |
|  | Not affected | The client is not affected because none of the CVE vulnerable packages are installed. |
|  | Patched | A patch has been successfully installed on the client. |

For more information about CVE auditing, see **Administration › Auditing**.

2.9.2. サブスクリプションマッチング

The **Audit › Subscription Matching** section provides reports that match your currently installed clients to your existing product subscriptions. Subscription matching reports provide information about clients that do not have a subscription, and subscription start and end dates.

表 23. Subscription Matching Options

| Column | Description |
|-------------|------------------------------------|
| Part Number | Identifier of the matched product |
| Description | Description of the matched product |

| Column | Description |
|---------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Policy | The type of subscription matched to the product |
| Matched/Total | The number of clients currently using the subscription, of the total available. If the subscription is fully matched, the quantity column value is highlighted. |
| Start Date | Start date of the subscription |
| End Date | End date of the subscription |

Table entries are highlighted if they are due to expire within three months. Table entries that have already expired are shown in grayscale.

For messages relating to subscription matching, navigate to the **Messages** tab.

表 24. Subscription Matching Messages

| Message | Type | Description | Action |
|--------------------------------------------------------------------------|---------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Unsupported part number detected | Debug | The detected part number is unknown or unsupported. | Call SUSE support and open a Service Request ticket to have the part number added to the product. |
| Physical system is reported as virtual guest, please check hardware data | Debug | A client is reporting as virtual, but could be a physical client. | Check the client hardware data. |
| Virtual guest has unknown host, assuming it is a physical system | Warning | A virtual client has an unknown host. During the matching process, it was treated as a physical system. This might translate into a wrong subscription assignment. | Check the virtual host manager (VHM) configuration to ensure it is reporting correctly. For Linux-based hosts using libvirt , check that the host is registered, and that the virtual host system type is set correctly. |

| Message | Type | Description | Action |
|----------------------------------------------------------------------------------------------|---------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------------------------------------|
| System has an unknown number of sockets, assuming 16 | Warning | Unable to determine how many CPUs a client has. SUSE Multi-Linux Manager used the default value of 16 CPUs every time the number was relevant for matching a subscription. This might translate into a wrong subscription assignment. | Schedule a hardware refresh on this client. |
| Two subscriptions with the same part number are in a bundle | Informational | Two subscriptions were identified to be part of a bundle and, as result, they were merged together during the computation process. | No actions needed. |
| Two subscriptions with the same part number (and other properties) have been merged together | Informational | Two subscription shared multiple common properties and they were merged together during the computation process. | No actions needed. |
| Pinned match adjusted due to merged subscriptions | Informational | A user defined pin was updated since the chosen subscription was merged with another one. | No actions needed. |
| Subscription with unsupported part number and no associated product has been ignored. | Informational | An unknown subscription without any associated product has been detected and it was ignored during the matching process. | No actions needed. |

To pin clients to a particular subscription, navigate to the **Pins** tab.

表 25. Pin Statuses

| Status | Description |
|-----------|-----------------------------------------------------|
| Satisfied | The client and subscription were matched correctly. |

| Status | Description |
|------------------|--------------------------------------------------------------|
| Not satisfied | The client was not successfully matched with a subscription. |
| Pending next run | Waiting for the next matcher run. |

For more information about subscription matching, see **Administration › Subscription-matching**.

2.9.3. OpenSCAP Menu

The **Audit › OpenSCAP** section displays the results of OpenSCAP scans that you have performed on your clients.

The Security Content Automation Protocol (SCAP) is a synthesis of interoperable specifications derived from community ideas. SUSE Multi-Linux Manager uses OpenSCAP to implement the SCAP specifications.

For more information about OpenSCAP, see **Administration › Openscap**.

2.9.3.1. OpenSCAP

The **Audit › OpenSCAP** section displays the results of OpenSCAP scans that you have performed on your clients.

The Security Certification and Authorization Package (SCAP) is a standardized compliance checking solution for enterprise-level Linux infrastructures. SUSE Multi-Linux Manager uses OpenSCAP to implement the SCAP specifications.

For more information about OpenSCAP, see **Administration › Openscap**.

2.9.3.2. All Scans

The **Audit › OpenSCAP** section displays the results of OpenSCAP scans that you have performed on your clients.


 The Security Content Automation Protocol (SCAP) is a synthesis of interoperable specifications derived from community ideas.

表 26. OpenSCAP Scan Details

| Name | Description | Evaluation Results |
|---------------|---------------------------------------|--------------------|
| System | The name of the scanned client. | |
| XCCDF Profile | The evaluated profile. | |
| Completed | The time that the scan was completed. | |

| Name | Description | Evaluation Results |
|--------------|---------------------------------------------------------------|------------------------------------------------------------------------------------------------------------|
| Satisfied | The total number of rules that have been satisfied. | A rule is satisfied if the result of the evaluation is Pass or Fixed . |
| Dissatisfied | The total number of rules that are not satisfied. | A rule is dissatisfied if the result of the evaluation is Fail . |
| Unknown | The total number of rules that were not able to be evaluated. | A rule is unknown if the result of the evaluation is Error , Unknown or Not checked . |



Rules can also return other results, including **Informational**, **Not Applicable**, or **Not Selected**. Rules that return these results are not shown in the scan results.

For more information about OpenSCAP, see **Administration › Openscap**.

2.9.3.3. XCCDF Diff

The **Audit › OpenSCAP › XCCDF Diff** section allows you to compare two OpenSCAP XCCDF scans.

For more information about OpenSCAP, see **Administration › Openscap**.

2.9.3.4. Advanced Search

The **Audit › OpenSCAP › Advanced Search** section allows you to search through OpenSCAP scans and results.

For more information about OpenSCAP, see **Administration › Openscap**.

2.10. Configuration Menu

The **Configuration** section provides access to features for managing the configuration of SUSE Multi-Linux Manager clients.



The **Configuration** menu is only available if you are signed in with a configuration administrator or SUSE Multi-Linux Manager administrator account.

Within the configuration pages, you can:

- manage clients using configuration files
- configure channels offering configuration files
- manage configuration files themselves

Centrally managed files are available to multiple clients, while locally managed files are available to individual clients only.

2.10.1. Configuration Overview

The **Configuration › Overview** section is a dashboard that contains a summary of the configuration files that are managed by your organization in SUSE Multi-Linux Manager. There are different panes listing files that are managed centrally in configuration channels and files that are managed locally with individual system profiles.

For more information about managing configuration files, see **Client-configuration › Configuration-management**.

Configuration Summary

Provides quick information about your configuration files. Click the blue text to the right to display:

- Systems with managed configuration files
- Configuration channels
- Centrally managed configuration files
- Locally managed configuration files

Configuration Actions

Configuration Actions offers direct access to the most common configuration management tasks:

- View clients with managed configuration files
- View all managed configuration files
- View all managed configuration channels
- Create a new configuration channel
- Enable configuration management on clients

Recently Modified Configuration Files

The list shows which files have changed when and to which channel they belong. If no files have been changed, no list appears.

表 27. Recently Modified Configuration Files Columns

| Column | Description |
|-----------------------|----------------------------------------------|
| Filename | Absolute filename of the configuration file. |
| Configuration Channel | Name of the configuration channel. |
| Modified | The time and date the file was modified. |

Click the name of a file to see its **Details** page. Click the channel name to see its **Channel Details** page.

Recently Scheduled Configuration File Deployments

Each scheduled action is listed along with the status of the action. Any scheduled configuration task, from enabling configuration management on a system to deploying a specific configuration file, is

displayed. Here you can quickly assess if all tasks have been successfully carried out or fix any problems.

+

表 28. Scheduled Configuration File Deployments Columns

| Column | Description |
|----------------------|--------------------------------------------------------------------------|
| System | Host name of the system where you want to deploy the configuration file. |
| Files to be Deployed | Number of files to be deployed. |
| Scheduled By | The user who scheduled the job. |
| Scheduled For | The time and date the file deployment will happen. |
| Status | Status of the deployment: Queued |

+ Clicking the blue status text displays the **System Details > Schedule** page for the specified system.

2.10.2. チャンネル

SUSE Multi-Linux Manager manages both central and local configuration channels and files. Central configuration management allows you to deploy configuration files to multiple systems, by using state channels. When you create a state channel, you can create or upload custom Salt states. For more information about custom states, see **Specialized-guides > Salt**.

Click the name of the configuration channel to see the details page for that channel. If you click the number of files in the channel, you are taken to the **List/Remove Files** page of that channel. If you click the number of systems subscribed to the configuration channel, you are taken to the **Configuration Channel Details > Systems > Subscribed Systems** page for that channel.

2.10.2.1. Configuration Channel Details

概要

The **Overview** page of the **Configuration Channel Details** page is divided into several panels:

チャンネルプロパティ[管理]

Edit the name, label, and description of the channel by clicking [**Edit Properties**].

チャンネル情報

Provides status information for the contents of the channel.

Configuration Actions

Provides access to the most common configuration tasks. For Salt clients, there is a link to edit the **init.sls** file.

This panel allows you to deploy, compare, and add and create files. Some action are only

available if you have files created and clients assigned to configuration channels.

List/Remove Files

This page only appears if there are files in the configuration channel. You can remove files or copy the latest versions into a set of local overrides or into other central configuration channels. Check the box next to files you want to manipulate, then click the action button at the bottom.

Add Files

The **Add Files** page has three subtabs of its own, which allow you to **Upload**, **Import**, or **Create** configuration files to be included in the channel.

Upload File

To upload a file into the configuration channel, browse for the file on your local system, populate all fields, and click the **[Upload Configuration File]** button. The **Filename/Path** field is the absolute path where the file will be deployed.

You can set the **Ownership** via the **user name** and **group name** and the **Permissions** of the file when it is deployed.

If the client has SELinux enabled, you can configure **SELinux contexts** to enable the required file attributes (such as user, role, and file type).

If the configuration file includes a macro (a variable in a configuration file), enter the symbol that marks the beginning and end of the macro. For more information on using macros, see [reference:configuration/files-locally-managed.pdf](#).

Import Files

To import files from other configuration channels, including any locally managed channels, check the box to the left of any file you want to import. Then click **[Import Configuration Files]**.



A sandbox icon () indicates that the listed file is currently located in a local sandbox. Files in a system's sandbox are considered experimental and could be unstable. Use caution when selecting them for a central configuration channel.

Create File

Create a configuration file, directory, or symbolic link to be included in the configuration channel.

Deploy Files

This page only appears when there are files in the channel and a system is subscribed to the channel. Deploy all files by clicking the **[Deploy All Files]** button or check selected files and click the **[Deploy Selected Files]** button. Select to which systems the files should be applied. All systems subscribed to this channel are listed. If you want to apply the file to a different system, subscribe it to the channel first. To deploy the files, click **[Confirm & Deploy to Selected Systems]**.

システム

Manage systems subscribed to the configuration channel with two subtabs:

Subscribed Systems

All systems subscribed to the current channel are displayed. Click the name of a system to see the **System Details** page. To unsubscribe a system from the configuration channel, check the box to the left of the system name and click [**Unsubscribe systems**].

Target Systems

This subtab displays a list of systems enabled for configuration management but not yet subscribed to the channel. To add a system to the configuration channel, check the box to the left of the system name and click [**Subscribe systems**].

2.10.3. ファイル

This page allows you to manage your configuration files independently. Both centrally managed and locally managed files can be reached from sub-pages.



By default, the maximum file size for configuration files is 128 KB (131072 bytes). SUSE supports a configuration file size up to 1 MB. Larger files are not guaranteed to work.

The default maximum file size is set on the SUSE Multi-Linux Manager Server in these files:

```
# /usr/share/rhn/config-defaults/rhn_web.conf
web.maximum_config_file_size = 131072

# /usr/share/rhn/config-defaults/rhn_server.conf
maximum_config_file_size = 131072
```

Copy these variables to **/etc/rhn/rhn.conf** and edit them. Values are specified in bytes, for example:

```
# /etc/rhn/rhn.conf
web.maximum_config_file_size = 262144
server.maximum_config_file_size = 262144
```

Then restart **spacewalk**:

```
spacewalk-service restart
```

2.10.3.1. Centrally Managed Configuration Files

Centrally managed files are available to multiple systems. Changing a file within a centrally managed channel may result in changes to several systems. Locally managed files supersede centrally managed files. For more information about locally managed files, see **Reference > Configuration**.

This page lists all files currently stored in your central configuration channel.

表 29. Centrally Managed Files Columns

| Column | Description |
|-----------------------|----------------------------------------------|
| Path | Absolute filename of the configuration file. |
| Configuration Channel | Name of the configuration channel. |
| Systems Subscribed | Number of systems subscribed. |
| Systems Overriding | |

Click the **Path** of a file to see **Details** tab of the file. Click the name of the **Configuration Channel** to see the **Overview** tab of the channel. Clicking **Systems Subscribed** shows you all systems currently subscribed to the channel containing that file. Click **Systems Overriding** to see all systems that have a local (or override) version of the configuration file. The centrally managed file will not be deployed to those systems.

2.10.3.2. Locally Managed Configuration Files

Locally managed configuration files apply to only one system. They may be files in the system's sandbox or files that can be deployed to the system at any time. Local files have higher priority than centrally managed files. If a system is subscribed to a configuration channel with a given file and additionally has a locally managed version of that file, the locally managed version will be deployed.

The list of all local (override) configuration files for your systems includes the local configuration channels and the sandbox channel for each Provisioning-entitled system.

Click the **Path** of the file to see its **Config File Details**. Click the name of the system to which it belongs to see its **System Details** › **Configuration** › **Overview** page.

設定管理の詳細については、**Client-configuration** › **Configuration-management**を参照してください。

2.10.4. Systems Menu

Displays status information about your system in relation to configuration. There are two sub-pages: **Managed Systems** and **Target Systems**.

2.10.4.1. Managed Systems

By default the **Managed Systems** page is displayed. The listed systems have been fully prepared for configuration file deployment. The number of locally managed and centrally managed files is displayed.

Click the name of a system to show the relevant **System Details** › **Configuration** › **Overview** page.

Click the number of local files to show the **System Details** › **Configuration** › **View/Modify Files** › **Locally Managed Files** page, where you can manage which local (override) files apply to the system.

Click the number of centrally managed files to show the **System Details** › **Configuration** › **Manage Configuration Channels** › **List/Unsubscribe from Channels** page. On this page, you can unsubscribe from channels.

2.10.4.2. Target Systems

This page shows the systems that are not prepared for configuration file deployment, or are not yet subscribed to a configuration channel.

The table has three columns:

- The system name
- If the system is prepared for configuration file deployment
- The steps necessary to prepare the system.

To prepare a system, check the box to the left of the profile name then click the [**Enable SUSE Multi-Linux Manager Configuration Management**] button. All of the preparatory steps that can be automatically performed are scheduled by SUSE Multi-Linux Manager.



You will need to perform some manual tasks to enable configuration file deployment.
Follow the on-screen instructions provided to assist with each step.

2.11. Schedule Menu

The **Schedule** section allows you to view actions and action chains.

Actions include:

- Package alterations, including installation, upgrade, removal, and rolling back of packages
- Client reboots
- Patch installation
- Configuration file alterations, including deploy, upload, and diff
- Hardware profile updates
- Package list profile updates
- Automated installation initiation
- 製品移行
- リモートコマンド

For more information about actions, see **Administration › Actions**.

2.11.1. Pending Actions

The **Schedule › Pending Actions** section shows actions that are in progress, or that have not yet started. Use the **Filter by Action** field to search the list.

Cancel pending actions by checking the action in the list, and clicking [**Cancel Actions**]. If you archive a pending action, it is not canceled, but the action item moves from the **Pending Actions** list to the **Archived Actions** list.

表 30. Actions List Columns

| Column | Description |
|----------------|------------------------------------------------------------------------------|
| Action | Type of action to perform. Click the action to go to Action Details . |
| Scheduled Time | The earliest time to perform the action. |
| Succeeded | Number of clients on which this action was successful. |
| Failed | Number of clients on which this action has failed. |
| Pending | Number of clients on which this action is currently running |
| Total | Total number of clients on which this action has been scheduled. |

For more information about actions, see **Administration › Actions**.

2.11.2. 定期的なアクション

The **Schedule › Recurring Actions** section shows all recurring actions that you have permissions for.



The recurring actions list on this page is a read-only table. To modify a schedule, you can follow the links in the **Target Name** column and list the schedules of an individual target.

Recurring Action Details

View the details about an action from the action list. In the **Actions** column, click the **[Details]** icon for the action you are interested in.

For more information about recurring actions, see **Administration › Actions**.

2.11.3. Completed Actions

The **Schedule › Completed Actions** section shows actions that have been successfully completed. Use the **Filter by Action** field to search the list. Archive completed actions by checking the action in the list, and clicking **[Archive Actions]**.

表 31. Completed Actions List Columns

| Column | Description |
|----------------|------------------------------------------------------------------------------|
| Action | Type of action to perform. Click the action to go to Action Details . |
| Scheduled Time | The earliest time to perform the action. |

| Column | Description |
|-----------|------------------------------------------------------------------|
| Succeeded | Number of clients on which this action was successful. |
| Failed | Number of clients on which this action has failed. |
| Pending | Number of clients on which this action is currently running |
| Total | Total number of clients on which this action has been scheduled. |

For more information about actions, see **Administration › Actions**.

2.11.4. Failed Actions

The **Schedule › Failed Actions** section shows actions that have not been completed, or that have returned an error. Use the **Filter by Action** field to search the list. Archive failed actions by checking the action in the list, and clicking **[Archive Actions]**.

Reschedule failed actions by checking the action in the list, and clicking **[Reschedule]**. Following the rescheduling, the action is:

- removed from the **Event History**
- replaced by the rescheduled action.

表 32. Actions List Columns

| Column | Description |
|----------------|------------------------------------------------------------------------------|
| Action | Type of action to perform. Click the action to go to Action Details . |
| Scheduled Time | The earliest time to perform the action. |
| Succeeded | Number of clients on which this action was successful. |
| Failed | Number of clients on which this action has failed. |
| Pending | Number of clients on which this action is currently running |
| Total | Total number of clients on which this action has been scheduled. |

For more information about actions, see **Administration › Actions**.

2.11.5. Archived Actions

The **Schedule › Archived Actions** section shows actions that you have marked as archived. Use the **Filter by Action** field to search the list. Completed or failed actions can be archived.

For more information about actions, see **Administration › Actions**.

2.11.6. Action Chains

The **Schedule › Action Chains** If you need to perform a number of sequential actions on your clients, you can create an action chain to automate them.

For more information about action chains, see **Administration › Actions**.

2.11.7. メンテナンスウィンドウ

The **Schedule › Maintenance Windows** section allows you to manage your maintenance window schedules. To create a maintenance schedule, you need to have an existing **.ical** file that contains the calendar. Upload the calendar, create a new schedule, and assign the schedule to a client. When a schedule is applied to a client, you are prevented from executing some actions outside of the specified period.

Navigate to **Schedule › Maintenance Windows › Schedules** to see a list of all current schedules. Click [**Create**] to create a new schedule. Click [**Edit**] to change the schedule.

Navigate to **Schedule › Maintenance Windows › Calendars** to see a list of all current calendars. Click [**Create**] to create a new calendar. Click [**Edit**] to change the calendar.

For more information about maintenance windows, see **Administration › Maintenance-windows**.

2.12. Users Menu

The **Users** menu provides access to grant and edit permissions for those who administer your system groups. You can create new users, and edit user details, roles, and system groups.



The **Users** menu is only available if you are signed in to SUSE Multi-Linux Manager with an administrator account.

For more information about managing users, see **Administration › Users**.

2.12.1. User Details

The **User Details** section provides additional details about the user account, and allows you to manage permissions for the user. You can also deactivate or delete users from this section.

For more information about managing users, see **Administration › Users**.

The **User Details** section is split into tabs:

2.12.1.1. 詳細

This tab allows you to change the name and password of the user account, and provides information about the various permissions the user has assigned.

Use this section to assign or remove roles, except for the SUSE Multi-Linux Manager Administrator. To change a user's SUSE Multi-Linux Manager Administrator role, navigate to **Admin › Users** and check or uncheck **SUSE Multi-Linux Manager Admin?** as required.

2.12.1.2. System Groups

This tab shows the system groups the user is assigned to. Check or uncheck system groups as required.

2.12.1.3. システム

This tab shows the clients the user is able to administer. Use system groups to modify client access levels.

Select multiple systems from this page to add them to the system set manager (SSM). For more information about SSM, see **Client-configuration › System-set-manager**.

2.12.1.4. Channel Permissions

This tab shows the channel permissions for the user.

The **Subscription** subtab shows channels that the user has subscription permissions for. The **Management** subtab shows channels that the user has management permissions for.

Check channels in the list to grant permissions.

2.12.1.5. User Preferences

This tab is used to configure preference settings for users.

表 33. User Preferences

| Option | Description | Default |
|-----------------------------------------|-----------------------------------------------------------------------------------------|-----------------|
| Email Notification | Receive email for client and Taskomatic notifications, including a daily summary email. | Checked |
| SUSE Multi-Linux Manager List Page Size | Maximum number of items that can appear in a list on a single page. | 25 entries |
| "Overview" Start Page | Select the information panes to display on the Home › Overview page. | All checked |
| Time Zone | Set your local timezone. | System timezone |

| Option | Description | Default |
|-----------|---------------------------------------------------------------------------------------------|---------|
| CSV Files | Select whether to use comma or semi-colon delimiters when producing downloadable CSV files. | Comma |

2.12.1.6. Addresses

This tab shows the mailing addresses associated with the user. Click **[Fill in this address]** to set a mailing address. Click **[Edit this address]** to change an existing mailing address.

2.12.2. User List

The **Users › User List** section provides access to the lists of users.

2.12.2.1. Active Users

The **Users › User List › Active** section shows all active users in your SUSE Multi-Linux Manager Server.

Each user in the list shows the username, real name, assigned roles, and the date the user last signed in. Click **[Create User]** to create a new user account. Click the username to go to the **User Details** page.

For more information about managing users, see **Administration › Users**.

2.12.2.2. Deactivated Users

The **Users › User List › Deactivated** section shows all deactivated users in your SUSE Multi-Linux Manager Server.

Each user in the list shows the username, real name, assigned roles, the date the user last signed in, the user who deactivated the account, and the date the account was deactivated. Click **[Create User]** to create a new user account. Click the username to go to the **User Details** page.

To reactivate a user, check the username in the list and click **[Reactivate]**.

For more information about managing users, see **Administration › Users**.

2.12.2.3. All Users

The **Users › User List › All** section shows all activated and deactivated users in your SUSE Multi-Linux Manager Server. Deleted users are not shown in the list.

Each user in the list shows the username, real name, assigned roles, the date the user last signed in, and the current status of the user. Click **[Create User]** to create a new user account. Click the username to go to the **User Details** page.

For more information about managing users, see **Administration › Users**.

2.12.3. System Group Configuration

The **Users › System Configuration** section allows you to configure system groups for your users.

System groups allow you to grant permissions to a group of users, instead of granting permissions to individuals. This is particularly useful if you have many users.

You can also configure system groups for users that have been externally authenticated.

For more information about managing users with system groups, see **Administration › Users**.

2.13. Admin Menu

The **Admin** menu provides access to features for managing SUSE Multi-Linux Manager configuration. Configuration tasks include creating and managing organizations, users, and tasks. You can also use the setup wizard to help configure SUSE Multi-Linux Manager.



The **Admin** menu is only available if you are logged in to SUSE Multi-Linux Manager with an administrator account.

2.13.1. セットアップウィザード

The **Admin › Setup Wizard** section helps you configure SUSE Multi-Linux Manager. It is the default page when you use the SUSE Multi-Linux Manager Web UI for the first time.

表 34. Setup Wizard Options

| Option | Description |
|--------------------------|---------------------------------------------------------------|
| HTTP Proxy | Configure an HTTP proxy connection. |
| Organization Credentials | Configure an organization for accessing SUSE Customer Center. |
| Products | View product entitlements and subscribe to product channels. |

2.13.1.1. Configure the HTTP Proxy

SUSE Multi-Linux Manager can connect to the SUSE Customer Center (SCC) or other remote servers using a proxy. Navigate to the **HTTP Proxy** tab to configure the proxy.

You will need to provide the hostname of the proxy. Use the syntax **<hostname>:<port>**. For example: **example.com:8080**.

You can disable use of the proxy by clearing the fields.



When choosing a username or password for your SUSE Multi-Linux Manager Proxy, ensure it does not contain an **@** or **:** character. These characters are reserved.

2.13.1.2. Configure Organization Credentials

Your SUSE Customer Center account is associated with the administration account of your organization. You can share your SUSE Customer Center access with other users within your organization. Navigate to the **Organization Credentials** tab to grant users within your organization access to your SUSE Customer Center account.

Click **[Add a new credential]**, enter the username and password of the user to grant access to, and click **[Save]**. A new credential card is shown for the user you have granted access to. Use these buttons on the card to edit or revoke access:

- Check credential validation status (green tick or red cross icon). To re-check the credential with SCC, click the icon.
- Set the primary credentials for inter-server synchronization (yellow star icon).
- 特定の資格情報と関係のあるサブスクリプションをリストします(リストアイコン)。
- Edit the credential (pencil icon).
- Delete the credential (trash can icon).

2.13.1.3. Configure Products

Your SUSE subscription entitles you to access a range of products. Navigate to the **Products** tab to browse the products available to you and synchronize SUSE Multi-Linux Manager with SUSE Customer Center.

Filters help you search for products by description or architecture.

The list is organized by product name showing products on top which have a subscription. Freely available products appear at the end of the list. For each product, you can see the architecture it can be used on. Click the arrow next to the product name to see associated channels and extensions. Click the **[Channels]** icon to see the complete list of channels associated with each product.

For products based on SUSE Linux Enterprise 15 and above, you can choose to only synchronize required packages, or to also include recommended products. Toggle the **[include recommended]** switch on to synchronize all products, and toggle the switch off to synchronize only required products.

You can further refine which products you want to synchronize by selecting or deselecting individual product.

When you have completed your selection, click **[Add products]**, and click **[Refresh]** to schedule the synchronization.

Synchronization progress for each product is shown in a progress bar next to the product name. Depending on the products you have chosen, synchronization can take up to several hours. New products will be available for you to use in SUSE Multi-Linux Manager when synchronization is complete.

If your synchronization fails, it could be because of a third party GPG key or your company firewall blocking access to the download server. Please check the notification details for the error. For more information about troubleshooting product synchronization, see **Administration › Troubleshooting**.

2.13.2. 組織

The **Admin › Organizations** section allows you to create and manage your SUSE Multi-Linux Manager organizations. Click an organization in the list to see details.

For more information about organizations, see **Administration › Organizations**.

2.13.3. ユーザー

The **Admin › Users** section allows you to view and manage all users of the organization you are logged in to. Every user shows the username, real name, the organization they are associated with, and whether the user is an organization or SUSE Multi-Linux Manager administrator.

To change a user's SUSE Multi-Linux Manager Administrator role, check or uncheck **SUSE Multi-Linux Manager Admin** as required.

Click a username to modify the user account details, and change other administrator roles.

For more information, see **Reference › Users**.

2.13.4. PAYG

The **Admin › PAYG** section allows you to view and manage PAYG instances. Every instance shows its description and connection data.

To add new instance, click [**Add PAYG**]. Click an instance to modify its details.

For more information, see **Specialized-guides › Public-cloud-guide**.

2.13.5. Manager Configuration

The **Admin › Manager Configuration** section contains tabs to allow you to configure SUSE Multi-Linux Manager.

表 35. Configuration Options

| Option | Description |
|------------------|------------------------------------------------------------------------------------------------|
| General | Configure your SUSE Multi-Linux Manager installation. |
| Bootstrap Script | Generate a custom bootstrap script. |
| Organizations | Create and configure organizations and users. |
| Restart | Restart SUSE Multi-Linux Manager. You will need to do this after making configuration changes. |
| Cobbler | Run a Cobbler synchronization. |
| Monitoring | Enable server monitoring. |

2.13.5.1. 全般

On the **Admin › Manager Configuration › General** page you can configure your SUSE Multi-Linux Manager installation.

表 36. Bootstrap Script Options

| Option | Description | Default |
|-----------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------|------------------------|
| Administrator Email Address | Email address of the SUSE Multi-Linux Manager administrator. | Pre-populated |
| SUSE Multi-Linux Manager Hostname | Hostname of the SUSE Multi-Linux Manager Server. | Pre-populated |
| HTTP Proxy | The hostname and port of the proxy, if you are using one. Use syntax <hostname>:<port> , for example: <example.com>:8080 . | None |
| HTTP Proxy username | The username to use on the proxy server, if you are using one. | None |
| HTTP Proxy password | The password to use on the proxy server, if you are using one. | None |
| Confirm HTTP Proxy password | The directory where RPM packages are mirrored. | /var/spacewalk/ |
| RPM repository mount point | The hostname of the proxy server, if you are using one. | None |
| Default to SSL | Check to use SSL as the default value for communications. | Checked |

2.13.5.2. ブートストラップスクリプト

In the **Admin › Manager Configuration › Bootstrap Script** section you can generate a custom bootstrap script. Bootstrap scripts are used to register clients with SUSE Multi-Linux Manager. The generated script will be placed in **/srv/www/htdocs/pub/bootstrap/** on your SUSE Multi-Linux Manager Server.

表 37. Bootstrap Script Options

| Option | Description | Default |
|------------------------------------------|--------------------------------------------------------------------------------|---------------|
| SUSE Multi-Linux Manager Server hostname | The hostname for the SUSE Multi-Linux Manager Server to register the client to | Pre-populated |
| SSL cert location | Location and name of the SSL certificate | Pre-populated |
| Bootstrap using Salt | Check to bootstrap clients | Checked |

| Option | Description | Default |
|-----------------------------|--------------------------------------------------------------------------------------------------------------|-------------|
| Enable SSL | Check to use the corporate public CA certificate on the client, uncheck to use self-managed CA certificates. | Checked |
| Enable Client GPG checking | Check to use GPG, uncheck to disable GPG checking | Checked |
| Enable Remote Configuration | Check to allow configuration from a remote server. | Unchecked |
| Enable Remote Commands | Check to allow commands from a remote server. | Unchecked |
| Client HTTP Proxy | The hostname of the proxy server, if you are using one. | Unpopulated |
| Client HTTP Proxy Username | The username to use on the proxy server, if you are using one. | Unpopulated |
| Client HTTP Proxy Password | The password to use on the proxy server, if you are using one. | Unpopulated |



ブートストラップスクリプトのSSLを無効にしないでください。Web UIで **[Enable SSL]**（SSLの有効化）がチェックされていること、または設定 **USING_SSL=1** がブートストラップスクリプトに存在していることを確認してください。SSLを無効にすると、登録プロセスでカスタムSSL証明書が必要です。カスタム証明書の詳細については、**Administration > Ssl-certs**を参照してください。

2.13.5.3. 組織の設定

The **Admin > Manager Configuration > Organizations** section contains details about organizations in SUSE Multi-Linux Manager, and provides links to create and configure organizations and users.

2.13.5.4. 再起動

The **Admin > Manager Configuration > Restart** section allows you to restart SUSE Multi-Linux Manager. You will need to do this after making configuration changes. It will take some time for SUSE Multi-Linux Manager to become available again after a restart.

2.13.5.5. Cobbler

The **Admin > Manager Configuration > Cobbler** page allows you to run a Cobbler synchronization. You can repair or rebuild the contents of the `/srv/tftpboot/` and `/srv/www/cobbler/` directories after a manual modification of the Cobbler setup.

For more information about autoinstallation powered by Cobbler, see **Client-configuration > Autoinst-intro**.



SUSE only supports Cobbler functions that are available in the SUSE Multi-Linux Manager Web UI, or through the SUSE Multi-Linux Manager API. Only supported features are documented here.



Using NFS for the persistent volumes of Cobbler is not supported.

2.13.5.6. モニタリング

The **Admin › Manager Configuration › Monitoring** section allows you to enable SUSE Multi-Linux Manager monitoring with Prometheus.

For more information about monitoring, see **Administration › Monitoring**.

2.13.6. Task Schedules

The **Admin › Task Schedules** section lists all predefined task bunches. Tasks can be grouped together in bunches to simplify managing them.

This page shows the schedule for each bunch of tasks. Every schedule shows how frequently it runs using **cron** notation, the time it became active, and the bunch that it belongs to.

Click a schedule to change its frequency, disable or activate it.



Do not disable a schedule if you are not certain what it does. Some schedules are essential for SUSE Multi-Linux Manager to work properly.

For more information about task schedules, see **Administration › Task-schedules**.

2.13.7. タスクエンジンの状態

The **Admin › Task Engine Status** section shows all running tasks by the SUSE Multi-Linux Manager task engine.

Navigate to the **Last Execution Times** tab to see the task list. Each task shows the time it was last run, and the current status of the task.

Navigate to the **Runtime Status** tab to see all tasks that have run in the past five minutes. Each task shows the start and end time, the amount of time the task ran for, and the current status. Some tasks will also provide further data, if available.

2.13.8. Show Tomcat Logs

The **Admin › Show Tomcat Logs** section shows the Apache Tomcat log file. You can also view the Tomcat log from the command prompt at `/var/log/rhn/rhn_web_ui.log`.



The **Admin › Show Tomcat Logs** section is only available if you are signed in to SUSE Multi-Linux Manager with an administrator account.

2.14. Help Menu

The **Help** section opens the current version of the SUSE Multi-Linux Manager documentation in a new browser tab. This is the documentation installed locally on your SUSE Multi-Linux Manager Server.

For all versions and formats of the SUSE Multi-Linux Manager documentation, see <https://documentation.suse.com/multi-linux-manager/>

2.14.1. ドキュメンテーション

The **Help > Documentation 5.1** section opens the current version of the SUSE Multi-Linux Manager documentation in a new browser tab. This is the documentation installed locally on your SUSE Multi-Linux Manager Server.

For all versions and formats of the SUSE Multi-Linux Manager documentation, including API documentation, see <https://documentation.suse.com/multi-linux-manager/>.

2.14.2. Release Notes

The **Help > Release Notes** section opens the current version of the SUSE Multi-Linux Manager Release Notes in a new browser tab.

2.14.3. API Menu

The **Help > API** section contains links to the available API calls, and includes an API FAQ and sample scripts.

2.14.3.1. API Overview

The **Help > API > Overview** section provides a list of available API calls. Click the name of an API call to see the relevant documentation.

For the full API documentation, see [API Documentation](#).

2.14.3.2. API FAQ

The **Help > API > FAQ** section contains frequently asked questions related to SUSE Multi-Linux Manager APIs.

See: <https://documentation.suse.com/multi-linux-manager/5.1/api/docs/api/faqs.html>

2.14.3.3. API Sample Scripts

The **Help: > API > Sample Scripts** section contains example API calls for you to copy. The scripts are written in Ruby, Perl, and Python.

See: <https://documentation.suse.com/multi-linux-manager/5.1/api/docs/api/scripts.html>

Chapter 3. spacecmd Reference



サーバコンテナ内でシェルにアクセスするには、コンテナホストで**mgrctl term**を実行します。そこから、CLIツールを通常どおりに実行できます。

The following section will help you become more familiar with the **spacecmd** command-line interface. This interface is available for SUSE Multi-Linux Manager, Satellite and Spacewalk servers. **spacecmd** is written in Python and uses the XML-RPC API provided by the server.

What can spacecmd do for me?

- Manage almost all aspects of SUSE Multi-Linux Manager from the command line with **spacecmd**
- Tab completion is available for all commands
- Single commands can be passed to **spacecmd** without entering the interactive shell (excellent for shell scripts)
- May also be accessed and used as an interactive shell
- Advanced search methods are available for finding specific systems, thus removing the need to create system groups (nevertheless groups are still recommended)
- Complete functionality through the Spacewalk API. Almost all commands that can be executed from the Web UI can be performed via the **spacecmd** command-line

3.1. Configuring spacecmd



サーバコンテナ内でシェルにアクセスするには、コンテナホストで**mgrctl term**を実行します。そこから、CLIツールを通常どおりに実行できます。

The following section provides configuration tips for **spacecmd**.

3.1.1. Setup spacecmd credentials

Normally **spacecmd** prompts you for a username and password each time you attempt to login to the interactive shell. Alternatively you can configure **spacecmd** with a credentials file to avoid this requirement.

Procedure: Creating a spacecmd credentials file

1. Create a hidden **spacecmd** directory in your home directory and set permissions:

```
mkdir ~/.spacecmd
chmod 700 ~/.spacecmd
```

2. Create a **config** file in **~/.spacecmd/** and provide proper permissions:

```
touch ~/.spacecmd/config
```

```
chmod 600 ~/.spacecmd/config
```

3. Edit the **config** file and add the following configuration lines. (You can use either localhost, when running spacecmd from your SUSE Multi-Linux Manager server container, or the FQDN of your SUSE Multi-Linux Manager server):

```
[spacecmd]
server=FQDN-here
username=username-here
password=password-here
```

4. Check connectivity by entering **spacecmd** as root:

```
# spacecmd
```

3.1.2. spacecmd quiet mode

By default spacecmd prints server status messages during connection attempts. These messages can cause a lot of clutter when parsing system lists. The following alias will force spacecmd to use quiet mode thus preventing this behavior. Add the following line to your **~/.bashrc** file:

```
alias spacecmd='spacecmd -q'
```

3.1.3. spacecmd help

spacecmd help can be access by typing spacecmd **-h --help**

```
Usage: spacecmd [options] [command]

Options:
  -c CONFIG, --config CONFIG      config file to use [default: ~/.spacecmd/config]
  -u USERNAME, --username=USERNAME use this username to connect to the server
  -p PASSWORD, --password=PASSWORD use this password to connect to the server
  -s SERVER, --server=SERVER      connect to this server [default: local hostname]
  --nossl                        use HTTP instead of HTTPS
  --nohistory                     do not store command history
  -y, --yes                       answer yes for all questions
  -q, --quiet                     print only error messages
  -d, --debug                     print debug messages (can be passed multiple times)
  -h, --help                     show this help message and exit
```

As root you can access available functions without entering the spacecmd shell:

```
# spacecmd -- help

Documented commands (type help <topic>):
=====
activationkey_addchildchannels      org_trustdetails
activationkey_addconfigchannels     package_details
activationkey_addentitlements       package_listdependencies
activationkey_addgroups             package_listerrata
activationkey_addpackages           package_listinstalledsystems
activationkey_clone                 package_listorphans
activationkey_create                package_remove
activationkey_delete                package_removeorphans
activationkey_details               package_search
activationkey_diff                  repo_addfilters
activationkey_disable               repo_clearfilters
activationkey_disableconfigdeployment repo_create
...

```

3.2. help

List all available spacecmd commands with the help function.

Check for additional help on a specific function by calling for example:

```
user_create --help
```

リスト 1. Full List of Available Help Commands

```
Documented commands (type help <topic>):
=====
activationkey_addchildchannels      org_remove trust
activationkey_addconfigchannels     org_rename
activationkey_addentitlements       org_trustdetails
activationkey_addgroups             package_details
activationkey_addpackages           package_listdependencies
activationkey_clone                 package_listerrata
activationkey_create                package_listinstalledsystems
activationkey_delete                package_listorphans
activationkey_details               package_remove
activationkey_diff                  package_removeorphans
activationkey_disable               package_search
activationkey_disableconfigdeployment repo_addfilters
activationkey_enable               repo_clearfilters
activationkey_enableconfigdeployment repo_create
activationkey_export               repo_delete
activationkey_import               repo_details
activationkey_list                  repo_list
activationkey_listbasechannel       repo_listfilters
activationkey_listchildchannels     repo_removefilters
activationkey_listconfigchannels    repo_rename
activationkey_listentitlements      repo_setfilters
activationkey_listgroups            repo_updatessl
activationkey_listpackages          repo_updateurl
activationkey_listsystems           report_duplicates
activationkey_removechildchannels   report_errata
activationkey_removeconfigchannels  report_inactivesystems
activationkey_removeentitlements     report_ipaddresses
activationkey_removegroups          report_kernels

```


| | |
|-------------------------------------|---------------------------------------|
| activationkey_removepackages | report_outofdatesystems |
| activationkey_setbasechannel | report_ungroupedsystems |
| activationkey_setconfigchannelorder | scap_getxccdfscandetails |
| activationkey_setcontactmethod | scap_getxccdfscanruleresults |
| activationkey_setdescription | scap_listxccdfscans |
| activationkey_setuniversaldefault | scap_scheduledxccdfscan |
| activationkey_setusagelimit | schedule_cancel |
| api | schedule_details |
| clear | schedule_getoutput |
| clear_caches | schedule_list |
| configchannel_addfile | schedule_listarchived |
| configchannel_backup | schedule_listcompleted |
| configchannel_clone | schedule_listfailed |
| configchannel_create | schedule_listpending |
| configchannel_delete | schedule_reschedule |
| configchannel_details | snippet_create |
| configchannel_diff | snippet_delete |
| configchannel_export | snippet_details |
| configchannel_filedetails | snippet_list |
| configchannel_forcedeploy | snippet_update |
| configchannel_import | softwarechannel_adderrata |
| configchannel_list | softwarechannel_adderratabydate |
| configchannel_listfiles | softwarechannel_addpackages |
| configchannel_listsystems | softwarechannel_addrepo |
| configchannel_removefiles | softwarechannel_clone |
| configchannel_sync | softwarechannel_clonetree |
| configchannel_updatefile | softwarechannel_create |
| configchannel_verifyfile | softwarechannel_delete |
| cryptokey_create | softwarechannel_details |
| cryptokey_delete | softwarechannel_diff |
| cryptokey_details | softwarechannel_errata_diff |
| cryptokey_list | softwarechannel_errata_sync |
| custominfo_createkey | softwarechannel_getorgaccess |
| custominfo_deletekey | softwarechannel_list |
| custominfo_details | softwarechannel_listallpackages |
| custominfo_listkeys | softwarechannel_listbasechannels |
| custominfo_updatekey | softwarechannel_listchildchannels |
| distribution_create | softwarechannel_listerrata |
| distribution_delete | softwarechannel_listerratabydate |
| distribution_details | softwarechannel_listlatestpackages |
| distribution_list | softwarechannel_listpackages |
| distribution_rename | softwarechannel_listrepos |
| distribution_update | softwarechannel_listsyncschedule |
| errata_apply | softwarechannel_listsystems |
| errata_delete | softwarechannel_mirrorpackages |
| errata_details | softwarechannel_regenerateneededcache |
| errata_findbycve | softwarechannel_regenerateyumcache |
| errata_list | softwarechannel_removeerrata |
| errata_listaffectedsystems | softwarechannel_removepackages |
| errata_listcves | softwarechannel_removerepo |
| errata_publish | softwarechannel_removesyncschedule |
| errata_search | softwarechannel_setorgaccess |
| errata_summary | softwarechannel_setsyncschedule |
| filepreservation_create | softwarechannel_sync |
| filepreservation_delete | softwarechannel_syncrepos |
| filepreservation_details | ssm_add |
| filepreservation_list | ssm_clear |
| get_apiversion | ssm_intersect |
| get_certificateexpiration | ssm_list |
| get_serverversion | ssm_remove |
| get_session | system_addchildchannels |
| group_addsystems | system_addconfigchannels |
| group_backup | system_addconfigfile |
| group_create | system_addcustomvalue |
| group_delete | system_addentitlements |

| | |
|-----------------------------------|--------------------------------|
| group_details | system_addnote |
| group_list | system_applyerrata |
| group_listsystems | system_comparepackageprofile |
| group_removesystems | system_comparepackages |
| group_restore | system_comparewithchannel |
| help | system_createpackageprofile |
| history | system_delete |
| kickstart_addactivationkeys | system_deletenotes |
| kickstart_addchildchannels | system_deletepackageprofile |
| kickstart_addcryptokeys | system_deployconfigfiles |
| kickstart_addfilepreservations | system_details |
| kickstart_addoption | system_installpackage |
| kickstart_addpackages | system_list |
| kickstart_addscript | system_listbasechannel |
| kickstart_addvariable | system_listchildchannels |
| kickstart_clone | system_listconfigchannels |
| kickstart_create | system_listconfigfiles |
| kickstart_delete | system_listcustomvalues |
| kickstart_details | system_listentitlements |
| kickstart_diff | system_listerrata |
| kickstart_disableconfigmanagement | system_listevents |
| kickstart_disableremotecommands | system_listhardware |
| kickstart_enableconfigmanagement | system_listinstalledpackages |
| kickstart_enablelogging | system_listnotes |
| kickstart_enableremotecommands | system_listpackageprofiles |
| kickstart_export | system_listupgrades |
| kickstart_getcontents | system_lock |
| kickstart_getsoftwaredetails | system_reboot |
| kickstart_getupdatetype | system_removechildchannels |
| kickstart_import | system_removeconfigchannels |
| kickstart_import_raw | system_removecustomvalues |
| kickstart_importjson | system_removeentitlement |
| kickstart_list | system_removepackage |
| kickstart_listactivationkeys | system_rename |
| kickstart_listchildchannels | system_runscript |
| kickstart_listcryptokeys | system_schedulehardwarerefresh |
| kickstart_listcustomoptions | system_schedulepackagerefresh |
| kickstart_listoptions | system_search |
| kickstart_listpackages | system_setbasechannel |
| kickstart_listscripts | system_setconfigchannelorder |
| kickstart_listvariables | system_setcontactmethod |
| kickstart_removeactivationkeys | system_show_packageversion |
| kickstart_removechildchannels | system_syncpackages |
| kickstart_removecryptokeys | system_unlock |
| kickstart_removefilepreservations | system_updatecustomvalue |
| kickstart_removeoptions | system_upgradepackage |
| kickstart_removepackages | toggle_confirmations |
| kickstart_removescript | user_adddefaultgroup |
| kickstart_removevariables | user_addgroup |
| kickstart_rename | user_addrole |
| kickstart_setcustomoptions | user_create |
| kickstart_setdistribution | user_delete |
| kickstart_setlocale | user_details |
| kickstart_setpartitions | user_disable |
| kickstart_setselinux | user_enable |
| kickstartsetupdatetype | user_list |
| kickstart_updatevariable | user_listavailableroles |
| list_proxies | user_removedefaultgroup |
| login | user_removegroup |
| logout | user_removeole |
| org_addtrust | user_setemail |
| org_create | user_setfirstname |
| org_delete | user_setlastname |
| org_details | user_setpassword |
| org_list | user_setprefix |

```
org_listtrusts      whoami
org_listusers       whoamitalkingto

Miscellaneous help topics:
=====
time systems ssm
```

3.3. history

List recent commands using the **history** command.

```
spacecmd {SSM:0}> history
 1  help
 2  api
 3  exit
 4  help
 5  time --help
 6  quit
 7  clear
spacecmd {SSM:0}>
```

3.4. Troubleshooting spacecmd

This section provides troubleshooting solutions when working with spacecmd

3.4.1. Creating a distribution where spacecmd sets localhost instead of FQDN

Situation

When creating a distribution with spacecmd it will automatically set **localhost** as the server name instead of the FQDN of SUSE Multi-Linux Manager. This will result in the following kernel option being written:

```
install=http://localhost/ks/dist/<distributionname>
```

Resolution

Set the FQDN in **\$HOME/.spacecmd/config** like the following:

```
test:~/.spacecmd # cat config

[spacecmd]
server=test.mytest.env username=admin password=password nssl=0
```

Cause

This problem may be experienced if **\$HOME/.spacecmd/config** has been created and the server name option was set to **localhost**.

3.4.2. spacecmd not accepting commands or options

When running **spacecmd** non-interactively:

- you must escape arguments passed to the command.
- always put `--` before arguments, to avoid them being treated as global arguments.
- make sure you escape any quotes that you pass to the functions so that they are not interpreted.

An example of a well-formed **spacecmd** command:

```
spacecmd -s server1 -- softwarechannel_create -n \'My Channel\' -l channel1 -a x86_64
```

3.4.3. spacecmd caching problems

The **spacecmd** command keeps a cache of the various systems and packages that you have installed. Sometimes, this can result in a mismatch between the system name and the system ID.

To clear the **spacecmd** cache, use this command:

```
spacecmd clear_caches
```

3.5. spacecmd Functions

The following sections provide descriptions for all documented spacecmd commands. Each command is grouped by the function prefix. Keep in mind that all commands may also be called using scripts and passed to spacecmd as stand-alone commands.

3.5.1. アクティベーションキー

The following spacecmd commands are available for use with activation keys.

3.5.1.1. activationkey_addchildchannels

Add child channels to an activation key.

```
使用方法: activationkey_addchildchannels キー <チャンネル ...>
```

3.5.1.2. activationkey_addconfigchannels

Add configuration channels to an activation key.

```
usage: activationkey_addconfigchannels KEY <CHANNEL ...> [options]
options:
  -t add channels to the top of the list
  -b add channels to the bottom of the list
```

3.5.1.3. activationkey_addentitlements

Add available entitlements to an activation key.

使用方法: `activationkey_addentitlements` キー <エンタイトルメント ...>



- In the WebUI entitlements are known as System Types. Nevertheless the spacecmd backend still utilizes the entitlements term. Therefore any scripts you may be using can remain unchanged.

3.5.1.4. `activationkey_addgroups`

Add existing groups to an activation key.

使用方法: `activationkey_addgroups` キー <グループ ...>

3.5.1.5. `activationkey_addpackages`

Add packages to an activation key.

使用方法: `activationkey_addpackages` キー <パッケージ ...>

3.5.1.6. `activationkey_clone`

Clone an existing activation key.

```
usage examples:
    activationkey_clone foo_key -c bar_key
    activationkey_clone foo_key1 foo_key2 -c prefix
    activationkey_clone foo_key -x "s/foo/bar"
    activationkey_clone foo_key1 foo_key2 -x "s/foo/bar"

options:
  -c CLONE_NAME : Name of the resulting key, treated as a prefix for multiple
                  keys
  -x "s/foo/bar" : Optional regex replacement, replaces foo with bar in the
                  clone description, base-channel label, child-channel
                  labels, config-channel names
```

3.5.1.7. `activationkey_create`

Create a new activation key.

```
usage: activationkey_create [options]

options:
  -n NAME
  -d DESCRIPTION
  -b BASE_CHANNEL
  -u set key as universal default
  -e [enterprise_entitled,virtualization_host]
```

3.5.1.8. `activationkey_delete`

Delete an existing activation key.

使用方法: `activationkey_delete` キー

3.5.1.9. activationkey_details

Show details of an existing activation key.

使用方法: `activationkey_details` キー ...

3.5.1.10. activationkey_diff

Check the difference between two activation keys.

usage: `activationkey_diff` SOURCE_ACTIVATIONKEY TARGET_ACTIVATIONKEY

3.5.1.11. activationkey_disable

Disable an existing activation key.

使用方法: `activationkey_disable` キー [キー ...]

3.5.1.12. activationkey_disableconfigdeployment

Disable configuration channel deployment for an existing activation key.

使用方法: `activationkey_disableconfigdeployment` キー

3.5.1.13. activationkey_enable

Enable an existing activation key.

使用方法: `activationkey_enable` キー [キー ...]

3.5.1.14. activationkey_enableconfigdeployment

Enable configuration channel deployment for an existing activation key.

使用方法: `activationkey_enableconfigdeployment` キー

3.5.1.15. activationkey_export

Export activation keys to a JSON formatted file.

usage: `activationkey_export` [options] [<KEY> ...]

options:

-f outfile.json : specify an output filename, defaults to <KEY>.json
if exporting a single key, akeys.json for multiple keys,
or akey_all.json if no KEY specified (export ALL)

Note : KEY list is optional, default is to export ALL keys

3.5.1.16. activationkey_import

Import activation keys from JSON files

使用方法: `activationkey_import <JSONファイル ...>`

3.5.1.17. activationkey_list

List all existing activation keys.

使用方法: `activationkey_list`

3.5.1.18. activationkey_listbasechannel

List the base channel associated with an activation key.

使用方法: `activationkey_listbasechannel キー`

3.5.1.19. activationkey_listchildchannels

List child channels associated with an activation key.

使用方法: `activationkey_listchildchannels キー`

3.5.1.20. activationkey_listconfigchannels

List configuration channels associated with an activation key.

使用方法: `activationkey_listconfigchannels キー`

3.5.1.21. activationkey_listentitlements

List entitlements associated with an activation key.

使用方法: `activationkey_listentitlements キー`

3.5.1.22. activationkey_listgroups

List groups associated with an activation key

使用方法: `activationkey_listgroups キー`

3.5.1.23. activationkey_listpackages

List packages associated with an activation key.

使用方法: `activationkey_listpackages` キー

3.5.1.24. activationkey_listsystems

List systems registered with an activation key.

使用方法: `activationkey_listsystems` キー

3.5.1.25. activationkey_removechildchannels

Remove child channels from an activation key.

使用方法: `activationkey_removechildchannels` キー <チャンネル ...>

3.5.1.26. activationkey_removeconfigchannels

Remove configuration channels from an activation key.

使用方法: `activationkey_removeconfigchannels` キー <チャンネル ...>

3.5.1.27. activationkey_removeentitlements

Remove entitlements from an activation key.

使用方法: `activationkey_removeentitlements` キー <エンタイトルメント ...>

3.5.1.28. activationkey_removegroups

Remove groups from an activation key.

使用方法: `activationkey_removegroups` キー <グループ ...>

3.5.1.29. activationkey_removepackages

Remove packages from an activation key.

使用方法: `activationkey_removepackages` キー <パッケージ ...>

3.5.1.30. activationkey_setbasechannel

Set the base channel for an activation key.

使用方法: `activationkey_setbasechannel` キー チャンネル

3.5.1.31. `activationkey_setconfigchannelorder`

Set the ranked order of configuration channels.

使用方法: `activationkey_setconfigchannelorder` キー

3.5.1.32. `activationkey_setcontactmethod`

Set the contact method to use for systems registered with a specific key. (Use the XML-RPC API to access the latest contact methods.)

使用方法: `activationkey_setcontactmethod` キー 連絡方法

3.5.1.33. `activationkey_setdescription`

Add a description for an activation key.

使用方法: `activationkey_setdescription` キー 説明

3.5.1.34. `activationkey_setuniversaldefault`

Set a specific key as the universal default.

使用方法: `activationkey_setuniversaldefault` キー



Using a universal default key is not a Best Practice recommendation.

3.5.2. `api`

The following API command and its options are available for calling the XML-RPC API directly. Calling the API directly allows you to use the latest features in SUSE Multi-Linux Manager from the command-line using `spacecmd` as a wrapper for stand-alone commands or used from within scripts.

To gain access to the latest feature additions call **`api api.getApiCallList`** from within `spacecmd` to list all currently available API commands formatted in json.

3.5.2.1. `api_`

Call XML-RPC API with arguments directly.

usage: `api [options] API_STRING`

options:

- A, --args Arguments for the API other than session id in comma separated strings or JSON expression
- F, --format Output format
- o, --output Output file

```
examples:
api api.getApiCallList
api --args "sysgroup_A" systemgroup.listSystems
api -A "rhel-i386-server-5,2011-04-01,2011-05-01" -F "%(name)s" \
channel.software.listAllPackages
```

3.5.3. clear

Clears the terminal screen.

3.5.4. clear_caches

Clear the internal caches kept for systems and packages.

使用方法: `clear_caches`

3.5.5. configchannel

The following spacecmd commands are available for use with configuration channels.

3.5.5.1. configchannel_addfile

Creates a configuration file.

```
usage: configchannel_addfile [CHANNEL] [options]

options:
-c CHANNEL
-p PATH
-r REVISION
-o OWNER [default: root]
-g GROUP [default: root]
-m MODE [default: 0644]
-x SELINUX_CONTEXT
-d path is a directory
-s path is a symlink
-b path is a binary (or other file which needs base64 encoding)
-t SYMLINK_TARGET
-f local path to file contents
```

Note re binary/base64: Some text files, notably those containing trailing newlines, those containing ASCII escape characters (or other characters not allowed in XML) need to be sent as binary (-b). Some effort is made to auto- detect files which require this, but you may need to explicitly specify.

3.5.5.2. configchannel_backup

Backup a configuration channel.

```
usage: configchannel_backup CHANNEL [OUTDIR]

OUTDIR defaults to $HOME/spacecmd-backup/configchannel/YYYY-MM-DD/CHANNEL
```

3.5.5.3. configchannel_clone

Clone configuration channels.

usage examples:

```
configchannel_clone foo_label -c bar_label
configchannel_clone foo_label1 foo_label2 -c prefix
configchannel_clone foo_label -x "s/foo/bar"
configchannel_clone foo_label1 foo_label2 -x "s/foo/bar"
```

options:

- c CLONE_LABEL : name/label of the resulting cc (note does not update description, see -x option), treated as a prefix if multiple keys are passed
- x "s/foo/bar" : Optional regex replacement, replaces foo with bar in the clone name, label and description

Note : If no -c or -x option is specified, interactive is assumed

3.5.5.4. configchannel_create

Create a configuration channel.

usage: configchannel_create [options]

options:

- n NAME
- l LABEL
- d DESCRIPTION

3.5.5.5. configchannel_delete

Delete a configuration channel.

使用方法: configchannel_delete チャンネル ...

3.5.5.6. configchannel_details

Show the details of a configuration channel.

使用方法: configchannel_details チャンネル ...

3.5.5.7. configchannel_diff

Find differences between configuration channels.

使用方法: configchannel_diff チャンネル_1 チャンネル_2

3.5.5.8. configchannel_export

Export configuration channels to a json formatted file.

usage: configchannel_export <CHANNEL>... [options]

```
options:
  -f outfile.json : specify an output filename, defaults to <CHANNEL>.json
                    if exporting a single channel, ccs.json for multiple
                    channels, or cc_all.json if no CHANNEL specified
                    e.g (export ALL)
```

Note : CHANNEL list is optional, default is to export ALL

3.5.5.9. configchannel_filedetails

Show the details of a file in a configuration channel.

使用方法: configchannel_filedetails チャンネル ファイル [リビジョン]

3.5.5.10. configchannel_forcedeploy

Forces a redeployment of files within a channel on all subscribed systems.

使用方法: configchannel_forcedeploy チャンネル

3.5.5.11. configchannel_import

Import configuration channels from a json file.

使用方法: configchannel_import <JSONファイル...>

3.5.5.12. configchannel_list

List all configuration channels.

使用方法: configchannel_list

3.5.5.13. configchannel_listfiles

List all files in a configuration channel.

使用方法: configchannel_listfiles チャンネル ...

3.5.5.14. configchannel_listsystems

List all systems subscribed to a configuration channel.

使用方法: configchannel_listsystems チャンネル

3.5.5.15. configchannel_removefiles

Remove configuration files.

```
usage: configchannel_removefile CHANNEL <FILE ...>
```

3.5.5.16. configchannel_sync

Sync configuration files between two configuration channels.

使用方法: configchannel_sync 同期元チャンネル 同期先チャンネル

3.5.5.17. configchannel_updatefile

Update a configuration file.

```
usage: configchannel_updatefile CHANNEL FILE
```

3.5.5.18. configchannel_verifyfile

Verify a configuration file.

使用方法: configchannel_verifyfile チャンネル ファイル <システム>

<SYSTEMS> may be substituted with any of the following targets: name ssm (see 'help ssm')
search:QUERY (see 'help system_search') group:GROUP channel:CHANNEL

3.5.6. cryptokey

The following spacecmd commands are available for use with cryptographic keys.

3.5.6.1. cryptokey_create

Create a cryptographic key.

```
usage: cryptokey_create [options]
```

```
options:
  -t GPG or SSL
  -d DESCRIPTION
  -f KEY_FILE
```

3.5.6.2. cryptokey_delete

Delete a cryptographic key.

使用方法: cryptokey_delete 名前

3.5.6.3. cryptokey_details

Show the contents of a cryptographic key.

使用方法: `cryptokey_details` 鍵 ...

3.5.6.4. `cryptokey_list`

List all cryptographic keys (SSL, GPG).

使用方法: `cryptokey_list`

3.5.7. `custominfo`

The following spacecmd commands are available for working with custom keys.

3.5.7.1. `custominfo_createkey`

Create a custom key.

使用方法: `custominfo_createkey` [名前] [説明]

3.5.7.2. `custominfo_deletekey`

Delete a custom key.

使用方法: `custominfo_deletekey` 鍵 ...

3.5.7.3. `custominfo_details`

Show the details of a custom key.

使用方法: `custominfo_details` 鍵 ...

3.5.7.4. `custominfo_listkeys`

List all custom keys.

使用方法: `custominfo_listkeys`

3.5.7.5. `custominfo_updatekey`

Update a custom key.

使用方法: `custominfo_updatekey` [名前] [説明]

3.5.8. ディストリビューション

The following spacecmd commands are available for working with kickstart distributions.

3.5.8.1. distribution_create

Create a Kickstart tree.

```
usage: distribution_create [options]

options:
  -n NAME
  -p path to tree
  -b base channel to associate with
  -t install type [fedora|rhel_4/5/6|suse|generic_rpm]
```

3.5.8.2. distribution_delete

Delete a Kickstart tree.

```
使用方法: distribution_delete ラベル
```

3.5.8.3. distribution_details

Show the details of a Kickstart tree.

```
使用方法: distribution_details ラベル
```

3.5.8.4. distribution_list

List the available autoinstall trees.

```
使用方法: distribution_list
```

3.5.8.5. distribution_rename

Rename a Kickstart tree.

```
使用方法: distribution_rename 変更前の名前 変更後の名前
```

3.5.8.6. distribution_update

Update the path of a Kickstart tree.

```
usage: distribution_update NAME [options]

options:
  -p path to tree
  -b base channel to associate with
  -t install type [fedora|rhel_4/5/6|suse|generic_rpm]
```

3.5.9. errata

The following spacecmd commands are available for use with errata data.

3.5.9.1. errata_apply

Apply an patch to all affected systems.

```
usage: errata_apply ERRATA|search:XXX ...
```

3.5.9.2. errata_delete

Delete an patch.

```
使用方法: errata_delete エラータ|search:XXX ...
```

3.5.9.3. errata_details

Show the details of an patch.

```
使用方法: errata_details エラータ|search:XXX ...
```

3.5.9.4. errata_findbycve

List errata addressing a CVE.

```
使用方法: errata_findbycve CVE-YYYY-NNNN ...
```

3.5.9.5. errata_list

List all patches.

```
使用方法: errata_list
```

3.5.9.6. errata_listaffectedsystems

List of systems affected by an patch.

```
使用方法: errata_listaffectedsystems エラータ|search:XXX ...
```

3.5.9.7. errata_listcves

List of CVEs addressed by an patch.

```
使用方法: errata_listcves エラータ|search:XXX ...
```

3.5.9.8. errata_publish

Publish a patch to a channel.

使用方法: `errata_publish エラータ|search:XXX <チャンネル ...>`

3.5.9.9. errata_search

List patches that meet user provided criteria

例: `errata_search CVE|RHSA|RHBA|RHEA|CLA ...`

例:

```
> errata_search CVE-2009:1674
> errata_search RHSA-2009:1674
```

3.5.9.10. errata_summary

Print a summary of all errata.

使用方法: `errata_summary`

3.5.10. filepreservation

The following spacecmd commands are available for working with kickstart file preservation lists.

3.5.10.1. filepreservation_create

Create a file preservation list.

使用方法: `filepreservation_create [名前] [ファイル ...]`

3.5.10.2. filepreservation_delete

Delete a file preservation list.

`filepreservation_delete NAME`

3.5.10.3. filepreservation_details

Show the details of a file preservation list.

使用方法: `filepreservation_details 名前`

3.5.10.4. filepreservation_list

List all file preservations.

使用方法: `filepreservation_list`

3.5.11. get

The following spacecmd commands are available for use with get.

3.5.11.1. get_apiversion

Display the API version of the server.

使用方法: `get_apiversion`

3.5.11.2. get_certificateexpiration

Print the expiration date of the server's entitlement certificate.

usage: `get_certificateexpiration`

3.5.11.3. get_serverversion

Display SUSE Multi-Linux Manager server version.

使用方法: `get_serverversion`

3.5.11.4. get_session

Show the current session string.

使用方法: `get_session`

3.5.12. group

3.5.12.1. group_addsystems

Add systems to a group.

使用方法: `group_addsystems グループ <システム>`

<SYSTEMS> can be any of the following: `name ssm` (see 'help ssm') `search:QUERY` (see 'help system_search') `group:GROUP` `channel:CHANNEL`

3.5.12.2. group_backup

Backup a system group.

usage: `group_backup NAME [OUTDIR]`

OUTDIR defaults to `$HOME/spacecmd-backup/group/YYYY-MM-DD/NAME`

3.5.12.3. group_create

Create a system group.

使用方法: group_create [名前] [説明]

3.5.12.4. group_delete

Delete a system group.

使用方法: group_delete 名前 ...

3.5.12.5. group_details

Show the details of a system group.

使用方法: group_details グループ ...

3.5.12.6. group_list

List available system groups.

使用方法: group_list

3.5.12.7. group_listsystems

List the members of a group.

使用方法: group_listsystems グループ

3.5.12.8. group_removesystems

Remove systems from a group.

使用方法: group_removesystems グループ <システム>

<SYSTEMS> can be any of the following: name ssm (see 'help ssm') search:QUERY (see 'help system_search') group:GROUP channel:CHANNEL

3.5.12.9. group_restore

Restore a system group.

usage: group_backup INPUTDIR [NAME] ...

3.5.13. kickstart

The following spacecmd functions are available for use with kickstart.

3.5.13.1. kickstart_addactivationkeys

Add activation keys to a Kickstart profile.

使用方法: `kickstart_addactivationkeys` プロファイル <キー ...>

3.5.13.2. kickstart_addchildchannels

Add a child channels to a Kickstart profile.

使用方法: `kickstart_addchildchannels` プロファイル <チャンネル ...>

3.5.13.3. kickstart_addcryptokeys

Add cryptography keys to a Kickstart profile.

使用方法: `kickstart_addcryptokeys` プロファイル <鍵 ...>

3.5.13.4. kickstart_addfilepreservations

Add file preservations to a Kickstart profile.

使用方法: `kickstart_addfilepreservations` プロファイル <ファイルリスト ...>

3.5.13.5. kickstart_adoption

Set an option for a Kickstart profile.

使用方法: `kickstart_adoption` プロファイル キー [値]

3.5.13.6. kickstart_addpackages

Add packages to a Kickstart profile.

使用方法: `kickstart_addpackages` プロファイル <パッケージ ...>

3.5.13.7. kickstart_addscript

Add a script to a Kickstart profile.

usage: `kickstart_addscript` PROFILE [options]

options:
-p PROFILE

```
-e EXECUTION_TIME ['pre', 'post']
-i INTERPRETER
-f FILE
-c execute in a chroot environment
-t ENABLING_TEMPLATING
```

3.5.13.8. kickstart_addvariable

Add a variable to a Kickstart profile.

使用方法: kickstart_addvariable プロファイル キー 値

3.5.13.9. kickstart_clone

Clone a Kickstart profile.

usage: kickstart_clone [options]

options:

```
-n NAME
-c CLONE_NAME
```

3.5.13.10. kickstart_create

Create a Kickstart profile.

usage: kickstart_create [options]

options:

```
-n NAME
-d DISTRIBUTION
-p ROOT_PASSWORD
-v VIRT_TYPE ['none', 'para_host', 'qemu', 'xenfv', 'xenpv']
```

3.5.13.11. kickstart_delete

Delete kickstart profiles.

usage: kickstart_delete PROFILE usage: kickstart_delete PROFILE1 PROFILE2 usage:
kickstart_delete "PROF*"

3.5.13.12. kickstart_details

Show the details of a Kickstart profile.

使用方法: kickstart_details プロファイル

3.5.13.13. kickstart_diff

List differences between two kickstart files.

使用方法: `kickstart_diff` 比較元チャンネル 比較先チャンネル

3.5.13.14. `kickstart_disableconfigmanagement`

Disable configuration management on a Kickstart profile.

使用方法: `kickstart_disableconfigmanagement` プロファイル

3.5.13.15. `kickstart_disableremotecommands`

Disable remote commands on a Kickstart profile.

使用方法: `kickstart_disableremotecommands` プロファイル

3.5.13.16. `kickstart_enableconfigmanagement`

Enable configuration management on a Kickstart profile.

使用方法: `kickstart_enableconfigmanagement` プロファイル

3.5.13.17. `kickstart_enablelogging`

Enable logging for a Kickstart profile.

使用方法: `kickstart_enablelogging` プロファイル

3.5.13.18. `kickstart_enableremotecommands`

Enable remote commands on a Kickstart profile.

使用方法: `kickstart_enableremotecommands` プロファイル

3.5.13.19. `kickstart_export`

Export kickstart profiles to json formatted file.

```
usage: kickstart_export <KSPROFILE>... [options]
options:
  -f outfile.json : specify an output filename, defaults to <KSPROFILE>.json
                   if exporting a single kickstart, profiles.json for multiple
                   kickstarts, or ks_all.json if no KSPROFILE specified
                   e.g (export ALL)
```

Note : KSPROFILE list is optional, default is to export ALL

3.5.13.20. `kickstart_getcontents`

Show the contents of a Kickstart profile as they would be presented to a client.

使用方法: kickstart_getcontents ラベル

3.5.13.21. kickstart_getsoftwaredetails

Gets kickstart profile software details.

```
usage: kickstart_getsoftwaredetails KS_LABEL usage: kickstart_getsoftwaredetails KS_LABEL
KS_LABEL2 ...
```

3.5.13.22. kickstart_getupdatetype

Get the update type for a kickstart profiles.

```
usage: kickstart_getupdatetype PROFILE usage: kickstart_getupdatetype PROFILE1 PROFILE2
usage: kickstart_getupdatetype "PROF*"
```

3.5.13.23. kickstart_import

Import a Kickstart profile from a file.

```
usage: kickstart_import [options]

options:
  -f FILE
  -n NAME
  -d DISTRIBUTION
  -v VIRT_TYPE ['none', 'para_host', 'qemu', 'xenfv', 'xenpv']
```

3.5.13.24. kickstart_import_raw

Import a raw Kickstart or AutoYaST profile from a file.

```
usage: kickstart_import_raw [options]

options:
  -f FILE
  -n NAME
  -d DISTRIBUTION
  -v VIRT_TYPE ['none', 'para_host', 'qemu', 'xenfv', 'xenpv']
```

3.5.13.25. kickstart_importjson

Import kickstart profiles from json file.

使用方法: kickstart_import <JSON_ファイル...>

3.5.13.26. kickstart_list

List the available Kickstart profiles.

使用方法: `kickstart_list`

3.5.13.27. `kickstart_listactivationkeys`

List the activation keys associated with a Kickstart profile.

使用方法: `kickstart_listactivationkeys` プロファイル

3.5.13.28. `kickstart_listchildchannels`

List the child channels of a Kickstart profile.

使用方法: `kickstart_listchildchannels` プロファイル

3.5.13.29. `kickstart_listcryptokeys`

List the crypto keys associated with a Kickstart profile.

使用方法: `kickstart_listcryptokeys` プロファイル

3.5.13.30. `kickstart_listcustomoptions`

List the custom options of a Kickstart profile.

使用方法: `kickstart_listcustomoptions` プロファイル

3.5.13.31. `kickstart_listoptions`

List the options of a Kickstart profile.

使用方法: `kickstart_listoptions` プロファイル

3.5.13.32. `kickstart_listpackages`

List the packages for a Kickstart profile.

使用方法: `kickstart_listpackages` プロファイル

3.5.13.33. `kickstart_listscripts`

List the scripts for a Kickstart profile.

使用方法: `kickstart_listscripts` プロファイル

3.5.13.34. kickstart_listvariables

List the variables of a Kickstart profile.

使用方法: kickstart_listvariables プロファイル

3.5.13.35. kickstart_removeactivationkeys

Remove activation keys from a Kickstart profile.

使用方法: kickstart_removeactivationkeys プロファイル <キー ...>

3.5.13.36. kickstart_removechildchannels

Remove child channels from a Kickstart profile.

使用方法: kickstart_removechildchannels プロファイル <チャンネル ...>

3.5.13.37. kickstart_removecryptokeys

Remove crypto keys from a Kickstart profile.

使用方法: kickstart_removecryptokeys プロファイル <鍵 ...>

3.5.13.38. kickstart_removefilepreservations

Remove file preservations from a Kickstart profile.

使用方法: kickstart_removefilepreservations プロファイル <ファイル ...>

3.5.13.39. kickstart_removeoptions

Remove options from a Kickstart profile.

使用方法: kickstart_removeoptions プロファイル <オプション ...>

3.5.13.40. kickstart_removepackages

Remove packages from a Kickstart profile.

使用方法: kickstart_removepackages プロファイル <パッケージ ...>

3.5.13.41. kickstart_removescript

Add a script to a Kickstart profile.

使用方法: `kickstart_remove_script` プロファイル [ID]

3.5.13.42. `kickstart_removevariables`

Remove variables from a Kickstart profile.

使用方法: `kickstart_removevariables` プロファイル <キー ...>

3.5.13.43. `kickstart_rename`

Rename a Kickstart profile

使用方法: `kickstart_rename` 変更前の名前 変更後の名前

3.5.13.44. `kickstart_setcustomoptions`

Set custom options for a Kickstart profile.

使用方法: `kickstart_setcustomoptions` プロファイル

3.5.13.45. `kickstart_setdistribution`

Set the distribution for a Kickstart profile.

使用方法: `kickstart_setdistribution` プロファイル ディストリビューション

3.5.13.46. `kickstart_setlocale`

Set the locale for a Kickstart profile.

使用方法: `kickstart_setlocale` プロファイル ロケール

3.5.13.47. `kickstart_setpartitions`

Set the partitioning scheme for a Kickstart profile.

使用方法: `kickstart_setpartitions` プロファイル

3.5.13.48. `kickstart_setselinux`

Set the SELinux mode for a Kickstart profile.

使用方法: `kickstart_setselinux` プロファイル モード

3.5.13.49. kickstartsetupdatetype

Set the update type for a kickstart profiles.

```
usage: kickstartsetupdatetype [options] KS_LABEL
options:
  -u UPDATE_TYPE ['red_hat', 'all', 'none']
```

3.5.13.50. kickstart_updatevariable

Update a variable in a Kickstart profile.

使用方法: kickstart_updatevariable プロファイル キー 値

3.5.14. list_proxies

The following spacecmd function is available for listing proxies.

3.5.14.1. list_proxies

List the proxies within the user's organization.

使用方法: list_proxies

3.5.15. login

Connect as a specific user to the SUSE manager server.

```
# spacecmd -- login <USERNAME>
```

3.5.16. logout

Logout from server as the current user.

```
# spacecmd -- logout
```

3.5.17. org

The following **spacecmd** functions are available for use with organizations.

3.5.17.1. org_addtrust

Add a trust between two organizations

使用方法: org_addtrust 信頼元の組織 信頼先の組織

3.5.17.2. org_create

Create an organization.

```
usage: org_create [options]

options:
  -n ORG_NAME
  -u USERNAME
  -P PREFIX (Dr., Mr., Miss, Mrs., Ms.)
  -f FIRST_NAME
  -l LAST_NAME
  -e EMAIL
  -p PASSWORD
  --pam enable PAM authentication
```

3.5.17.3. org_createfirst

Create the initial organization and admin user after completing the installation.

```
usage: org_createfirst [options]

options:
  -n ORG_NAME
  -u USERNAME
  -f FIRST_NAME
  -l LAST_NAME
  -e EMAIL
  -p PASSWORD
```

3.5.17.4. org_delete

Delete an organization.

```
使用方法: org_delete 名前
```

3.5.17.5. org_details

Show the details of an organization.

```
使用方法: org_details 名前
```

3.5.17.6. org_list

List all organizations.

```
使用方法: org_list
```

3.5.17.7. org_listtrusts

List an organization's trusts.

```
org_listtrusts NAME
```

3.5.17.8. org_listusers

List an organization's users.

```
org_listusers NAME
```

3.5.17.9. org_remove trust

Remove a trust between two organizations.

```
使用方法: org_remove trust 信頼元の組織 信頼先の組織
```

3.5.17.10. org_rename

Rename an organization.

```
使用方法: org_rename 変更前の名前 変更後の名前
```

3.5.17.11. org_trustdetails

Show the details of an organizational trust.

```
使用方法: org_trustdetails 信頼する組織
```

3.5.18. パッケージ

The following spacecmd functions are available for working with packages.

3.5.18.1. package_details

Show the details of a software package.

```
usage: package_details PACKAGE ...
```

3.5.18.2. package_listdependencies

List the dependencies for a package.

```
usage: package_listdependencies PACKAGE
```

3.5.18.3. package_listerrata

List the errata that provide this package.

```
usage: package_listerrata PACKAGE ...
```

3.5.18.4. package_listinstalledsystems

List the systems with a package installed.

```
usage: package_listinstalledsystems PACKAGE ...
```

3.5.18.5. package_listorphans

List packages that are not in a channel.

```
使用方法: package_listorphans
```

3.5.18.6. package_remove

Remove a package from SUSE Multi-Linux Manager/Satellite

```
使用方法: package_remove パッケージ ...
```

3.5.18.7. package_removeorphans

Remove packages that are not in a channel.

```
使用方法: package_removeorphans
```

3.5.18.8. package_search

Find packages that meet the given criteria.

```
usage: package_search NAME|QUERY
```

```
Example: package_search kernel
```

Advanced Search

利用可能な項目: name (名前), epoch (エポック), version (バージョン), release (リリース), arch (アーキテクチャ), description (説明), summary (概要)

例: name:kernel AND version:2.6.18 AND -description:devel

3.5.19. proxy_container_config

The following spacecmd functions are available for use with proxy container configuration

3.5.19.1. proxy_container_config_generate_cert

Create SUSE Multi-Linux Manager Proxy container configuration and generate new SSL server certificate for it.

```
usage: proxy_container_config_generate_cert PROXY_FQDN PARENT_FQDN MAX_CACHE EMAIL

parameters:
  PROXY_FQDN  the fully qualified domain name of the proxy to create.
  PARENT_FQDN the fully qualified domain name of the server or another proxy to connect
to.
  MAX_CACHE   the maximum cache size in MB. 60% of the storage is a good value.
  EMAIL       the email of the proxy administrator

options:
  -o, --output Path where to create the generated configuration. Default: 'config.zip'
  -p, --ssh-port SSH port the proxy listens one. Default: 22
  --ca-cert path to the certificate of the CA to use to generate a new proxy certificate.
        Using /root/ssl-build/RHN-ORG-TRUSTED-SSL-CERT by default.
  --ca-key path to the private key of the CA to use to generate a new proxy certificate.
        Using /root/ssl-build/RHN-ORG-PRIVATE-SSL-KEY by default.
  --ca-pass path to a file containing the password of the CA private key, will be prompted
if not passed.
  --ssl-cname alternate name of the proxy to set in the certificate. Can be provided
multiple times
  --ssl-country country code to set in the certificate. If omitted, default values from
mgr-ssl-tool will be used.
  --ssl-state state name to set in the certificate. If omitted, default values from mgr-
ssl-tool will be used.
  --ssl-city the city name to set in the certificate. If omitted, default values from mgr-
ssl-tool will be used.
  --ssl-org the organization name to set in the certificate. If omitted, default values
from mgr-ssl-tool will be used.
  --ssl-org-unit the organization unit name to set in the certificate. If omitted, default
values from mgr-ssl-tool will be used.
  --ssl-email the email to set in the certificate. If omitted, default values from mgr-
ssl-tool will be used.
```

3.5.19.2. proxy_container_config

Create SUSE Multi-Linux Manager Proxy container configuration and use already existing SSL server certificate.

```
usage: proxy_container_config [options] PROXY_FQDN PARENT_FQDN MAX_CACHE EMAIL ROOT_CA CRT
KEY

parameters:
  PROXY_FQDN  the fully qualified domain name of the proxy to create.
  PARENT_FQDN the fully qualified domain name of the server or another proxy to connect
to.
  MAX_CACHE   the maximum cache size in MB. 60% of the storage is a good value.
  EMAIL       the email of the proxy administrator
  CA          path to the root CA used to sign the proxy certificate in PEM format
  CRT         path to the proxy certificate in PEM format
  KEY         path to the proxy certificate private key in PEM format

options:
  -o, --output Path where to create the generated configuration. Default: 'config.zip'
  -p, --ssh-port SSH port the proxy listens one. Default: 22
  -i, --intermediate-ca Path to an intermediate CA used to sign the proxy
```

certificate in PEM format. May be provided multiple times.

3.5.20. repo

The following spacecmd functions are available for working with repositories.

3.5.20.1. repo_addfilters

Add filters for a user repository.

```
usage: repo_addfilters repo <filter ...>
```

3.5.20.2. repo_clearfilters

Clears the filters for a user repository.

```
usage: repo_clearfilters repo
```

3.5.20.3. repo_create

Create a user repository.

```
usage: repo_create <options>

options:
  -n, --name      name of repository
  -u, --url       url of repository

  --ca           SSL CA certificate (not required)
  --cert         SSL Client certificate (not required)
  --key          SSL Client key (not required)
```

3.5.20.4. repo_delete

Delete a user repository.

```
usage: repo_delete <repo ...>
```

3.5.20.5. repo_details

Show the details of a user repository.

```
usage: repo_details <repo ...>
```

3.5.20.6. repo_list

List all available user repository.

```
usage: repo_list
```


3.5.20.7. repo_listfilters

Show the filters for a user repository.

```
usage: repo_listfilters repo
```

===repo_removefilters

Remove filters from a user repository.

```
usage: repo_removefilters repo <filter ...>
```

3.5.20.8. repo_rename

Rename a user repository.

```
usage: repo_rename OLDNAME NEWNAME
```

3.5.20.9. repo_setfilters

Set the filters for a user repo.

```
usage: repo_setfilters repo <filter ...>
```

3.5.20.10. repo_updatessl

Change the SSL certificates of a user repository.

```
usage: repo_updatessl <options>
options:
  --ca          SSL CA certificate (not required)
  --cert        SSL Client certificate (not required)
  --key         SSL Client key (not required)
```

3.5.20.11. repo_updateurl

Change the URL of a user repository.

```
usage: repo_updateurl <repo> <url>
```

3.5.21. report

The following spacecmd functions are available for working with reports.

3.5.21.1. report_duplicates

List duplicate system profiles.

```
usage: report_duplicates
```

3.5.21.2. report_errata

List all errata and how many systems they affect.

```
usage: report_errata [ERRATA|search:XXX ...]
```

3.5.21.2.1. report_inactivesystems

List all inactive systems.

```
usage: report_inactivesystems [DAYS]
```

3.5.21.3. report_ipaddresses

List the hostname and IP of each system.

```
usage: report_network [<SYSTEMS>]
```

<システム> は下記のいずれかを指定できます:

name

ssm ('help ssm' を参照)

search:QUERY ('help system_search' を参照)

group:GROUP

channel:CHANNEL

3.5.21.4. report_kernels

List the running kernel of each system.

```
usage: report_kernels [<SYSTEMS>]
```

<システム> は下記のいずれかを指定できます:

name

ssm ('help ssm' を参照)

search:QUERY ('help system_search' を参照)

group:GROUP

channel:CHANNEL

3.5.21.5. report_outofdatesystems

List all out-of-date systems.

```
usage: report_outofdatesystems
```

3.5.21.6. report_ungroupedsystems

List all ungrouped systems.

```
usage: report_ungroupedsystems
```

3.5.22. scap

The following spacecmd functions are available for working with OpenSCAP.

3.5.22.1. scap_getxccdfscandetails

Get details of given OpenSCAP XCCDF scan.

```
usage: scap_getxccdfscandetails <XID>
```

3.5.22.2. scap_getxccdfscanruleresults

Return a full list of RuleResults for given OpenSCAP XCCDF scan.

```
usage: scap_getxccdfscanruleresults <XID>
```

3.5.22.3. scap_listxccdfscans

Return a list of finished OpenSCAP scans for given systems.

```
usage: scap_listxccdfscans <SYSTEMS>
```

3.5.22.4. scap_scheduledxccdfscan

Schedule Scap XCCDF scan.

```
usage: scap_scheduledxccdfscan PATH_TO_XCCDF_FILE XCCDF_OPTIONS SYSTEMS
```

Example:

```
> scap_scheduledxccdfscan '/usr/share/openscap/scap-security-xccdf.xml' 'profile Web-Default' \
system-scap.example.com
```

3.5.23. スケジュール

The following spacecmd functions are available for working with scheduling.

3.5.23.1. schedule_cancel

Cancel a scheduled action.

```
usage: schedule_cancel ID|* ...
```

3.5.23.2. schedule_details

Show the details of a scheduled action.

```
usage: schedule_details ID
```

3.5.23.3. schedule_getoutput

Show the output from an action.

```
usage: schedule_getoutput ID
```

3.5.23.4. schedule_list

List all actions.

```
usage: schedule_list [BEGINDATE] [ENDDATE]
```

Dates can be any of the following:

Explicit Dates:

Dates can be expressed as explicit date strings in the YYYYMMDD[HHMM] format.

The year, month and day are required, while the hours and minutes are not; the hours and minutes will default to 0000 if no values are provided.

Deltas:

Dates can be expressed as delta values. For example, '2h' would mean 2 hours in the future. You can also use negative values to express times in the past (e.g., -7d would be one week ago).

Units:

s -> seconds

m -> minutes

h -> hours

d -> days

3.5.23.5. schedule_listarchived

List archived actions.

```
usage: schedule_listarchived [BEGINDATE] [ENDDATE]
```

Dates can be any of the following:

Explicit Dates:

Dates can be expressed as explicit date strings in the YYYYMMDD[HHMM] format.

The year, month and day are required, while the hours and minutes are not; the hours and minutes will default to 0000 if no values are provided.

Deltas:

Dates can be expressed as delta values. For example, '2h' would mean 2 hours in the future. You can also use negative values to express times in the past (e.g., -7d would be one week ago).

Units:

s -> seconds

m -> minutes

h -> hours

d -> days

3.5.23.6. schedule_listcompleted

List completed actions.

Dates can be any of the following:

Explicit Dates:

Dates can be expressed as explicit date strings in the YYYYMMDD[HHMM] format.

The year, month and day are required, while the hours and minutes are not; the hours and minutes will default to 0000 if no values are provided.

Deltas:

Dates can be expressed as delta values. For example, '2h' would mean 2 hours in the future. You can also use negative values to express times in the past (e.g., -7d would be one week ago).

Units:

s -> seconds

m -> minutes

h -> hours

d -> days

3.5.23.7. schedule_listfailed

List failed actions.

usage: schedule_listfailed [BEGINDATE] [ENDDATE]

Dates can be any of the following:

Explicit Dates:

Dates can be expressed as explicit date strings in the YYYYMMDD[HHMM] format.

The year, month and day are required, while the hours and minutes are not; the hours and minutes will default to 0000 if no values are provided.

Deltas:

Dates can be expressed as delta values. For example, '2h' would mean 2 hours in the future. You can also use negative values to express times in the past (e.g., -7d would be one week ago).

Units:

s -> seconds

m -> minutes

h -> hours

d -> days

3.5.23.8. schedule_listpending

List pending actions.

usage: schedule_listpending [BEGINDATE] [ENDDATE]

Dates can be any of the following:

Explicit Dates:

Dates can be expressed as explicit date strings in the YYYYMMDD[HHMM] format.

The year, month and day are required, while the hours and minutes are not; the hours and minutes will default to 0000 if no values are provided.

Deltas:

Dates can be expressed as delta values. For example, '2h' would mean 2 hours in the future. You can also use negative values to express times in the past (e.g., -7d would be

```
one week ago).
```

```
Units:
s -> seconds
m -> minutes
h -> hours
d -> days
```

3.5.23.9. schedule_reschedule::

Reschedule failed actions.

```
usage: schedule_reschedule ID|* ...
```

3.5.24. snippet

The following spacecmd functions are available for working with Kickstart snippets.

3.5.24.1. snippet_create

Create a Kickstart snippet

```
usage: snippet_create [options]

options:
  -n NAME
  -f FILE
```

3.5.24.2. snippet_delete

Delete a Kickstart snippet.

```
usage: snippet_removefile NAME
```

3.5.24.3. snippet_details

Show the contents of a snippet.

```
usage: snippet_details SNIPPET ...
```

3.5.24.4. snippet_list

List the available Kickstart snippets.

```
usage: snippet_list
```

3.5.24.5. snippet_update

Update a Kickstart snippet.

```
usage: snippet_update NAME
```

3.5.25. ソフトウェアチャンネル

The following spacecmd functions are available for working with software channels.

3.5.25.1. softwarechannel_adderrata

Add patches from one channel into another channel.

```
usage: softwarechannel_adderrata SOURCE DEST <ERRATA|search:XXX ...>
Options:
  -q/--quick : Don't display list of packages (slightly faster)
  -s/--skip  : Skip errata which appear to exist already in DEST
```

3.5.25.2. softwarechannel_adderratabydate

Add errata from one channel into another channel based on a date range.

```
usage: softwarechannel_adderratabydate [options] SOURCE DEST BEGINDATE ENDDATE
Date format : YYYYMMDD
Options:
  -p/--publish : Publish errata to the channel (don't clone)
```

3.5.25.3. softwarechannel_addpackages

Add packages to a software channel.

```
usage: softwarechannel_addpackages CHANNEL <PACKAGE ...>
```

3.5.25.4. softwarechannel_addrepo

Add a repo to a software channel.

```
usage: softwarechannel_addrepo CHANNEL REPO
```

3.5.25.5. softwarechannel_clone

Clone a software channel.

```
usage: softwarechannel_clone [options]
options:
  -s SOURCE_CHANNEL
  -n NAME
  -l LABEL
  -p PARENT_CHANNEL
  --gpg-copy/-g (copy SOURCE_CHANNEL GPG details)
  --gpg-url GPG_URL
  --gpg-id GPG_ID
  --gpg-fingerprint GPG_FINGERPRINT
```

```
-o do not clone any patches
--regex/-x "s/foo/bar" : Optional regex replacement,
                        replaces foo with bar in the clone name and label
```

3.5.25.6. softwarechannel_clonetree

Clone a software channel and its child channels.

```
usage: softwarechannel_clonetree [options]A
      e.g   softwarechannel_clonetree foobasechannel -p "my_"
            softwarechannel_clonetree foobasechannel -x "s/foo/bar"
            softwarechannel_clonetree foobasechannel -x "s/^/my_"

options:
-s/--source-channel SOURCE_CHANNEL
-p/--prefix PREFIX (is prepended to the label and name of all channels)
--gpg-copy/-g (copy GPG details for corresponding source channel)
--gpg-url GPG_URL (applied to all channels)
--gpg-id GPG_ID (applied to all channels)
--gpg-fingerprint GPG_FINGERPRINT (applied to all channels)
-o do not clone any errata
--regex/-x "s/foo/bar" : Optional regex replacement,
                        replaces foo with bar in the clone name, label and description
```

3.5.25.7. softwarechannel_create

Create a software channel.

```
usage: softwarechannel_create [options]

options:
-n NAME
-l LABEL
-p PARENT_CHANNEL
-a ARCHITECTURE ['ia32', 'ia64', 'x86_64', 'ppc',
                'i386-sun-solaris', 'sparc-sun-solaris']
-c CHECKSUM ['sha1', 'sha256', 'sha384', 'sha512']
-u GPG_URL
-i GPG_ID
-f GPG_FINGERPRINT
```

3.5.25.8. softwarechannel_delete

Delete a software channel.

```
usage: softwarechannel_delete <CHANNEL ...>
```

3.5.25.9. softwarechannel_details

Show the details of a software channel.

```
usage: softwarechannel_details <CHANNEL ...>
```


3.5.25.10. softwarechannel_diff

Check the difference between software channels.

```
usage: softwarechannel_diff SOURCE_CHANNEL TARGET_CHANNEL
```

3.5.25.11. softwarechannel_errata_diff

Check the difference between software channel files.

```
usage: softwarechannel_errata_diff SOURCE_CHANNEL TARGET_CHANNEL
```

3.5.25.12. softwarechannel_errata_sync

Sync errata of two software channels.

```
usage: softwarechannel_errata_sync SOURCE_CHANNEL TARGET_CHANNEL
```

3.5.25.13. softwarechannel_getorgaccess

Get the org-access for the software channel.

```
usage : softwarechannel_getorgaccess : get org access for all channels
usage : softwarechannel_getorgaccess <channel_label(s)> : get org access for specific
channel(s)
```

3.5.25.14. softwarechannel_list

List all available software channels.

```
usage: softwarechannel_list [options]'
options:
  -v verbose (display label and summary)
  -t tree view (pretty-print child-channels)
```

3.5.25.15. softwarechannel_listallpackages

List all packages in a channel.

```
usage: softwarechannel_listallpackages CHANNEL
```

3.5.25.16. softwarechannel_listbasechannels

List all base software channels.

```
usage: softwarechannel_listbasechannels [options]
options:
  -v verbose (display label and summary)
```

3.5.25.17. softwarechannel_listchildchannels

List child software channels.

```
usage:
softwarechannel_listchildchannels [options]
softwarechannel_listchildchannels : List all child channels
softwarechannel_listchildchannels CHANNEL : List children for a specific base channel
options:
-v verbose (display label and summary)
```

3.5.25.18. softwarechannel_listerrata

List the errata associated with a software channel.

```
usage: softwarechannel_listerrata <CHANNEL ...> [from=yyyymmdd [to=yyyymmdd]]
```

3.5.25.19. softwarechannel_listerratabydate

List errata from channelbased on a date range.

```
usage: softwarechannel_listerratabydate CHANNEL BEGINDATE ENDDATE
Date format : YYYYMMDD
```

3.5.25.20. softwarechannel_listlatestpackages

List the newest version of all packages in a channel.

```
usage: softwarechannel_listlatestpackages CHANNEL
```

3.5.25.21. softwarechannel_listpackages

List the most recent packages available from a software channel.

```
usage: softwarechannel_listpackages CHANNEL
```

3.5.25.22. softwarechannel_listrepos

List the repos for a software channel.

```
usage: softwarechannel_listrepos CHANNEL
```

3.5.25.23. softwarechannel_listsyncschedule

List sync schedules for all software channels.

```
usage: softwarechannel_listsyncschedule : List all channels
```

3.5.25.24. softwarechannel_listsystems

List all systems subscribed to a software channel.

```
usage: softwarechannel_listsystems CHANNEL
```

3.5.25.25. softwarechannel_mirrorpackages

Download packages of a given channel.

```
usage: softwarechannel_mirrorpackages CHANNEL
Options:
  -l/--latest : Only mirror latest package version
```

3.5.25.26. softwarechannel_regenerateneededcache

Regenerate the needed errata and package cache for all systems.

```
usage: softwarechannel_regenerateneededcache
```

3.5.25.27. softwarechannel_regenerateyumcache

Regenerate the YUM cache for a software channel.

```
usage: softwarechannel_regenerateyumcache <CHANNEL ...>
```

3.5.25.28. softwarechannel_removeerrata

Remove patches from a software channel.

```
usage: softwarechannel_removeerrata CHANNEL <ERRATA:search:XXX ...>
```

3.5.25.29. softwarechannel_removepackages

Remove packages from a software channel.

```
usage: softwarechannel_removepackages CHANNEL <PACKAGE ...>
```

3.5.25.30. softwarechannel_removerepo

Remove a repo from a software channel.

```
usage: softwarechannel_removerepo CHANNEL REPO
```

3.5.25.31. softwarechannel_removesyncschedule

Removes the repo sync schedule for a software channel.

```
usage: softwarechannel_setsyncschedule <CHANNEL>
```

3.5.25.32. softwarechannel_setorgaccess

Set the org-access for the software channel.

```
usage : softwarechannel_setorgaccess <channel_label> [options]
-d,--disable : disable org access (private, no org sharing)
-e,--enable : enable org access (public access to all trusted orgs)
```

3.5.25.33. softwarechannel_setsyncschedule

Sets the repo sync schedule for a software channel.

```
usage: softwarechannel_setsyncschedule <CHANNEL> <SCHEDULE>
```

The schedule is specified in Quartz CronTrigger format without enclosing quotes.
For example, to set a schedule of every day at 1am, <SCHEDULE> would be 0 0 1 * * ?

3.5.25.34. softwarechannel_sync

Sync the packages of two software channels.

```
usage: softwarechannel_sync SOURCE_CHANNEL TARGET_CHANNEL
```

3.5.25.35. softwarechannel_syncrepos

Sync users repos for a software channel.

```
usage: softwarechannel_syncrepos <CHANNEL ...>
```

3.5.26. ssm

The following spacecmd functions are available for use with the system set manager (SSM).

3.5.26.1. ssm_add

Add systems to the SSM.

```
usage: ssm_add <SYSTEMS>

see 'help ssm' for more details

<システム> は下記のいずれかを指定できます:
name
ssm ('help ssm' を参照)
search:QUERY ('help system_search' を参照)
group:GROUP
channel:CHANNEL
```

3.5.26.2. ssm_clear

Remove all systems from the SSM.

```
usage: ssm_clear
```

3.5.26.3. ssm_intersect

Replace the current SSM with the intersection of the current list of systems and the list of systems passed as arguments.

```
usage: ssm_intersect <SYSTEMS>

see 'help ssm' for more details

<SYSTEMS> can be any of the following:
name
ssm (see 'help ssm')
search:QUERY (see 'help system_search')
group:GROUP
channel:CHANNEL
```

3.5.26.4. ssm_list

List the systems currently in the SSM.

```
usage: ssm_list

see 'help ssm' for more details
```

3.5.26.5. ssm_remove

Remove systems from the SSM.

+

```
usage: ssm_remove <SYSTEMS>

see 'help ssm' for more details

<システム> は下記のいずれかを指定できます:
name
ssm ('help ssm' を参照)
search:QUERY ('help system_search' を参照)
group:GROUP
channel:CHANNEL
```

3.5.27. システム

The following spacecmd functions are available for use with systems.

3.5.27.1. system_addchildchannels

Add child channels to a system.

```
usage: system_addchildchannels <SYSTEMS> <CHANNEL ...>
```

<システム> は下記のいずれかを指定できます:

name

ssm ('help ssm' を参照)

search:QUERY ('help system_search' を参照)

group:GROUP

channel:CHANNEL

3.5.27.2. system_addconfigchannels

Add config channels to a system.

```
usage: system_addconfigchannels <SYSTEMS> <CHANNEL ...> [options]
```

options:

-t add channels to the top of the list

-b add channels to the bottom of the list

<システム> は下記のいずれかを指定できます:

name

ssm ('help ssm' を参照)

search:QUERY ('help system_search' を参照)

group:GROUP

channel:CHANNEL

3.5.27.3. system_addconfigfile

Create a configuration file.

Note this is only for system sandbox or locally-managed files
Centrally managed files should be created via configchannel_addfile
usage: system_addconfigfile [SYSTEM] [options]

options:

-S/--sandbox : list only system-sandbox files

-L/--local : list only locally managed files

-p PATH

-r REVISION

-o OWNER [default: root]

-g GROUP [default: root]

-m MODE [default: 0644]

-x SELINUX_CONTEXT

-d path is a directory

-s path is a symlink

-b path is a binary (or other file which needs base64 encoding)

-t SYMLINK_TARGET

-f local path to file contents

Note re binary/base64: Some text files, notably those containing trailing newlines, those containing ASCII escape characters (or other characters not allowed in XML) need to be sent as binary (-b). Some effort is made to auto-detect files which require this, but you may need to explicitly specify.

3.5.27.4. system_addcustomvalue

Set a custom value for a system.

```
usage: system_addcustomvalue KEY VALUE <SYSTEMS>
```

<システム> は下記のいずれかを指定できます:

name

ssm ('help ssm' を参照)

search:QUERY ('help system_search' を参照)

group:GROUP

channel:CHANNEL

3.5.27.5. system_addentitlements

Add entitlements to a system.

```
usage: system_addentitlements <SYSTEMS> ENTITLEMENT
```

<システム> は下記のいずれかを指定できます:

name

ssm ('help ssm' を参照)

search:QUERY ('help system_search' を参照)

group:GROUP

channel:CHANNEL

3.5.27.6. system_addnote

Set a note for a system.

```
usage: system_addnote <SYSTEM> [options]
```

options:

-s SUBJECT

-b BODY

<システム> は下記のいずれかを指定できます:

name

ssm ('help ssm' を参照)

search:QUERY ('help system_search' を参照)

group:GROUP

channel:CHANNEL

3.5.27.7. system_applyerrata

Apply errata to a system.

```
usage: system_applyerrata <SYSTEMS> [ERRATA|search:XXX ...]
```

<システム> は下記のいずれかを指定できます:

name

ssm ('help ssm' を参照)

search:QUERY ('help system_search' を参照)

group:GROUP

channel:CHANNEL

3.5.27.8. system_comparepackageprofile

Compare a system against a package profile.

```
usage: system_comparepackageprofile <SYSTEMS> PROFILE
```

<システム> は下記のいずれかを指定できます:

name

ssm ('help ssm' を参照)

search:QUERY ('help system_search' を参照)

group:GROUP

channel:CHANNEL

3.5.27.9. system_comparepackages

Compare the packages between two systems.

```
usage: system_comparepackages SOME_SYSTEM ANOTHER_SYSTEM
```

3.5.27.10. system_comparewithchannel

Compare the installed packages on a system with those in the channels it is registered to, or optionally some other channel.

```
usage: system_comparewithchannel <SYSTEMS> [options]
```

options:

```
-c/--channel : Specific channel to compare against,
               default is those subscribed to, including
               child channels
```

<システム> は下記のいずれかを指定できます:

name

ssm ('help ssm' を参照)

search:QUERY ('help system_search' を参照)

group:GROUP

channel:CHANNEL

3.5.27.11. system_createpackageprofile

Create a package profile.

```
usage: system_createpackageprofile SYSTEM [options]
```

options:

```
-n NAME
```

```
-d DESCRIPTION
```

3.5.27.12. system_delete

Delete a system profile.

```
usage: system_delete <SYSTEMS>
```

<システム> は下記のいずれかを指定できます:


```
name
ssm ('help ssm' を参照)
search:QUERY ('help system_search' を参照)
group:GROUP
channel:CHANNEL
```

3.5.27.13. system_deletenotes

Delete notes from a system.

```
usage: system_deletenotes <SYSTEM> <ID|*>

<システム> は下記のいずれかを指定できます:
name
ssm ('help ssm' を参照)
search:QUERY ('help system_search' を参照)
group:GROUP
channel:CHANNEL
```

3.5.27.14. system_deletepackageprofile

Delete a package profile.

```
usage: system_deletepackageprofile PROFILE
```

3.5.27.15. system_deployconfigfiles\

Deploy all configuration files for a system.

```
usage: system_deployconfigfiles <SYSTEMS>

<システム> は下記のいずれかを指定できます:
name
ssm ('help ssm' を参照)
search:QUERY ('help system_search' を参照)
group:GROUP
channel:CHANNEL
```

3.5.27.16. system_details

Show the details of a system profile.

```
usage: system_details <SYSTEMS>

<システム> は下記のいずれかを指定できます:
name
ssm ('help ssm' を参照)
search:QUERY ('help system_search' を参照)
group:GROUP
channel:CHANNEL
```

3.5.27.17. system_installpackage

Install a package on a system.

```
usage: system_installpackage <SYSTEMS> <PACKAGE ...>
```

<システム> は下記のいずれかを指定できます:

name

ssm ('help ssm' を参照)

search:QUERY ('help system_search' を参照)

group:GROUP

channel:CHANNEL

3.5.27.18. system_list

List all system profiles.

```
usage: system_list
```

3.5.27.19. system_listbasechannel

List the base channel for a system.

```
usage: system_listbasechannel <SYSTEMS>
```

<システム> は下記のいずれかを指定できます:

name

ssm ('help ssm' を参照)

search:QUERY ('help system_search' を参照)

group:GROUP

channel:CHANNEL

3.5.27.20. system_listchildchannels

List the child channels for a system.

```
usage: system_listchildchannels <SYSTEMS>
```

<システム> は下記のいずれかを指定できます:

name

ssm ('help ssm' を参照)

search:QUERY ('help system_search' を参照)

group:GROUP

channel:CHANNEL

3.5.27.21. system_listconfigchannels

List the config channels of a system.

```
usage: system_listconfigchannels <SYSTEMS>
```

<システム> は下記のいずれかを指定できます:

name

ssm ('help ssm' を参照)

```
search:QUERY ('help system_search' を参照)
group:GROUP
channel:CHANNEL
```

3.5.27.22. system_listconfigfiles

List the managed config files of a system.

```
usage: system_listconfigfiles <SYSTEMS>
options:
  -s/--sandbox : list only system-sandbox files
  -l/--local   : list only locally managed files
  -c/--central : list only centrally managed files
  -q/--quiet   : quiet mode (omits the header)
```

<システム> は下記のいずれかを指定できます:
 name
 ssm ('help ssm' を参照)
 search:QUERY ('help system_search' を参照)
 group:GROUP
 channel:CHANNEL

3.5.27.23. system_listcustomvalues

List the custom values for a system.

```
usage: system_listcustomvalues <SYSTEMS>
```

<システム> は下記のいずれかを指定できます:
 name
 ssm ('help ssm' を参照)
 search:QUERY ('help system_search' を参照)
 group:GROUP
 channel:CHANNEL

3.5.27.24. system_listentitlements

List the entitlements for a system.

```
usage: system_listentitlements <SYSTEMS>
```

<システム> は下記のいずれかを指定できます:
 name
 ssm ('help ssm' を参照)
 search:QUERY ('help system_search' を参照)
 group:GROUP
 channel:CHANNEL

3.5.27.25. system_listerrata

List available errata for a system.

```
usage: system_listerrata <SYSTEMS>
```

<システム> は下記のいずれかを指定できます:

```
name
ssm ('help ssm' を参照)
search:QUERY ('help system_search' を参照)
group:GROUP
channel:CHANNEL
```

3.5.27.26. system_listeventhistory

List the event history for a system.

```
usage: system_listeventhistory <SYSTEMS> [options]

options:
  -s START_TIME list only the events happened after the specified time. [Default: returns
all events]
  -o OFFSET skip the first events. Ignored if -l is not specified as well. [Default: 0]
  -l LIMIT limit the results to the specified number of events. [Default: no limit]

<システム> は下記のいずれかを指定できます:
name
ssm ('help ssm' を参照)
search:QUERY ('help system_search' を参照)
group:GROUP
channel:CHANNEL
```

3.5.27.27. system_listevents

List the event history for a system.

```
usage: system_listevents <SYSTEMS>

<システム> は下記のいずれかを指定できます:
name
ssm ('help ssm' を参照)
search:QUERY ('help system_search' を参照)
group:GROUP
channel:CHANNEL
```

3.5.27.28. system_listhardware

List the hardware details of a system.

```
usage: system_listhardware <SYSTEMS>

<システム> は下記のいずれかを指定できます:
name
ssm ('help ssm' を参照)
search:QUERY ('help system_search' を参照)
group:GROUP
channel:CHANNEL
```

3.5.27.29. system_listinstalledpackages

List the installed packages on a system.

```
usage: system_listinstalledpackages <SYSTEMS>

<システム> は下記のいずれかを指定できます:
name
ssm ('help ssm' を参照)
search:QUERY ('help system_search' を参照)
group:GROUP
channel:CHANNEL
```

3.5.27.30. system_listnotes

List the available notes for a system.

```
usage: system_listnotes <SYSTEM>

<システム> は下記のいずれかを指定できます:
name
ssm ('help ssm' を参照)
search:QUERY ('help system_search' を参照)
group:GROUP
channel:CHANNEL
```

3.5.27.31. system_listpackageprofiles

List all package profiles.

```
usage: system_listpackageprofiles
```

3.5.27.32. system_listupgrades

List the available upgrades for a system.

```
usage: system_listupgrades <SYSTEMS>

<システム> は下記のいずれかを指定できます:
name
ssm ('help ssm' を参照)
search:QUERY ('help system_search' を参照)
group:GROUP
channel:CHANNEL
```

3.5.27.33. system_lock

Lock a system.

```
usage: system_lock <SYSTEMS>

<システム> は下記のいずれかを指定できます:
name
ssm ('help ssm' を参照)
search:QUERY ('help system_search' を参照)
group:GROUP
channel:CHANNEL
```

3.5.27.34. system_reboot

Reboot a system.

```
usage: system_reboot <SYSTEMS>

<システム> は下記のいずれかを指定できます:
name
ssm ('help ssm' を参照)
search:QUERY ('help system_search' を参照)
group:GROUP
channel:CHANNEL
```

3.5.27.35. system_removechildchannels

Remove child channels from a system.

```
usage: system_removechildchannels <SYSTEMS> <CHANNEL ...>

<システム> は下記のいずれかを指定できます:
name
ssm ('help ssm' を参照)
search:QUERY ('help system_search' を参照)
group:GROUP
channel:CHANNEL
```

3.5.27.36. system_removeconfigchannels

Remove config channels from a system.

```
usage: system_removeconfigchannels <SYSTEMS> <CHANNEL ...>

<システム> は下記のいずれかを指定できます:
name
ssm ('help ssm' を参照)
search:QUERY ('help system_search' を参照)
group:GROUP
channel:CHANNEL
```

3.5.27.37. system_removecustomvalues

Remove a custom value for a system.

```
usage: system_removecustomvalues <SYSTEMS> <KEY ...>

<システム> は下記のいずれかを指定できます:
name
ssm ('help ssm' を参照)
search:QUERY ('help system_search' を参照)
group:GROUP
channel:CHANNEL
```

3.5.27.38. system_removeentitlement

Remove an entitlement from a system.

```
usage: system_removeentitlement <SYSTEMS> ENTITLEMENT
```

<システム> は下記のいずれかを指定できます:

name

ssm ('help ssm' を参照)

search:QUERY ('help system_search' を参照)

group:GROUP

channel:CHANNEL

3.5.27.39. system_removepackage

Remove a package from a system.

```
usage: system_removepackage <SYSTEMS> <PACKAGE ...>
```

<システム> は下記のいずれかを指定できます:

name

ssm ('help ssm' を参照)

search:QUERY ('help system_search' を参照)

group:GROUP

channel:CHANNEL

3.5.27.40. system_rename

Rename a system profile.

```
usage: system_rename OLDNAME NEWNAME
```

3.5.27.41. system_runscript

Schedule a script to run on the list of systems provided.

```
usage: system_runscript <SYSTEMS> [options]
```

options:

-u USER

-g GROUP

-t TIMEOUT

-s START_TIME

-l LABEL

-f FILE

<システム> は下記のいずれかを指定できます:

name

ssm ('help ssm' を参照)

search:QUERY ('help system_search' を参照)

group:GROUP

channel:CHANNEL

Dates can be any of the following:

Explicit Dates:

Dates can be expressed as explicit date strings in the YYYYMMDD[HHMM]

format. The year, month and day are required, while the hours and

minutes are not; the hours and minutes will default to 0000 if no

values are provided.

Deltas:

Dates can be expressed as delta values. For example, '2h' would mean 2 hours in the future. You can also use negative values to express times in the past (e.g., -7d would be one week ago).

Units:

s -> seconds
m -> minutes
h -> hours
d -> days

3.5.27.42. system_schedulehardwarerefresh

Schedule a hardware refresh for a system.

```
usage: system_schedulehardwarerefresh <SYSTEMS>
```

<システム> は下記のいずれかを指定できます:

name
ssm ('help ssm' を参照)
search:QUERY ('help system_search' を参照)
group:GROUP
channel:CHANNEL

3.5.27.43. system_schedulepackagerefresh

Schedule a software package refresh for a system.

```
usage: system_schedulepackagerefresh <SYSTEMS>
```

<システム> は下記のいずれかを指定できます:

name
ssm ('help ssm' を参照)
search:QUERY ('help system_search' を参照)
group:GROUP
channel:CHANNEL

3.5.27.44. system_search

List systems that match the given criteria.

```
usage: system_search QUERY
```

Available Fields:

id
name
ip
hostname
device
vendor
driver
uuid

Examples:

```
> system_search device:vmware  
> system_search ip:192.168.82
```


3.5.27.45. system_setbasechannel

Set a system's base software channel.

```
usage: system_setbasechannel <SYSTEMS> CHANNEL
```

<システム> は下記のいずれかを指定できます:

name

ssm ('help ssm' を参照)

search:QUERY ('help system_search' を参照)

group:GROUP

channel:CHANNEL

3.5.27.46. system_setconfigchannelorder

Set the ranked order of configuration channels.

```
usage: system_setconfigchannelorder <SYSTEMS>
```

<システム> は下記のいずれかを指定できます:

name

ssm ('help ssm' を参照)

search:QUERY ('help system_search' を参照)

group:GROUP

channel:CHANNEL

3.5.27.47. system_setcontactmethod

Set the contact method for a given system.

Available contact methods: ['default', 'ssh-push', 'ssh-push-tunnel']

```
usage: system_setcontactmethod <SYSTEMS> <CONTACT_METHOD>
```

<システム> は下記のいずれかを指定できます:

name

ssm ('help ssm' を参照)

search:QUERY ('help system_search' を参照)

group:GROUP

channel:CHANNEL

3.5.27.48. system_show_packageversion

Shows version of installed package on a given system.

```
usage: system_show_packageversion <SYSTEM> <PACKAGE>
```

<システム> は下記のいずれかを指定できます:

name

ssm ('help ssm' を参照)

search:QUERY ('help system_search' を参照)

group:GROUP

channel:CHANNEL

3.5.27.49. system_syncpackages

Sync packages between two systems.

```
usage: system_syncpackages SOURCE TARGET
```

system_unlock

Unlock a system.

```
usage: system_unlock <SYSTEMS>
```

<システム> は下記のいずれかを指定できます:

name

ssm ('help ssm' を参照)

search:QUERY ('help system_search' を参照)

group:GROUP

channel:CHANNEL

3.5.27.50. system_updatecustomvalue

Update a custom value for a system.

```
usage: system_updatecustomvalue KEY VALUE <SYSTEMS>
```

<システム> は下記のいずれかを指定できます:

name

ssm ('help ssm' を参照)

search:QUERY ('help system_search' を参照)

group:GROUP

channel:CHANNEL

3.5.27.51. system_upgradepackage

Upgrade a package on a system.

```
usage: system_upgradepackage <SYSTEMS> <PACKAGE ...>|*
```

<システム> は下記のいずれかを指定できます:

name

ssm ('help ssm' を参照)

search:QUERY ('help system_search' を参照)

group:GROUP

channel:CHANNEL

3.5.28. toggle

The following spacecmd functions are available to toggle functions on and off.

3.5.28.1. toggle_confirmations

Toggle confirmation messages on/off.

```
usage: toggle_confirmations
```

3.5.29. user

The following spacecmd functions are available managing users.

3.5.29.1. user_adddefaultgroup

Add a default group to an user account.

```
usage: user_adddefaultgroup USER <GROUP ...>
```

3.5.29.2. user_addgroup

Add a group to an user account.

```
usage: user_addgroup USER <GROUP ...>
```

3.5.29.3. user_addrole

Add a role to an user account.

```
usage: user_addrole USER ROLE
```

3.5.29.4. user_create

Create an user.

```
usage: user_create [options]

options:
  -u USERNAME
  -f FIRST_NAME
  -l LAST_NAME
  -e EMAIL
  -p PASSWORD
  --pam enable PAM authentication
```

3.5.29.5. user_delete

Delete an user.

```
usage: user_delete NAME
```

3.5.29.6. user_details

Show the details of an user.

```
usage: user_details USER ...
```

3.5.29.7. user_disable

Disable an user account.

```
usage: user_disable NAME
```

3.5.29.8. user_enable

Enable an user account.

```
usage: user_enable NAME
```

3.5.29.9. user_list

List all users.

```
usage: user_list
```

3.5.29.10. user_listavailableroles

List all available roles for users.

```
usage: user_listavailableroles
```

3.5.29.11. user_removedefaultgroup

Remove a default group from an user account.

```
usage: user_removedefaultgroup USER <GROUP ...>
```

3.5.29.12. user_removegroup

Remove a group to an user account.

```
usage: user_removegroup USER <GROUP ...>
```

3.5.29.13. user_removeole

Remove a role from an user account.

```
usage: user_removeole USER ROLE
```

3.5.29.14. user_setemail

Set an user accounts email field.

```
usage: user_setemail USER EMAIL
```

3.5.29.15. user_setfirstname

Set an user accounts first name field.

```
usage: user_setfirstname USER FIRST_NAME
```

3.5.29.16. user_setlastname

Set an user accounts last name field.

```
usage: user_setlastname USER LAST_NAME
```

3.5.29.17. user_setpassword

Set an user accounts name prefix field.

```
usage: user_setpassword USER PASSWORD
```

3.5.29.18. user_setprefix

Set an user accounts name prefix field.

```
usage: user_setprefix USER PREFIX
```

3.5.30. whoami

The following command is available for returning the currently logged spacecmd username.

3.5.30.1. whoami

Print the currently logged spacecmd user.

```
spacecmd {SSM:0}> whoami  
admin
```

3.5.31. whoamitalkingto

The following spacecmd function is available for returning the server hostname.

3.5.31.1. whoamitalkingto

Return the server hostname that spacecmd is connected with.

```
spacecmd {SSM:0}> whoamitalkingto
MGR_SERVER_HOSTNAME
```

3.5.32. Miscellaneous Help Topics

The following help topics are printed with all functions requiring the relevant information.

3.5.32.1. time

Dates can be any of the following:

```
Explicit Dates:
Dates can be expressed as explicit date strings in the YYYYMMDD[HHMM] format.
The year, month and day are required, while the hours and minutes are not; the hours and
minutes will default to 0000 if no values are provided.

Deltas:
Dates can be expressed as delta values.
For example, '2h' would mean 2 hours in the future.
You can also use negative values to express times in the past (e.g., -7d would be one week
ago).

Units:
s -> seconds
m -> minutes
h -> hours
d -> days
```

3.5.32.2.

<SYSTEMS> can be any of the following:

```
name
ssm (see 'help ssm')
search:QUERY (see 'help system_search')
group:GROUP
channel:CHANNEL
```

3.5.32.3. ssm

The System Set Manager (SSM) is a group of systems that you can perform tasks on as a group.

```
Adding Systems:
> ssm_add group:rhel5-x86_64
> ssm_add channel:rhel-x86_64-server-5
> ssm_add search:device:vmware
> ssm_add host.example.com

Intersections:
> ssm_add group:rhel5-x86_64
> ssm_intersect group:web-servers

Using the SSM:
> system_installpackage ssm zsh
> system_runscript ssm
```

Chapter 4. Command Line Tools



サーバコンテナ内でシェルにアクセスするには、コンテナホストで**mgrctl term**を実行します。そこから、CLIツールを通常どおりに実行できます。

There are several command line tools available in SUSE Multi-Linux Manager. Every action that can be completed using the Web UI can be performed at a command prompt instead. Additionally, there are some actions that can only be performed at the command prompt.

Manage package and channel synchronization with:

- **spacewalk-repo-sync**
- **mgr-sync**

Manage bootstrapping with:

- **mgr-create-bootstrap-repo**

Manage the database with:

- **smdba**

Some of these command line tools are installed by default. To install a command line tool, you can use the SUSE Multi-Linux Manager Web UI, or use your package manager at the command prompt.

Procedure: Installing Command Line Tools with the WebUI

1. In the SUSE Multi-Linux Manager Web UI, navigate to **Systems › System List**, select the client to install the tool on, and navigate to the **Software › Packages › Install** sub-tab.
2. Use the search tool to search for the command line tool you want to install.
3. Check the package to install, and click [**Install Selected Packages**].
4. Click [**Confirm**] to begin installation.

Procedure: Installing Command Line Tools from the Command Prompt

1. On the client that you want to install the packages on, at the command prompt, as root, use zypper to install the package:

```
zypper in <CLI_TOOL_NAME>
```

4.1. Synchronization CLI Tools



サーバコンテナ内でシェルにアクセスするには、コンテナホストで**mgrctl term**を実行します。そこから、CLIツールを通常どおりに実行できます。

There are two tools for synchronizing clients to the server. For clients that are connected to the SUSE Customer Center, use **mgr-sync**. For all other clients, use **spacewalk-repo-sync**.

4.1.1. Synchronize SCC Repositories With mgr-sync

The primary use of **mgr-sync** is to connect to the SUSE Customer Center, retrieve product and package information, and prepare channels for synchronization with the SUSE Multi-Linux Manager Server.

このツールは、SUSEサポートサブスクリプションで使用するよう設計されています。
openSUSE、CentOS、Ubuntuなどのオープンソースディストリビューションには必要ありません。

mgr-syncに使用できるコマンドおよび引数を以下の表に一覧表示しています。 **mgr-sync**コマンドには次の構文を使用します。

```
mgr-sync [-h] [--version] [-v] [-s] [-d {1,2,3}] {list,add,refresh,delete}
```

表 38. mgr-syncコマンド

| コマンド | 説明 | 使用例 |
|---------|------------------------------------|---------------------------------------------------|
| list | チャンネル、組織の資格情報、または製品を一覧表示する | mgr-sync list channels |
| add | チャンネル、組織の資格情報、または製品を追加する | mgr-sync add channel <channel_name> |
| refresh | 製品、チャンネル、およびサブスクリプションのローカルコピーを更新する | mgr-sync refresh |
| delete | ローカルシステムから既存のSCC組織の資格情報を削除する | mgr-sync delete credentials |
| sync | 指定されたチャンネルを同期するか、空白のままの場合は尋ねる | mgr-sync sync channel <channel_name> |

コマンドに固有のオプションの全リストを表示するには、次のコマンドを使用します。

```
mgr-sync <command> --help
```

表 39. mgr-syncオプション引数

| オプション | 短縮オプション | 説明 | 使用例 |
|---------|----------|-------------------------------------------|-----------------------------------|
| help | h | コマンドの使用方法和オプションを表示する | mgr-sync --help |
| version | N/A | 現在インストールされているバージョンの mgr-sync を表示する | mgr-sync --version |
| verbose | v | 詳細な出力を提供する | mgr-sync --verbose refresh |

| オプション | 短縮オプション | 説明 | 使用例 |
|-------------------|----------|-------------------------------------------------------|----------------------------------------------------|
| store-credentials | s | 資格情報をローカルの隠しファイルに保存する | mgr-sync --store-credentials |
| debug | d | 追加のデバッグ情報をログに記録する。レベル1、2、3が必要です。3は、最も多くのデバッグ情報を提供します。 | mgr-sync -d 3 refresh |
| no-sync | N/A | add コマンドと一緒に使用して、同期を開始せずに製品またはチャンネルを追加する | mgr-sync --no-sync add <channel_name> |

mgr-syncのログは次の場所にあります。

- **/var/log/rhn/mgr-sync.log**
- **/var/log/rhn/rhn_web_api.log**

4.1.2. Synchronize Repositories with spacewalk-repo-sync

The **spacewalk-repo-sync** tool synchronizes software repositories into SUSE Multi-Linux Manager channels. In most cases, this happens automatically, but you can use the tool to run it manually if required.

The **spacewalk-repo-sync** tool has these primary commands:

表 40. spacewalk-repo-sync Options

| Option | Description | Example Use |
|------------------|------------------------------------------------------------------|-------------------------------------------------------------|
| list | List all custom channels and the repositories assigned to them. | spacewalk-repo-sync --list |
| channel | Synchronize a single channel to all repositories assigned to it. | spacewalk-repo-sync --channel <custom-channel> |
| deep-verify | ignore cached package checksums. | spacewalk-repo-sync --deep-verify |
| force-all-errata | force re-importing all the patches. | spacewalk-repo-sync --deep-verify |
| no-packages | excludes packages from the operation. | spacewalk-repo-sync --deep-verify --no-packages |

For a complete list of options, see the **spacewalk-repo-sync** manpage:

```
man spacewalk-repo-sync
```

4.1.3. 同期のトラブルシューティング

If you are having trouble synchronizing with **spacewalk-repo-sync** you can find out more by watching the HTTP log as the command runs.

Procedure: Troubleshooting Synchronization Problems

1. Log the HTTP output into **/var/log/zypper.log**:

```
ZYPP_MEDIA_CURL_DEBUG=2 spacewalk-repo-sync --channel <channel-label>
```

2. Export the setting:

```
export URLGRABBER_DEBUG=DEBUG
```

3. Start the synchronization:

```
/usr/bin/spacewalk-repo-sync --channel <channel-label> --type yum
```

You can increase the debug level, by adding the `[option]``-vvv``` option to the command.

4. When the complete completes, or fails, disable debug mode:

```
unset URLGRABBER_DEBUG
```

4.1.3.1. Add Custom Extra HTTP Headers

You can add custom HTTP headers to the requests made by **spacewalk-repo-sync** at the time of synchronization. The custom HTTP headers are defined in the **/etc/rhn/spacewalk-repo-sync/extra_headers.conf** configuration file. The headers can be defined by repository name or channel label. You can also define global headers by putting them in the **main** section. For example:

```
[testchannel]
X-MY-HEADER-1=VALUE
X-MY-HEADER-2=VALUE

[mychannel]
X-MY-HEADER-3=VALUE
X-MY-HEADER-4=VALUE

[main]
X-MYGLOBAL-HEADER=VALUE
```

This can be particularly useful when dealing with Red Hat Update Infrastructure (RHUI) repositories in the public cloud.

4.2. Channel Management CLI Tools



サーバコンテナ内でシェルにアクセスするには、コンテナホストで**mgrctl term**を実行します。そこから、CLIツールを通常どおりに実行できます。

There are tools for managing channels on the server. With **spacewalk-remove-channel**, list and delete channels in various ways.

4.2.1. Manage Channels with **spacewalk-remove-channel**

Usage: **spacewalk-remove-channel** [options]

The use of **spacewalk-remove-channel** is to remove channels in various ways.

The available commands and arguments for **spacewalk-remove-channel** are listed in this table. Use this syntax for **spacewalk-remove-channel** commands:

```
spacewalk-remove-channel [options]
```

The **spacewalk-remove-channel** tool has these primary commands:

表 41. **spacewalk-remove-channel** Options

| Option | Description | Example Use |
|-----------------------|----------------------------------------------------------------------------------------|-------------------------------------------------------------------------------|
| list | List defined channels and exit. | spacewalk-remove-channel --list |
| channel | Delete this channel (can be present multiple times). | spacewalk-remove-channel --channel=CHANNEL |
| channel-with-children | Delete this channel and its child channels (can be present multiple times). | spacewalk-remove-channel --channel-with-children=CHANNEL_WITH_CHILDREN |
| unsubscribe | Unsubscribe systems registered to the specified channels. Note: Credentials are needed | spacewalk-remove-channel --unsubscribe |
| justdb | Delete only from the database, do not remove files from disk. | spacewalk-remove-channel --justdb |
| just-kickstart-trees | Remove only the kickstart trees for the channels specified. | spacewalk-remove-channel --just-kickstart-trees |
| skip-channels | Remove only packages from channel not the channel itself. | spacewalk-remove-channel --skip-channels |

For a complete list of options and abbreviated options, see the **--help** output or the **spacewalk-remove-channel** manpage:

```
man spacewalk-remove-channel
```

For more information, see [Administration › Removing-channels](#).

4.3. Bootstrapping Command Line Tools



- To access a shell inside the Server container run **mgrctl term** on the container host.
- From there, one can run the CLI tools as usual.

The **mgr-create-bootstrap-repo** tool allows you to create a bootstrap repository.

Use the **mgr-create-bootstrap-repo** command on the SUSE Multi-Linux Manager Server to create a new bootstrap repository. The **-l** option lists all available repositories:

```
mgr-create-bootstrap-repo -l
```

Give the repository name to create the bootstrap repository you require:

```
mgr-create-bootstrap-repo <repo-name>
```

You can also create a new bootstrap repository from a custom channel, with the **--with-custom-channels** option:

```
mgr-create-bootstrap-repo --with-custom-channels
```

If you create a bootstrap repository that contains custom channels, and later attempt to rebuild with the **mgr-create-bootstrap-repo** command, the custom channel information will remain in the bootstrap repository. To remove custom channel information from your bootstrap repository, use the **--flush** option when you rebuild:

```
mgr-create-bootstrap-repo --flush
```

Chapter 5. GNU Free Documentation License

Copyright © 2000, 2001, 2002 Free Software Foundation, Inc. 51 Franklin St, Fifth Floor, Boston, MA 02110-1301 USA. Everyone is permitted to copy and distribute verbatim copies of this license document, but changing it is not allowed.

0. PREAMBLE

The purpose of this License is to make a manual, textbook, or other functional and useful document "free" in the sense of freedom: to assure everyone the effective freedom to copy and redistribute it, with or without modifying it, either commercially or noncommercially. Secondly, this License preserves for the author and publisher a way to get credit for their work, while not being considered responsible for modifications made by others.

This License is a kind of "copyleft", which means that derivative works of the document must themselves be free in the same sense. It complements the GNU General Public License, which is a copyleft license designed for free software.

We have designed this License in order to use it for manuals for free software, because free software needs free documentation: a free program should come with manuals providing the same freedoms that the software does. But this License is not limited to software manuals; it can be used for any textual work, regardless of subject matter or whether it is published as a printed book. We recommend this License principally for works whose purpose is instruction or reference.

1. APPLICABILITY AND DEFINITIONS

This License applies to any manual or other work, in any medium, that contains a notice placed by the copyright holder saying it can be distributed under the terms of this License. Such a notice grants a world-wide, royalty-free license, unlimited in duration, to use that work under the conditions stated herein. The "Document", below, refers to any such manual or work. Any member of the public is a licensee, and is addressed as "you". You accept the license if you copy, modify or distribute the work in a way requiring permission under copyright law.

A "Modified Version" of the Document means any work containing the Document or a portion of it, either copied verbatim, or with modifications and/or translated into another language.

A "Secondary Section" is a named appendix or a front-matter section of the Document that deals exclusively with the relationship of the publishers or authors of the Document to the Document's overall subject (or to related matters) and contains nothing that could fall directly within that overall subject. (Thus, if the Document is in part a textbook of mathematics, a Secondary Section may not explain any mathematics.) The relationship could be a matter of historical connection with the subject or with related matters, or of legal, commercial, philosophical, ethical or political position regarding them.

The "Invariant Sections" are certain Secondary Sections whose titles are designated, as being those of Invariant Sections, in the notice that says that the Document is released under this License. If a section does not fit the above definition of Secondary then it is not allowed to be designated as Invariant. The Document may contain zero Invariant Sections. If the Document does not identify any Invariant Sections

then there are none.

The "Cover Texts" are certain short passages of text that are listed, as Front-Cover Texts or Back-Cover Texts, in the notice that says that the Document is released under this License. A Front-Cover Text may be at most 5 words, and a Back-Cover Text may be at most 25 words.

A "Transparent" copy of the Document means a machine-readable copy, represented in a format whose specification is available to the general public, that is suitable for revising the document straightforwardly with generic text editors or (for images composed of pixels) generic paint programs or (for drawings) some widely available drawing editor, and that is suitable for input to text formatters or for automatic translation to a variety of formats suitable for input to text formatters. A copy made in an otherwise Transparent file format whose markup, or absence of markup, has been arranged to thwart or discourage subsequent modification by readers is not Transparent. An image format is not Transparent if used for any substantial amount of text. A copy that is not "Transparent" is called "Opaque".

Examples of suitable formats for Transparent copies include plain ASCII without markup, Texinfo input format, LaTeX input format, SGML or XML using a publicly available DTD, and standard-conforming simple HTML, PostScript or PDF designed for human modification. Examples of transparent image formats include PNG, XCF and JPG. Opaque formats include proprietary formats that can be read and edited only by proprietary word processors, SGML or XML for which the DTD and/or processing tools are not generally available, and the machine-generated HTML, PostScript or PDF produced by some word processors for output purposes only.

The "Title Page" means, for a printed book, the title page itself, plus such following pages as are needed to hold, legibly, the material this License requires to appear in the title page. For works in formats which do not have any title page as such, "Title Page" means the text near the most prominent appearance of the work's title, preceding the beginning of the body of the text.

A section "Entitled XYZ" means a named subunit of the Document whose title either is precisely XYZ or contains XYZ in parentheses following text that translates XYZ in another language. (Here XYZ stands for a specific section name mentioned below, such as "Acknowledgements", "Dedications", "Endorsements", or "History".) To "Preserve the Title" of such a section when you modify the Document means that it remains a section "Entitled XYZ" according to this definition.

The Document may include Warranty Disclaimers next to the notice which states that this License applies to the Document. These Warranty Disclaimers are considered to be included by reference in this License, but only as regards disclaiming warranties: any other implication that these Warranty Disclaimers may have is void and has no effect on the meaning of this License.

2. VERBATIM COPYING

You may copy and distribute the Document in any medium, either commercially or noncommercially, provided that this License, the copyright notices, and the license notice saying this License applies to the Document are reproduced in all copies, and that you add no other conditions whatsoever to those of this License. You may not use technical measures to obstruct or control the reading or further copying of the copies you make or distribute. However, you may accept compensation in exchange for copies. If you distribute a large enough number of copies you must also follow the conditions in section 3.

You may also lend copies, under the same conditions stated above, and you may publicly display copies.

3. COPYING IN QUANTITY

If you publish printed copies (or copies in media that commonly have printed covers) of the Document, numbering more than 100, and the Document's license notice requires Cover Texts, you must enclose the copies in covers that carry, clearly and legibly, all these Cover Texts: Front-Cover Texts on the front cover, and Back-Cover Texts on the back cover. Both covers must also clearly and legibly identify you as the publisher of these copies. The front cover must present the full title with all words of the title equally prominent and visible. You may add other material on the covers in addition. Copying with changes limited to the covers, as long as they preserve the title of the Document and satisfy these conditions, can be treated as verbatim copying in other respects.

If the required texts for either cover are too voluminous to fit legibly, you should put the first ones listed (as many as fit reasonably) on the actual cover, and continue the rest onto adjacent pages.

If you publish or distribute Opaque copies of the Document numbering more than 100, you must either include a machine-readable Transparent copy along with each Opaque copy, or state in or with each Opaque copy a computer-network location from which the general network-using public has access to download using public-standard network protocols a complete Transparent copy of the Document, free of added material. If you use the latter option, you must take reasonably prudent steps, when you begin distribution of Opaque copies in quantity, to ensure that this Transparent copy will remain thus accessible at the stated location until at least one year after the last time you distribute an Opaque copy (directly or through your agents or retailers) of that edition to the public.

It is requested, but not required, that you contact the authors of the Document well before redistributing any large number of copies, to give them a chance to provide you with an updated version of the Document.

4. MODIFICATIONS

You may copy and distribute a Modified Version of the Document under the conditions of sections 2 and 3 above, provided that you release the Modified Version under precisely this License, with the Modified Version filling the role of the Document, thus licensing distribution and modification of the Modified Version to whoever possesses a copy of it. In addition, you must do these things in the Modified Version:

- A. Use in the Title Page (and on the covers, if any) a title distinct from that of the Document, and from those of previous versions (which should, if there were any, be listed in the History section of the Document). You may use the same title as a previous version if the original publisher of that version gives permission.
- B. List on the Title Page, as authors, one or more persons or entities responsible for authorship of the modifications in the Modified Version, together with at least five of the principal authors of the Document (all of its principal authors, if it has fewer than five), unless they release you from this requirement.
- C. State on the Title page the name of the publisher of the Modified Version, as the publisher.
- D. Preserve all the copyright notices of the Document.
- E. Add an appropriate copyright notice for your modifications adjacent to the other copyright notices.
- F. Include, immediately after the copyright notices, a license notice giving the public permission to use the Modified Version under the terms of this License, in the form shown in the Addendum

below.

- G. Preserve in that license notice the full lists of Invariant Sections and required Cover Texts given in the Document's license notice.
- H. Include an unaltered copy of this License.
- I. Preserve the section Entitled "History", Preserve its Title, and add to it an item stating at least the title, year, new authors, and publisher of the Modified Version as given on the Title Page. If there is no section Entitled "History" in the Document, create one stating the title, year, authors, and publisher of the Document as given on its Title Page, then add an item describing the Modified Version as stated in the previous sentence.
- J. Preserve the network location, if any, given in the Document for public access to a Transparent copy of the Document, and likewise the network locations given in the Document for previous versions it was based on. These may be placed in the "History" section. You may omit a network location for a work that was published at least four years before the Document itself, or if the original publisher of the version it refers to gives permission.
- K. For any section Entitled "Acknowledgements" or "Dedications", Preserve the Title of the section, and preserve in the section all the substance and tone of each of the contributor acknowledgements and/or dedications given therein.
- L. Preserve all the Invariant Sections of the Document, unaltered in their text and in their titles. Section numbers or the equivalent are not considered part of the section titles.
- M. Delete any section Entitled "Endorsements". Such a section may not be included in the Modified Version.
- N. Do not retitle any existing section to be Entitled "Endorsements" or to conflict in title with any Invariant Section.
- O. Preserve any Warranty Disclaimers.

If the Modified Version includes new front-matter sections or appendices that qualify as Secondary Sections and contain no material copied from the Document, you may at your option designate some or all of these sections as invariant. To do this, add their titles to the list of Invariant Sections in the Modified Version's license notice. These titles must be distinct from any other section titles.

You may add a section Entitled "Endorsements", provided it contains nothing but endorsements of your Modified Version by various parties—for example, statements of peer review or that the text has been approved by an organization as the authoritative definition of a standard.

You may add a passage of up to five words as a Front-Cover Text, and a passage of up to 25 words as a Back-Cover Text, to the end of the list of Cover Texts in the Modified Version. Only one passage of Front-Cover Text and one of Back-Cover Text may be added by (or through arrangements made by) any one entity. If the Document already includes a cover text for the same cover, previously added by you or by arrangement made by the same entity you are acting on behalf of, you may not add another; but you may replace the old one, on explicit permission from the previous publisher that added the old one.

The author(s) and publisher(s) of the Document do not by this License give permission to use their names for publicity for or to assert or imply endorsement of any Modified Version.

5. COMBINING DOCUMENTS

You may combine the Document with other documents released under this License, under the terms defined in section 4 above for modified versions, provided that you include in the combination all of the Invariant Sections of all of the original documents, unmodified, and list them all as Invariant Sections of your combined work in its license notice, and that you preserve all their Warranty Disclaimers.

The combined work need only contain one copy of this License, and multiple identical Invariant Sections may be replaced with a single copy. If there are multiple Invariant Sections with the same name but different contents, make the title of each such section unique by adding at the end of it, in parentheses, the name of the original author or publisher of that section if known, or else a unique number. Make the same adjustment to the section titles in the list of Invariant Sections in the license notice of the combined work.

In the combination, you must combine any sections Entitled "History" in the various original documents, forming one section Entitled "History"; likewise combine any sections Entitled "Acknowledgements", and any sections Entitled "Dedications". You must delete all sections Entitled "Endorsements".

6. COLLECTIONS OF DOCUMENTS

You may make a collection consisting of the Document and other documents released under this License, and replace the individual copies of this License in the various documents with a single copy that is included in the collection, provided that you follow the rules of this License for verbatim copying of each of the documents in all other respects.

You may extract a single document from such a collection, and distribute it individually under this License, provided you insert a copy of this License into the extracted document, and follow this License in all other respects regarding verbatim copying of that document.

7. AGGREGATION WITH INDEPENDENT WORKS

A compilation of the Document or its derivatives with other separate and independent documents or works, in or on a volume of a storage or distribution medium, is called an "aggregate" if the copyright resulting from the compilation is not used to limit the legal rights of the compilation's users beyond what the individual works permit. When the Document is included in an aggregate, this License does not apply to the other works in the aggregate which are not themselves derivative works of the Document.

If the Cover Text requirement of section 3 is applicable to these copies of the Document, then if the Document is less than one half of the entire aggregate, the Document's Cover Texts may be placed on covers that bracket the Document within the aggregate, or the electronic equivalent of covers if the Document is in electronic form. Otherwise they must appear on printed covers that bracket the whole aggregate.

8. TRANSLATION

Translation is considered a kind of modification, so you may distribute translations of the Document under the terms of section 4. Replacing Invariant Sections with translations requires special permission from their copyright holders, but you may include translations of some or all Invariant Sections in addition to the original versions of these Invariant Sections. You may include a translation of this

License, and all the license notices in the Document, and any Warranty Disclaimers, provided that you also include the original English version of this License and the original versions of those notices and disclaimers. In case of a disagreement between the translation and the original version of this License or a notice or disclaimer, the original version will prevail.

If a section in the Document is Entitled "Acknowledgements", "Dedications", or "History", the requirement (section 4) to Preserve its Title (section 1) will typically require changing the actual title.

9. TERMINATION

You may not copy, modify, sublicense, or distribute the Document except as expressly provided for under this License. Any other attempt to copy, modify, sublicense or distribute the Document is void, and will automatically terminate your rights under this License. However, parties who have received copies, or rights, from you under this License will not have their licenses terminated so long as such parties remain in full compliance.

10. FUTURE REVISIONS OF THIS LICENSE

The Free Software Foundation may publish new, revised versions of the GNU Free Documentation License from time to time. Such new versions will be similar in spirit to the present version, but may differ in detail to address new problems or concerns. See <http://www.gnu.org/copyleft/>.

Each version of the License is given a distinguishing version number. If the Document specifies that a particular numbered version of this License "or any later version" applies to it, you have the option of following the terms and conditions either of that specified version or of any later version that has been published (not as a draft) by the Free Software Foundation. If the Document does not specify a version number of this License, you may choose any version ever published (not as a draft) by the Free Software Foundation.

ADDENDUM: How to use this License for your documents

Copyright (c) YEAR YOUR NAME.

Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.2 or any later version published by the Free Software Foundation; with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts. A copy of the license is included in the section entitled "GNU Free Documentation License".