

使用 systemd 计时器

内容

从定期运行备份脚本，到计算机引导后立即启动特定进程，Linux 系统上有大量的任务需要调度。systemd 计时器为调度和管理作业及服务提供了灵活的机制。

原因

本文旨在提供 systemd 计时器的完整概述，涵盖创建、维护、测试、查错以及从 cron 迁移等方面的信息。

工作量

创建示例 systemd 计时器需要 10 分钟。最多花费 30 分钟即可完全了解 systemd 计时器的工作原理。

要求

- 基本了解 systemd。
- root 或 sudo 特权。要以普通用户的身份使用 systemd 计时器，请先参见第 7 节 “以普通用户身份使用计时器”。

出版日期：2025 年 12 月 11 日

目录

- 1 systemd 计时器概念 3

2	创建计时器	3
3	管理计时器	6
4	计时器类型	9
5	测试日历项	12
6	当计时器失败时接收电子邮件通知	13
7	以普通用户身份使用计时器	15
8	从 cron 迁移到 systemd 计时器	17
9	查错和常见问题	18
10	更多信息	22
11	法律声明	23
A	GNU Free Documentation License	23

1 systemd 计时器概念

systemd 计时器单元提供了用于在 Linux 上调度作业的机制。这些作业的执行时间可以基于时间和日期或基于事件。

systemd 计时器单元通过 .timer 文件扩展名标识。每个计时器文件都需要一个由它控制的相应服务文件。也就是说，计时器文件将激活并管理相应的服务文件。systemd 计时器支持以下功能：

- 使用计时器单元安排的作业可以依赖其他 systemd 服务。计时器单元被视为常规 systemd 服务，因此可以使用 systemctl 进行管理。
- 计时器可以是实时的（基于日历事件触发），也可以是单调性的（自特定起始时刻经过指定的时间后触发）。
- 时间单元将记录到系统日志中，这样用户便能更轻松地对时间单元进行监视和查错。
- 计时器使用集中式 systemd 管理服务。
- 如果系统在预期执行期间关闭，则一旦系统再次运行，就会执行计时器。

2 创建计时器

以下示例说明如何设置下面这样的计时器：在引导后触发 helloworld.sh 外壳脚本，并相对于其激活时间每隔 24 小时重复执行一次。此外，计时器会在星期一至星期五上午 10 点运行。

2.1 Hello World 示例

1. 创建包含以下内容的可执行文件 /usr/local/bin/helloworld.sh:

```
#!/bin/sh
# This is bash program to display Hello World
```

```
echo " Hello World "
```

这是一个可执行的 `.sh` 文件，其中包含您希望 `systemd` 运行和管理的命令。

2. 创建包含以下内容的 `/etc/systemd/system/helloworld.service` 文件：

```
[Unit]
Description="Hello World script"

[Service]
ExecStart=/usr/local/bin/helloworld.sh
```

这是一个 `systemd` 服务文件，告知 `systemd` 要运行哪个应用程序。

3. 创建包含以下内容的 `/etc/systemd/system/helloworld.timer` 文件：

```
[Unit]
Description="Run helloworld.service 5min after boot and every 24 hours
relative to activation time"

[Timer]
OnBootSec=5min
OnUnitActiveSec=24h
OnCalendar=Mon..Fri *-*-* 10:00
Unit=helloworld.service

[Install]
WantedBy=multi-user.target
```

这是计时器文件，用于控制相应服务文件的激活。

4. 校验您先前创建的文件是否不含错误：

```
> systemd-analyze verify /etc/systemd/system/helloworld.*
```

如果命令未返回任何输出，则表示文件成功通过了校验。

5. 启动计时器：

```
> sudo systemctl start helloworld.timer
```

仅针对当前会话激活计时器。

6. 启用计时器以确保在引导时将其激活：

```
> sudo systemctl enable helloworld.timer
```

2.2 示例解释

例 1：服务文件

```
[Unit]
Description="Hello World script" ❶

[Service]
ExecStart=/usr/local/bin/helloworld.sh ❷
```

- ❶ 解释服务文件用途的简短说明。
- ❷ 要执行的应用程序。

[Unit] 和 [Service] 部分是服务文件能够正常运行所需的最基础部分。`systemd` 服务文件通常还包含 [Install] 部分，该部分用于指定服务加载时对应的一个或多个目标。计时器的服务文件中不需要此部分，因为此信息已在计时器文件中提供。有关高级配置，请参见[如何使用 systemctl 管理 systemd 目标的文章 \(https://documentation.suse.com/smart/systems-management/html/reference-managing-systemd-targets-systemctl/reference-systemctl-managing-targets.html\)](https://documentation.suse.com/smart/systems-management/html/reference-managing-systemd-targets-systemctl/reference-systemctl-managing-targets.html)。

例 2：计时器文件

```
[Unit]
Description="Run helloworld.service 5min after boot and every 24 hours relative
to activation time" ❶

[Timer]
OnBootSec=5min ❷
OnUnitActiveSec=24h ❸
OnCalendar=Mon..Fri *-*-* 10:00 ❹
Unit=helloworld.service ❺
```

```
[Install]
```

```
WantedBy=multi-user.target ⑥
```

- ① 解释计时器文件用途的简短说明。
- ② 指定一个用于在系统引导 5 分钟后触发服务的计时器。有关详细信息，请参见[单调计时器](#)。
- ③ 指定一个用于在激活服务 24 小时后触发服务（即每天触发一次）的计时器。有关详细信息，请参见[实时计时器](#)。
- ④ 指定一个在固定时间点（在本示例中为星期一至星期五上午 10 点）触发服务的计时器。有关详细信息，请参见[实时计时器](#)。
- ⑤ 要执行的服务文件。
- ⑥ 要在其中激活计时器的 `systemd` 目标。有关 `systemd` 目标的详细信息，请参见[如何使用 systemctl 管理 systemd 目标的文章 \(https://documentation.suse.com/smart/systems-management/html/reference-managing-systemd-targets-systemctl/reference-systemctl-managing-targets.html\)](https://documentation.suse.com/smart/systems-management/html/reference-managing-systemd-targets-systemctl/reference-systemctl-managing-targets.html)。

3 管理计时器

可以使用 `systemctl` 命令管理计时器。

启动和停止计时器

```
> sudo systemctl start TIMER.timer  
> sudo systemctl restart TIMER.timer  
> sudo systemctl stop TIMER.timer
```

启用和禁用计时器

```
> sudo systemctl enable TIMER.timer  
> sudo systemctl disable TIMER.timer
```

显示计时器文件内容

```
> sudo systemctl cat TIMER.timer
```

检查特定的计时器

```
> sudo systemctl status TIMER.timer
```

例 3：计时器状态

```
> sudo systemctl status helloworld.timer
● helloworld.timer - "Run helloworld.service 5min after boot and every 24
  hours
  relative to activation time" ❶
Loaded: loaded (/etc/systemd/system/helloworld.timer; disabled; vendor
  preset: disabled) ❷
Active: active (waiting) since Tue 2022-10-26 18:35:41 CEST; 6s ago ❸
Trigger: Wed 2022-10-27 18:35:41 CEST; 23h left ❹
Triggers: ● helloworld.service ❺ ❻
Oct 26 18:35:41 neo systemd[1]: Started "Run helloworld.service 5min after
  boot and every 24 hours relative to activation time". ❼
```

- ❶ 计时器的文件名和说明。
- ❷ 列出计时器是否已成功分析并保留在内存中（已加载），显示计时器文件的完整路径，以及计时器在系统引导时会启动（已启用）还是不会启动（已禁用）。第一个值显示当前系统配置，第二个值显示供应商预设的值。
- ❸ 指示计时器是处于活动状态（正在等待触发事件）还是非活动状态。如果处于活动状态，它还会显示自上次激活以来经过的时间（在本示例中为 6 秒）。
- ❹ 下次触发计时器的日期和时间。
- ❺ 计时器触发的服务文件的名称。
- ❻ 指向文档（例如手册页）的可选行。如果不可用，则显示空行（如本示例中所示）。
- ❼ 计时器创建的最新日记项。

要列出系统上所有可用的计时器，请使用 `systemctl list-timers`。下列选项可用：

列出所有活动计时器：

```
> sudo systemctl list-timers
```

列出所有计时器，包括非活动的计时器：

```
> sudo systemctl list-timers --all
```

列出与模式匹配的所有计时器：

```
> sudo systemctl list-timers PATTERN> sudo systemctl list-timers --all PATTERN
```

`PATTERN` 必须是一个名称或外壳通配表达式。可以使用运算符 `*`、`?` 和 `[]`。有关通配模式的详细信息，请参见 [man 7 glob](#)。

列出与特定状态匹配的计时器：

```
> sudo systemctl list-timers --state=STATE
```

`STATE` 接受以下值：[active](#)、[failed](#)、[load](#)、[sub](#)。有关详细信息，请参见 [man systemctl](#)。

例 4：列出计时器

运行任何 `systemctl list-timers` 都会生成如下所示的表。此示例列出了与模式 `snapper*` 匹配的所有活动计时器：

```
> sudo systemctl list-timers snapper*
NEXT ①                LEFT ②                LAST ③
PASSED ④    UNIT ⑤                ACTIVATES ⑥
-----
Tue 2022-10-26 19:00:00 CEST 39min left Tue 2022-10-26 18:00:29 CEST 19min
ago snapper-timeline.timer snapper-timeline.service
Wed 2022-10-27 08:33:04 CEST 14h left Tue 2022-10-26 08:33:04 CEST 9h ago
snapper-cleanup.timer snapper-cleanup.service
```

- ① 下次运行计时器的时间点。
- ② 距离下次运行计时器的剩余时间。
- ③ 上次运行计时器的时间点。
- ④ 自上次运行计时器以来经过的时间。
- ⑤ 计时器单元的名称。
- ⑥ 计时器激活的服务的名称。

4 计时器类型

`systemd` 支持两种类型的计时器：实时（基于日历）和单调（基于事件）计时器。尽管计时器通常是永久性的，但 `systemd` 还允许设置仅对当前会话有效的瞬态计时器。

实时计时器

实时计时器由日历事件触发。它们是使用选项 `OnCalendar` 定义的。

您可以基于日期和时间指定何时触发事件。使用以下模板：

```
OnCalendar=DayOfWeek ① Year-Month-Day ② Hour:Minute:Second ③
```

- ① 星期日期。可能的值为 `Sun`、`Mon`、`Tue`、`Wed`、`Thu`、`Fri`、`Sat`。留空会忽略星期日期。
- ② 日期。用两位数指定月和日，用四位数指定年。可以用通配符 `*` 替换每个值，以匹配每个出现的值。
- ③ 时间。用两位数指定每个值。可以用通配符 `*` 替换每个值，以匹配每个出现的值。

应用于所有值：用两个点定义连续范围 (`Mon..Fri`)。用逗号分隔各个不同值的列表 (`Mon,Wed,Fri`)。

例 5：实时计时器示例

- 每个星期五的下午 6 点：

```
OnCalendar=Fri *- *- * 18:00:00
```

- 每天上午 5 点：

```
OnCalendar=Mon..Sun *- *- * 5:00:00
```

- 星期日和星期二凌晨 1 点和 3 点：

```
OnCalendar=Tue,Sun *- *- * 01,03:00:00
```

- 单个日期：

```
OnCalendar=Mo..Sun 2023-09-23 00:00:01
```

- 要指定不同时间的触发器，可以在单个计时器文件中创建多个 OnCalendar 项：

```
OnCalendar=Mon..Fri *-** 10:00
```

```
OnCalendar=Sat,Sun *-** 22:00
```

有关可用功能和选项的完整列表，请参见 [man 7 systemd.time](#)，其中提供了有关以下主题的其他信息：

- 缩短语法并使用缩写
- 指定重复次数
- 查找一个月中的特定日期（如月末最后一天、当月最后一个周日等）
- 应用时区

单调计时器

单调计时器在发生特定事件（例如系统引导或系统单元激活事件）后经过指定的时间时触发。值按时间单位（分钟、小时、日、月、年等）定义。支持以下单位：[usec](#)、[msec](#)、[seconds](#)、[minutes](#)、[hours](#)、[days](#)、[weeks](#)、[months](#)、[years](#)。可以使用多个选项来定义单调计时器：

- [OnActiveSec](#)：激活单元后经过的时间

```
OnActiveSec=50minutes
```

- [OnBootSec](#)：系统引导后经过的时间

```
OnBootSec=10hours
```

- [OnStartupSec](#)：启动服务管理器后经过的时间。对于系统服务，此选项大致相当于 [OnActiveSec](#)。请将此选项用于相应服务管理器会在用户登录时启动的用户服务。

```
OnStartupSec=5minutes 20seconds
```

- OnUnitActiveSec: 上次激活相应服务后经过的时间

```
OnUnitActiveSec=10seconds
```

- OnUnitInactiveSec: 上次停用相应服务后经过的时间

```
OnUnitInactiveSec=2hours 15minutes 18 seconds
```

瞬态计时器

瞬态计时器是仅对当前会话有效的临时计时器。借助这些计时器，可以使用现有的服务文件或直接启动程序。可以运行 **systemd-run** 来调用瞬态计时器。

以下示例每隔两小时运行一次 helloworld.service 单元：

```
> sudo systemd-run --on-active="2hours" --unit="helloworld.service"
```

要直接运行某个命令，请使用以下语法。此示例直接调用脚本 /usr/local/bin/helloworld.sh：

```
> sudo systemd-run --on-active="2hours" /usr/local/bin/helloworld.sh
```

如果命令接受参数，请用空格分隔添加的参数：

```
> sudo systemd-run --on-active="2hours" /usr/local/bin/helloworld.sh --  
language=pt_BR
```

瞬态计时器可以是单调的，也可以是实时的。支持以下开关，其工作方式如[单调计时器](#)中所述：

- --on-active
- --on-startup
- --on-unit-active
- --on-unit-inactive
- --on-calendar

有关详细信息，请参见 man 1 systemd-run。

5 测试日历项

`systemd` 提供了用于为实时计时器测试和创建日历计时器项的工具，即 `systemd-analyze calendar`。此工具接受的参数与用于设置实时计时器的 `OnCalendar` 项相同。

您可以串联多个参数（用空格分隔）。如果要测试的字词正确，则输出会显示下次触发计时器的时间（以本地时间和 UTC 表示）。其中还会显示 `Normalized form` 的字符串，建议在计时器文件中使用该字符串。考虑下列示例：

```
> systemd-analyze calendar "Tue,Sun *-*-* 01,03:00:00"
Normalized form: Tue,Sun *-*-* 01,03:00:00
Next elapse: Sun 2021-10-31 01:00:00 CEST
(in UTC): Sat 2021-10-30 23:00:00 UTC
From now: 3 days left

> systemd-analyze calendar "Mon..Fri *-*-* 10:00" "Sat,Sun *-*-* 22:00"
Original form: Mon..Fri *-*-* 10:00
Normalized form: Mon..Fri *-*-* 10:00:00
Next elapse: Thu 2021-10-28 10:00:00 CEST
(in UTC): Thu 2021-10-28 08:00:00 UTC
From now: 19h left

Original form: Sat,Sun *-*-* 22:00
Normalized form: Sat,Sun *-*-* 22:00:00
Next elapse: Sat 2021-10-30 22:00:00 CEST
(in UTC): Sat 2021-10-30 20:00:00 UTC
From now: 3 days left
```

对于重复性计时器，请使用 `-iterations N` 开关列出触发时间，然后测试计时器是否按预期工作。参数 `N` 指定您要测试的迭代次数。以下示例字符串在星期日每隔 8 小时（从 00:00:00 开始）触发一次计时器：

```
> systemd-analyze calendar --iterations 5 "Sun *-*-* 0/08:00:00"
Original form: Sun *-*-* 0/08:00:00
Normalized form: Sun *-*-* 00/8:00:00
Next elapse: Sun 2021-10-31 00:00:00 CEST
```

```
(in UTC): Sat 2021-10-30 22:00:00 UTC
From now: 3 days left
Iter. #2: Sun 2021-10-31 08:00:00 CET
(in UTC): Sun 2021-10-31 07:00:00 UTC
From now: 3 days left
Iter. #3: Sun 2021-10-31 16:00:00 CET
(in UTC): Sun 2021-10-31 15:00:00 UTC
From now: 4 days left
Iter. #4: Sun 2021-11-07 00:00:00 CET
(in UTC): Sat 2021-11-06 23:00:00 UTC
From now: 1 week 3 days left
Iter. #5: Sun 2021-11-07 08:00:00 CET
(in UTC): Sun 2021-11-07 07:00:00 UTC
From now: 1 week 3 days left
```

6 当计时器失败时接收电子邮件通知

`systemd` 未提供与 `cron` 的 `MAILTO` 类似的功能。以下过程介绍了当计时器失败时启用电子邮件通知的解决方法。

该过程包括以下步骤：

1. 创建一个用于发送电子邮件的脚本。
2. 创建运行电子邮件脚本的 `systemd` 服务文件。
3. 测试电子邮件服务文件。
4. 在计时器控制的服务中，通过 `OnFailure` 调用创建的电子邮件服务文件。

以下示例将使用软件包 `mailx` 中的 `mailx` 命令。这需要安装并正确配置 Postfix 电子邮件服务器。

1. 创建脚本 `/usr/local/bin/send_systemd_email`。
 - a. 该脚本需要两个参数：`$1`（电子邮件地址）和 `$2`（用于接收失败通知的服务文件的名称）。这两个参数均由运行邮件脚本的单元文件提供。

```
#!/bin/sh
systemctl status --full "$2" | mailx -S sendwait\
-s "Service failure for $2" -r root@$HOSTNAME $1
```

b. 确保该脚本可执行：

```
> sudo chmod 755 /usr/local/bin/send_systemd_email
```

2. 创建文件 `/etc/systemd/system/send_email_to_USER@.service`。

```
[Unit]
Description=Send systemd status information by email for %i to USER

[Service]
Type=oneshot
ExecStart=/usr/local/bin/send_systemd_email EMAIL_ADDRESS %i
User=root
Group=systemd-journal
```

将文件中的 `USER` 和 `EMAIL_ADDRESS` 分别替换为要接收电子邮件的用户的登录名和电子邮件地址。`%i` 是失败的服务名称（通过 `%n` 参数传递给电子邮件服务）。

3. 校验服务文件并修复报告的问题：

```
> systemd-analyze verify /etc/systemd/system/send_email_to_USER@.service
```

如果命令未返回任何输出，则表示文件成功通过了校验。

4. 要校验整个过程，请使用 `dbus` 实例启动服务进行测试。（您可以使用当前正在运行的任何其他服务。本示例使用 `dbus`，是因为该服务在所有安装环境中都能确保运行。）

```
> sudo systemctl start send_email_to_USER@dbus.service
```

如果成功，`EMAIL_ADDRESS` 会收到一封电子邮件，其主题为 `Service failure for dbus`，正文包含 `dbus` 状态消息。（这只是一项测试，`dbus` 服务本身并未出现问题。您可以放心删除该电子邮件，无需执行任何操作）。

如果测试电子邮件已成功发送，请将其集成到您的服务文件中。

5. 要向服务添加电子邮件通知，请将 `OnFailure` 选项添加到在发生失败时用于接收通知的服务文件的 `Unit` 部分：

```
[Unit]
Description="Hello World script"
OnFailure ❶=send_email_to_USER ❷@%n ❸.service

[Service]
ExecStart=/usr/local/bin/helloworld.sh
```

- ❶ `OnFailure` 选项接受将某个服务作为参数。
- ❷ 将此服务单元文件名部分替换为登录名。
- ❸ 指定服务的名称（在本示例中为 `helloworld`）。此名称在电子邮件服务文件中以 `%i` 形式提供。

您已成功为 `systemd` 服务设置失败通知。



提示：向多个用户发送电子邮件通知

电子邮件服务文件已将收件人的电子邮件地址硬编码。要向其他用户发送通知电子邮件，请复制电子邮件服务文件，并替换文件名中的用户登录名，以及抄送行中的电子邮件地址。

要同时向多个收件人发送失败通知，请将相应的服务文件添加到该服务文件（使用空格作为分隔符）：

```
OnFailure=send_email_to_tux@%n.service send_email_to_wilber@%n.service
```

7 以普通用户身份使用计时器

普通用户也可以使用 `systemd` 计时器。这些计时器可帮助您自动完成重复性任务，例如备份、处理图像或将数据移到云中。

适用于系统范围计时器的过程和任务同样适用于 `systemd` 计时器。但是，两者存在以下差异：

- 计时器和服务文件必须放在 `~/.config/systemd/user/` 中。
- 必须结合 `--user` 开关运行所有 `systemctl` 和 `journalctl` 命令。`systemd-analyze` 不需要此选项。

作为普通用户，您必须提供单元文件的路径，如以下示例中所示。否则，如果存在同名的系统范围计时器，则会执行或列出该系统范围计时器。

```
> systemctl --user start ~/.config/systemd/user/helloworld.timer
> systemctl --user enable ~/.config/systemd/user/helloworld.timer
> systemctl --user list-timers
> journalctl --user -u helloworld.*
> systemd-analyze verify ~/.config/systemd/user/helloworld.timer
```

! 重要：用户计时器仅在活动会话期间运行

与以普通用户身份启动的其他 `systemd` 服务一样，用户计时器仅在用户登录后才运行。

若要让用户计时器在系统引导时启动，且在用户注销后仍保持运行状态，需要为每个相关用户启用用户驻留模式：

```
sudo loginctl enable-linger USER
```

有关详细信息，请参见 `man 1 loginctl`。

! 重要：不继承环境变量

`systemd` 用户实例不会继承 `~/.profile` 或 `~/.bashrc` 等脚本设置的环境变量。要检查 `systemd` 环境，请运行 `systemctl --user show-environment`。

要导入 `systemd` 环境中缺少的任何变量，请在 `~/.bashrc` 末尾指定以下命令：

```
systemctl --user import-environment VARIABLE1 VARIABLE2
```

8 从 cron 迁移到 systemd 计时器

所有 cron 作业都可以迁移到 `systemd` 计时器。下面提供了说明和示例。

1. 创建执行脚本的服务文件。有关详细信息，请参见例 1 “服务文件”。
2. 创建执行服务文件的计时器文件。有关一般说明，请参见例 2 “计时器文件”。
 - a. 转换日历项。在 cron 和 `systemd` 中，时间的指定方式不同。使用以下模式作为转换模板：

```
Cron:           Minute Hour Day Month DayOfWeek
systemd: OnCalendar=DayOfWeek Year-Month-Day Hour:Minute:Second
```

要测试转换后的日历项，请按照第 5 节 “测试日历项” 中的说明操作。

- b. 转换 cron 别名 (`@NICK`):

```
Cron      : systemd timer
-----  : -----
@reboot   : OnBootSec=1s
@yearly   : OnCalendar=*-01-01 00:00:00
@annually : OnCalendar=*-01-01 00:00:00
@monthly  : OnCalendar=*-*-01 00:00:00
@weekly   : OnCalendar=Sun *-*-* 00:00:00
@daily    : OnCalendar=*-*-* 00:00:00
@hourly   : OnCalendar=*-*-* *:00:00
```

- c. 转换变量赋值。`systemd` 变量赋值必须在 `[Service]` 部分中定义。不能以这种方式转换 `MAILTO` - 具体请参见下一步。

```
cron: VARIABLE=VALUE
systemd: Environment="VARIABLE=VALUE"
```

- d. 按照第 6 节 “当计时器失败时接收电子邮件通知” 中的说明设置电子邮件通知，以替换 cron 的 `MAILTO` 功能。

例 6：从 CRON 迁移到 systemd 计时器

下面是在引导后经过 5 分钟并在每个星期一至星期五 10 点调用脚本 `helloworld.sh` 的 crontab 项：

```
@reboot sleep 300 && /usr/local/bin/helloworld.sh
0 10 * * * 1-5 /usr/local/bin/helloworld.sh
```

调用脚本的 `systemd` 服务文件 (`helloworld.service`) 如下所示：

```
[Unit]
Description="Hello World script"
[Service]
ExecStart=/usr/local/bin/helloworld.sh
```

计时器文件 (`helloworld.timer`) 如下所示：

```
[Unit]
Description="Run helloworld.service 5min after boot and at 10am every Mon-Fri"
[Timer]
OnBootSec=5min
OnCalendar=Mon..Fri *-*-* 10:00
Unit=helloworld.service
[Install]
WantedBy=multi-user.target
```

9 查错和常见问题

了解如何对失败的 `systemd` 计时器进行调试和查错。查找有关 `systemd` 计时器的常见问题解答。

9.1 避免错误

为了避免 `systemd` 计时器出现错误，请确保遵循以下最佳实践：

- 校验您在服务中使用 `ExecStart` 指定的可执行文件是否正确运行。
- 运行 `systemd-analyze verify FILE` 来检查服务和计时器文件的语法。
- 运行 `systemd-analyze calendar CALENDER_ENTRY` 来检查日历项的执行时间。

9.2 事件未触发

当您激活包含非严重错误的计时器时，`systemd` 将静默忽略这些错误。例如：

例 7：包含非致命错误的 `systemd` 计时器文件中断

```
[Timer]
OnBootSec=5min
OnClendar=Mon..Fri 10:00
Unit=helloworld.service
```

第 3 行包含语法错误（应该是 `OnCalendar`，而不是 `OnClendar`）。由于 `[Timer]` 部分包含另一个计时器项 (`OnBoot`)，因此该错误并不严重，将被静默忽略。因此，星期一至星期五的触发器不会执行。检测错误的唯一方法是使用命令 `systemd-analyze verify`：

```
# systemd-analyze verify /etc/systemd/system/helloworld.timer
/etc/systemd/system/helloworld.timer:7: Unknown key name 'OnClendar' in
section 'Timer', ignoring.
```

9.3 在系统日记中检查错误

与每个 `systemd` 服务一样，计时器触发的事件和操作将记录到系统日志中。如果触发器未按预期运行，请使用 `journalctl` 检查日志消息。要过滤日志以显示相关信息，请使用 `-u` 开关指定 `systemd` 计时器和服务文件。使用此选项可显示计时器和相应服务文件的日志项：

```
sudo journalctl -u helloworld.timer -u helloworld.service
```

或使用更短的选项格式（如果适用）：

```
sudo journalctl -u helloworld.*
```

`journalctl` 是支持许多选项和过滤器的工具。请参见 [man 1 journalctl](#) 获取深入信息。

以下选项对于计时器查错非常有用：

- `-b`：仅显示当前引导对应的项。
- `-S today`：仅显示当日的项。
- `-x`：显示帮助文本以及日志项。
- `-f`：从最新的项开始，随着新项的不断添加持续列显日志。非常适合用于检查以较短间隔执行的触发器。按 `Ctrl - C` 键退出。

9.4 systemd 计时器：弥补错过的轮次

如果 `systemd` 计时器处于非活动状态或系统在预期执行期间关闭，可以选择性地在计时器再次激活后立即触发错过的事件。要启用此功能，请将配置选项 `Persistent=true` 添加到 `[Timer]` 部分：

```
[Timer]
OnCalendar=Mon..Fri 10:00
Persistent=true
Unit=helloworld.service
```

9.5 如何从 cron 迁移到 systemd 计时器？

所有 `cron` 作业都可以迁移到 `systemd` 计时器。下面是有关迁移 `cron` 作业的一般说明：

1. 创建执行脚本的服务文件。有关详细信息，请参见例 1 “服务文件”。
2. 创建执行服务文件的计时器文件。有关一般说明，请参见例 2 “计时器文件”。
 - a. 转换日历项。在 `cron` 和 `systemd` 中，时间的指定方式不同。使用以下模式作为转换模板：

```
Cron:           Minute Hour Day Month DayOfWeek
systemd: OnCalendar=DayOfWeek Year-Month-Day Hour:Minute:Second
```

要测试转换后的日历项，请按照第 5 节“测试日历项”中的说明操作。

b. 转换 cron 别名 (@NICK):

```
Cron      : systemd timer
-----  : -----
@reboot   : OnBootSec=1s
@yearly   : OnCalendar=*-01-01 00:00:00
@annually : OnCalendar=*-01-01 00:00:00
@monthly  : OnCalendar=*-*-01 00:00:00
@weekly   : OnCalendar=Sun *-*-* 00:00:00
@daily    : OnCalendar=*-*-* 00:00:00
@hourly   : OnCalendar=*-*-* *:00:00
```

c. 转换变量赋值。 `systemd` 变量赋值必须在 `[Service]` 部分中定义。不能以这种方式转换 `MAILTO` - 具体请参见下一步。

```
cron: VARIABLE=VALUE
systemd: Environment="VARIABLE=VALUE"
```

d. 按照第 6 节“当计时器失败时接收电子邮件通知”中的说明设置电子邮件通知，以替换 cron 的 `MAILTO` 功能。

例 8：从 CRON 迁移到 systemd 计时器

下面是在引导后经过 5 分钟并在每个星期一至星期五 10 点调用脚本 `helloworld.sh` 的 `crontab` 项：

```
@reboot sleep 300 && /usr/local/bin/helloworld.sh
0 10 * * * 1-5 /usr/local/bin/helloworld.sh
```

调用脚本的 `systemd` 服务文件 (`helloworld.service`) 如下所示：

```
[Unit]
Description="Hello World script"
[Service]
```

```
ExecStart=/usr/local/bin/helloworld.sh
```

计时器文件 (`helloworld.timer`) 如下所示:

```
[Unit]
Description="Run helloworld.service 5min after boot and at 10am every Mon-
Fri"
[Timer]
OnBootSec=5min
OnCalendar=Mon..Fri *-*- * 10:00
Unit=helloworld.service
[Install]
WantedBy=multi-user.target
```

10 更多信息

- 有关 `systemd` 计时器的完整参考，包括高级配置选项（例如延迟或者处理时钟或时区更改），请参见 `man 5 systemd.timer`。
- `systemd` 的基本概念 (<https://documentation.suse.com/smart/systems-management/html/concept-systemd/concept-systemd.html>) ↗
- 启动和停止 `systemd` 服务 (<https://documentation.suse.com/smart/systems-management/html/reference-systemctl-start-stop-services/reference-systemctl-start-stop-services.html>) ↗
- 启用和禁用 `systemd` 服务 (<https://documentation.suse.com/smart/systems-management/html/reference-systemctl-enable-disable-services/reference-systemctl-enable-disable-services.html>) ↗
- 调试失败的 `systemd` 服务 (<https://documentation.suse.com/smart/systems-management/html/task-debug-failed-systemd-services/index.html>) ↗
- 向 `systemd` 服务发送终止信号 (<https://documentation.suse.com/smart/systems-management/html/task-send-termination-signals-systemd/task-send-termination-signals-systemd.html>) ↗

11 法律声明

版权所有© 2006–2025 SUSE LLC 和撰稿人。保留所有权利。

根据 GNU 自由文档许可证 (GNU Free Documentation License) 版本 1.2 或 (根据您的选择) 版本 1.3 中的条款, 在此授予您复制、分发和/或修改本文档的权限; 本版权声明和许可证附带不可变部分。许可版本 1.2 的副本包含在 “GNU Free Documentation License” 部分。

有关 SUSE 商标, 请参见 <https://www.suse.com/company/legal/>。所有其他第三方商标分别为相应所有者的财产。商标符号 (®、™ 等) 代表 SUSE 及其关联公司的商标。星号 (*) 代表第三方商标。

本指南力求涵盖所有细节, 但这不能确保本指南准确无误。SUSE LLC 及其关联公司、作者和译者对于可能出现的错误或由此造成的后果皆不承担责任。

A GNU Free Documentation License

Copyright (C) 2000, 2001, 2002 Free Software Foundation, Inc. 51 Franklin St, Fifth Floor, Boston, MA 02110-1301 USA. Everyone is permitted to copy and distribute verbatim copies of this license document, but changing it is not allowed.

0. PREAMBLE

The purpose of this License is to make a manual, textbook, or other functional and useful document "free" in the sense of freedom: to assure everyone the effective freedom to copy and redistribute it, with or without modifying it, either commercially or non-commercially. Secondly, this License preserves for the author and publisher a way to get credit for their work, while not being considered responsible for modifications made by others.

This License is a kind of "copyleft", which means that derivative works of the document must themselves be free in the same sense. It complements the GNU General Public License, which is a copyleft license designed for free software.

We have designed this License to use it for manuals for free software, because free software needs free documentation: a free program should come with manuals providing the same freedoms that the software does. But this License is not limited to software

manuals; it can be used for any textual work, regardless of subject matter or whether it is published as a printed book. We recommend this License principally for works whose purpose is instruction or reference.

1. APPLICABILITY AND DEFINITIONS

This License applies to any manual or other work, in any medium, that contains a notice placed by the copyright holder saying it can be distributed under the terms of this License. Such a notice grants a world-wide, royalty-free license, unlimited in duration, to use that work under the conditions stated herein. The "Document", below, refers to any such manual or work. Any member of the public is a licensee, and is addressed as "you". You accept the license if you copy, modify or distribute the work in a way requiring permission under copyright law.

A "Modified Version" of the Document means any work containing the Document or a portion of it, either copied verbatim, or with modifications and/or translated into another language.

A "Secondary Section" is a named appendix or a front-matter section of the Document that deals exclusively with the relationship of the publishers or authors of the Document to the Document's overall subject (or to related matters) and contains nothing that could fall directly within that overall subject. (Thus, if the Document is in part a textbook of mathematics, a Secondary Section may not explain any mathematics.) The relationship could be a matter of historical connection with the subject or with related matters, or of legal, commercial, philosophical, ethical or political position regarding them.

The "Invariant Sections" are certain Secondary Sections whose titles are designated, as being those of Invariant Sections, in the notice that says that the Document is released under this License. If a section does not fit the above definition of Secondary then it is not allowed to be designated as Invariant. The Document may contain zero Invariant Sections. If the Document does not identify any Invariant Sections then there are none.

The "Cover Texts" are certain short passages of text that are listed, as Front-Cover Texts or Back-Cover Texts, in the notice that says that the Document is released under this License. A Front-Cover Text may be at most 5 words, and a Back-Cover Text may be at most 25 words.

A "Transparent" copy of the Document means a machine-readable copy, represented in a format whose specification is available to the general public, that is suitable for revising the document straightforwardly with generic text editors or (for images composed of pixels) generic paint programs or (for drawings) some widely available drawing editor, and that is suitable for input to text formatters or for automatic translation to a variety of formats suitable for input to text formatters. A copy made in an otherwise Transparent file format whose markup, or absence of markup, has been arranged to thwart or discourage subsequent modification by readers is not Transparent. An image format is not Transparent if used for any substantial amount of text. A copy that is not "Transparent" is called "Opaque".

Examples of suitable formats for Transparent copies include plain ASCII without markup, Texinfo input format, LaTeX input format, SGML or XML using a publicly available DTD, and standard-conforming simple HTML, PostScript or PDF designed for human modification. Examples of transparent image formats include PNG, XCF and JPG. Opaque formats include proprietary formats that can be read and edited only by proprietary word processors, SGML or XML for which the DTD and/or processing tools are not generally available, and the machine-generated HTML, PostScript or PDF produced by some word processors for output purposes only.

The "Title Page" means, for a printed book, the title page itself, plus such following pages as are needed to hold, legibly, the material this License requires to appear in the title page. For works in formats which do not have any title page as such, "Title Page" means the text near the most prominent appearance of the work's title, preceding the beginning of the body of the text.

A section "Entitled XYZ" means a named subunit of the Document whose title either is precisely XYZ or contains XYZ in parentheses following text that translates XYZ in another language. (Here XYZ stands for a specific section name mentioned below, such as "Acknowledgements", "Dedications", "Endorsements", or "History".) To "Preserve the Title" of such a section when you modify the Document means that it remains a section "Entitled XYZ" according to this definition.

The Document may include Warranty Disclaimers next to the notice which states that this License applies to the Document. These Warranty Disclaimers are considered to be included by reference in this License, but only as regards disclaiming warranties: any other implication that these Warranty Disclaimers may have is void and has no effect on the meaning of this License.

2. VERBATIM COPYING

You may copy and distribute the Document in any medium, either commercially or non-commercially, provided that this License, the copyright notices, and the license notice saying this License applies to the Document are reproduced in all copies, and that you add no other conditions whatsoever to those of this License. You may not use technical measures to obstruct or control the reading or further copying of the copies you make or distribute. However, you may accept compensation in exchange for copies. If you distribute a large enough number of copies you must also follow the conditions in section 3.

You may also lend copies, under the same conditions stated above, and you may publicly display copies.

3. COPYING IN QUANTITY

If you publish printed copies (or copies in media that commonly have printed covers) of the Document, numbering more than 100, and the Document's license notice requires Cover Texts, you must enclose the copies in covers that carry, clearly and legibly, all these Cover Texts: Front-Cover Texts on the front cover, and Back-Cover Texts on the back cover. Both covers must also clearly and legibly identify you as the publisher of these copies. The front cover must present the full title with all words of the title equally prominent and visible. You may add other material on the covers in addition. Copying with changes limited to the covers, as long as they preserve the title of the Document and satisfy these conditions, can be treated as verbatim copying in other respects.

If the required texts for either cover are too voluminous to fit legibly, you should put the first ones listed (as many as fit reasonably) on the actual cover, and continue the rest onto adjacent pages.

If you publish or distribute Opaque copies of the Document numbering more than 100, you must either include a machine-readable Transparent copy along with each Opaque copy, or state in or with each Opaque copy a computer-network location from which the general network-using public has access to download using public-standard network protocols a complete Transparent copy of the Document, free of added material. If you use the latter option, you must take reasonably prudent steps, when you begin distribution of Opaque copies in quantity, to ensure that this Transparent copy will remain thus accessible at the stated location until at least one year after the last time you distribute an Opaque copy (directly or through your agents or retailers) of that edition to the public. It is requested, but not required, that you contact the authors of the Document well before redistributing any large number of copies, to give them a chance to provide you with an updated version of the Document.

4. MODIFICATIONS

You may copy and distribute a Modified Version of the Document under the conditions of sections 2 and 3 above, provided that you release the Modified Version under precisely this License, with the Modified Version filling the role of the Document, thus licensing distribution and modification of the Modified Version to whoever possesses a copy of it. In addition, you must do these things in the Modified Version:

- A.** Use in the Title Page (and on the covers, if any) a title distinct from that of the Document, and from those of previous versions (which should, if there were any, be listed in the History section of the Document). You may use the same title as a previous version if the original publisher of that version gives permission.
- B.** List on the Title Page, as authors, one or more persons or entities responsible for authorship of the modifications in the Modified Version, together with at least five of the principal authors of the Document (all of its principal authors, if it has fewer than five), unless they release you from this requirement.

- C.** State on the Title page the name of the publisher of the Modified Version, as the publisher.
- D.** Preserve all the copyright notices of the Document.
- E.** Add an appropriate copyright notice for your modifications adjacent to the other copyright notices.
- F.** Include, immediately after the copyright notices, a license notice giving the public permission to use the Modified Version under the terms of this License, in the form shown in the Addendum below.
- G.** Preserve in that license notice the full lists of Invariant Sections and required Cover Texts given in the Document's license notice.
- H.** Include an unaltered copy of this License.
- I.** Preserve the section Entitled "History", Preserve its Title, and add to it an item stating at least the title, year, new authors, and publisher of the Modified Version as given on the Title Page. If there is no section Entitled "History" in the Document, create one stating the title, year, authors, and publisher of the Document as given on its Title Page, then add an item describing the Modified Version as stated in the previous sentence.
- J.** Preserve the network location, if any, given in the Document for public access to a Transparent copy of the Document, and likewise the network locations given in the Document for previous versions it was based on. These may be placed in the "History" section. You may omit a network location for a work that was published at least four years before the Document itself, or if the original publisher of the version it refers to gives permission.
- K.** For any section Entitled "Acknowledgements" or "Dedications", Preserve the Title of the section, and preserve in the section all the substance and tone of each of the contributor acknowledgements and/or dedications given therein.
- L.** Preserve all the Invariant Sections of the Document, unaltered in their text and in their titles. Section numbers or the equivalent are not considered part of the section titles.

- M.** Delete any section Entitled "Endorsements". Such a section may not be included in the Modified Version.
- N.** Do not retitle any existing section to be Entitled "Endorsements" or to conflict in title with any Invariant Section.
- O.** Preserve any Warranty Disclaimers.

If the Modified Version includes new front-matter sections or appendices that qualify as Secondary Sections and contain no material copied from the Document, you may at your option designate some or all of these sections as invariant. To do this, add their titles to the list of Invariant Sections in the Modified Version's license notice. These titles must be distinct from any other section titles.

You may add a section Entitled "Endorsements", provided it contains nothing but endorsements of your Modified Version by various parties--for example, statements of peer review or that the text has been approved by an organization as the authoritative definition of a standard.

You may add a passage of up to five words as a Front-Cover Text, and a passage of up to 25 words as a Back-Cover Text, to the end of the list of Cover Texts in the Modified Version. Only one passage of Front-Cover Text and one of Back-Cover Text may be added by (or through arrangements made by) any one entity. If the Document already includes a cover text for the same cover, previously added by you or by arrangement made by the same entity you are acting on behalf of, you may not add another; but you may replace the old one, on explicit permission from the previous publisher that added the old one.

The author(s) and publisher(s) of the Document do not by this License give permission to use their names for publicity for or to assert or imply endorsement of any Modified Version.

5. COMBINING DOCUMENTS

You may combine the Document with other documents released under this License, under the terms defined in section 4 above for modified versions, provided that you include in the combination all of the Invariant Sections of all of the original documents, unmodified, and list them all as Invariant Sections of your combined work in its license notice, and that you preserve all their Warranty Disclaimers.

The combined work need only contain one copy of this License, and multiple identical Invariant Sections may be replaced with a single copy. If there are multiple Invariant Sections with the same name but different contents, make the title of each such section unique by adding at the end of it, in parentheses, the name of the original author or publisher of that section if known, or else a unique number. Make the same adjustment to the section titles in the list of Invariant Sections in the license notice of the combined work.

In the combination, you must combine any sections Entitled "History" in the various original documents, forming one section Entitled "History"; likewise combine any sections Entitled "Acknowledgements", and any sections Entitled "Dedications". You must delete all sections Entitled "Endorsements".

6. COLLECTIONS OF DOCUMENTS

You may make a collection consisting of the Document and other documents released under this License, and replace the individual copies of this License in the various documents with a single copy that is included in the collection, provided that you follow the rules of this License for verbatim copying of each of the documents in all other respects.

You may extract a single document from such a collection, and distribute it individually under this License, provided you insert a copy of this License into the extracted document, and follow this License in all other respects regarding verbatim copying of that document.

7. AGGREGATION WITH INDEPENDENT WORKS

A compilation of the Document or its derivatives with other separate and independent documents or works, in or on a volume of a storage or distribution medium, is called an "aggregate" if the copyright resulting from the compilation is not used to limit the legal rights of the compilation's users beyond what the individual works permit. When the Document is included in an aggregate, this License does not apply to the other works in the aggregate which are not themselves derivative works of the Document.

If the Cover Text requirement of section 3 is applicable to these copies of the Document, then if the Document is less than one half of the entire aggregate, the Document's Cover Texts may be placed on covers that bracket the Document within the aggregate, or the electronic equivalent of covers if the Document is in electronic form. Otherwise they must appear on printed covers that bracket the whole aggregate.

8. TRANSLATION

Translation is considered a kind of modification, so you may distribute translations of the Document under the terms of section 4. Replacing Invariant Sections with translations requires special permission from their copyright holders, but you may include translations of some or all Invariant Sections in addition to the original versions of these Invariant Sections. You may include a translation of this License, and all the license notices in the Document, and any Warranty Disclaimers, provided that you also include the original English version of this License and the original versions of those notices and disclaimers. In case of a disagreement between the translation and the original version of this License or a notice or disclaimer, the original version will prevail.

If a section in the Document is Entitled "Acknowledgements", "Dedications", or "History", the requirement (section 4) to Preserve its Title (section 1) will typically require changing the actual title.

9. TERMINATION

You may not copy, modify, sublicense, or distribute the Document except as expressly provided for under this License. Any other attempt to copy, modify, sublicense or distribute the Document is void, and will automatically terminate your rights under this License. However, parties who have received copies, or rights, from you under this License will not have their licenses terminated so long as such parties remain in full compliance.

10. FUTURE REVISIONS OF THIS LICENSE

The Free Software Foundation may publish new, revised versions of the GNU Free Documentation License from time to time. Such new versions will be similar in spirit to the present version, but may differ in detail to address new problems or concerns. See <https://www.gnu.org/copyleft/>.

Each version of the License is given a distinguishing version number. If the Document specifies that a particular numbered version of this License "or any later version" applies to it, you have the option of following the terms and conditions either of that specified version or of any later version that has been published (not as a draft) by the Free Software Foundation. If the Document does not specify a version number of this License, you may choose any version ever published (not as a draft) by the Free Software Foundation.

ADDENDUM: How to use this License for your documents

```
Copyright (c) YEAR YOUR NAME.  
Permission is granted to copy, distribute and/or modify this document  
under the terms of the GNU Free Documentation License, Version 1.2  
or any later version published by the Free Software Foundation;  
with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts.  
A copy of the license is included in the section entitled "GNU  
Free Documentation License".
```

If you have Invariant Sections, Front-Cover Texts and Back-Cover Texts, replace the "with...Texts." line with this:

```
with the Invariant Sections being LIST THEIR TITLES, with the
```

Front-Cover Texts being LIST, and with the Back-Cover Texts being LIST.

If you have Invariant Sections without Cover Texts, or some other combination of the three, merge those two alternatives to suit the situation.

If your document contains nontrivial examples of program code, we recommend releasing these examples in parallel under your choice of free software license, such as the GNU General Public License, to permit their use in free software.