

Troubleshooting SELinux

WHAT?

A system with SELinux in the enforcing mode may cause access denials that may prevent applications from running correctly. You can use **audit2allow** or setroubleshoot to analyze denial messages in a user-friendly way.

WHY?

This article provides instructions on how to solve access denials caused by SELinux without decreasing the security of your system.

EFFORT

It takes approximately 30 minutes to read the article.

GOAL

You will be able to use one of the further described tools to debug SELinux denials.

REQUIREMENTS

- A running system with enabled SELinux.

Publication Date: 03 Nov 2025

Contents

- 1 The `/var/log/audit/audit.log` file 3
- 2 Analyzing `/var/log/audit/audit.log` with **audit2allow** 5

- 3 Analyzing AVC messages using **setroubleshoot** 6
- 4 Legal Notice 12
- A GNU Free Documentation License 12

1 The `/var/log/audit/audit.log` file

By default, if SELinux is the reason something is not working, a log message to this effect is sent to the `/var/log/audit/audit.log` file.



Note: Empty `/var/log/audit/audit.log`

If you see an empty `/var/log/audit/audit.log`, it usually means that the `auditd` service is not running. In this case, proceed as follows:

1. Start the `auditd` service:

```
> sudo systemctl start auditd
```

2. Enable the service in the targets of your system, using

```
> sudo systemctl enable auditd
```

The `/var/log/audit/audit.log` file stores messages of access denials, service events and so on. In *Example 1: "Example lines from `/etc/audit/audit.log`"*, you can see a partial example of the contents of `/var/log/audit/audit.log`.

EXAMPLE 1: EXAMPLE LINES FROM `/etc/audit/audit.log`

```
type=DAEMON_START msg=audit(1348173810.874:6248): auditd start, ver=1.7.7 format=raw
kernel=3.0.13-0.27-default audit=0 pid=4235 subj=system_u:system_r:auditd_t res=success
type=AVC msg=audit(1348173901.081:292): avc: denied { write } for
pid=3426 comm="smartd" name="smartmontools" dev=sda6 ino=581743
scontext=system_u:system_r:fsdaemon_t tcontext=system_u:object_r:var_lib_t tclass=dir
type=AVC msg=audit(1348173901.081:293): avc: denied { remove_name } for pid=3426
comm="smartd" name="smartd.WDC_WD2500BEKT_75PVMT0-WD_WXC1A21E0454.ata.state~" dev=sda6
ino=582390 scontext=system_u:system_r:fsdaemon_t tcontext=system_u:object_r:var_lib_t
tclass=dir
type=AVC msg=audit(1348173901.081:294): avc: denied { unlink } for pid=3426
comm="smartd" name="smartd.WDC_WD2500BEKT_75PVMT0-WD_WXC1A21E0454.ata.state~" dev=sda6
ino=582390 scontext=system_u:system_r:fsdaemon_t tcontext=system_u:object_r:var_lib_t
tclass=file
type=AVC msg=audit(1348173901.081:295): avc: denied { rename } for pid=3426
comm="smartd" name="smartd.WDC_WD2500BEKT_75PVMT0-WD_WXC1A21E0454.ata.state" dev=sda6
ino=582373 scontext=system_u:system_r:fsdaemon_t tcontext=system_u:object_r:var_lib_t
tclass=file
```

```
type=AVC msg=audit(1348173901.081:296): avc: denied { add_name } for pid=3426
comm="smartd" name="smartd.WDC_WD2500BEKT_75PVMT0-WD_WXC1A21E0454.ata.state~"
scontext=system_u:system_r:fsdaemon_t tcontext=system_u:object_r:var_lib_t tclass=dir
type=AVC msg=audit(1348173901.081:297): avc: denied { create } for pid=3426
comm="smartd" name="smartd.WDC_WD2500BEKT_75PVMT0-WD_WXC1A21E0454.ata.state"
scontext=system_u:system_r:fsdaemon_t tcontext=system_u:object_r:var_lib_t tclass=file
type=AVC msg=audit(1348173901.081:298): avc: denied { write open } for pid=3426
comm="smartd" name="smartd.WDC_WD2500BEKT_75PVMT0-WD_WXC1A21E0454.ata.state" dev=sda6
ino=582390 scontext=system_u:system_r:fsdaemon_t tcontext=system_u:object_r:var_lib_t
tclass=file
type=AVC msg=audit(1348173901.081:299): avc: denied { getattr } for pid=3426
comm="smartd" path="/var/lib/smartmontools/smartd.WDC_WD2500BEKT_75PVMT0-
WD_WXC1A21E0454.ata.state" dev=sda6 ino=582390 scontext=system_u:system_r:fsdaemon_t
tcontext=system_u:object_r:var_lib_t tclass=file
type=AVC msg=audit(1348173901.309:300): avc: denied { append } for pid=1316
```

A single message looks as follows:

```
type=AVC msg=audit(1348173901.081:299): avc: denied { getattr } for pid=3426
comm="smartd" path="/var/lib/smartmontools/smartd.WDC_WD2500BEKT_75PVMT0-
WD_WXC1A21E0454.ata.state" dev=sda6 ino=582390 scontext=system_u:system_r:fsdaemon_t
tcontext=system_u:object_r:var_lib_t tclass=file
```

Every line of the message can be broken down into sections. For example, the sections in the last line are:

type=AVC:

Every SELinux-related audit log line starts with the type identification, for example, type=AVC. Note that a message with the type=SYSCALL that follows one with a different type and has the same value of msg may provide further information regarding the event.

msg=audit(1348173901.309:300):

This is the time stamp, which is written in epoch time, the number of seconds that have passed since Jan 1, 1970. You can use **date -d** on the part up to the dot in the epoch time notation to find out when the event happened:

```
> date -d @1348173901
Thu Sep 20 16:45:01 EDT 2012
```

avc: denied { append }:

The specific action that was denied. In this case, the system has denied the appending of data to a file. While browsing through the audit log file, you can see other system actions, such as write open, getattr and more.

for pid=1316:

the process ID of the command or process that initiated the action

comm="rsyslogd":

the specific command that was associated with that PID

name="smartmontools":

the name of the subject of the action

dev=sda6 ino=582296:

the block device and inode number of the file that was involved

scontext=system_u:system_r:syslogd_t:

the source context, which is the context of the initiator of the action

tclass=file:

a class identification of the subject

2 Analyzing `/var/log/audit/audit.log` with `audit2allow`

Instead of interpreting the events in `/var/log/audit/audit.log` yourself, you can use the `audit2allow` command.

The command helps analyze the cryptic log messages in `/var/log/audit/audit.log`. An `audit2allow` troubleshooting session always consists of three different commands. First, you would use `audit2allow -w -a` to present the audit information in a more readable way. The `audit2allow -w -a` by default works on the `audit.log` file. If you want to analyze a specific message in the `audit.log` file, copy it to a temporary file and analyze the file with:

```
> sudo audit2allow -w -i FILENAME
```

EXAMPLE 2: ANALYZING AUDIT MESSAGES

```
> sudo audit2allow -w -i testfile
type=AVC msg=audit(1348173901.309:300): avc: denied { append } for pid=1316
comm="rsyslogd" name="acpid" dev=sda6 ino=582296
scontext=system_u:system_r:syslogd_t tcontext=system_u:object_r:apmd_log_t tclass=file
```

This was caused by:

A missing type enforcement (TE) allow rule.

To generate a loadable module to allow this access, run

```
> sudo audit2allow
```

To find out which specific rule has denied access, you can use `audit2allow -a` to show the enforcing rules from all events that were logged into the `audit.log` file, or `audit2allow -i FILENAME` to show it for messages that you have stored in a specific file:

EXAMPLE 3: VIEWING WHICH LINES DENY ACCESS

```
> sudo audit2allow -i testfile
#===== syslogd_t =====
allow syslogd_t apmd_log_t:file append;
```

To create an SELinux module with the name `mymodule` that you can load to allow the access that was previously denied, run

```
> sudo audit2allow -a -R -M mymodule
```

If you want to do this for all events that have been logged into the `audit.log` file, use the `-a -M` command arguments. To do it only for specific messages that are in a specific file, use `-i -M` as in the example below:

EXAMPLE 4: CREATING A POLICY MODULE ALLOWING AN ACTION PREVIOUSLY DENIED

```
> sudo audit2allow -i testfile -M example
***** IMPORTANT *****
To make this policy package active, run:

semodule -i example.pp
```

As indicated by the `audit2allow` command, you can now run this module by using the `semodule -i` command, followed by the name of the module that `audit2allow` has created for you (`example.pp` in the above example).

3 Analyzing AVC messages using `setroubleshoot`

To analyze AVC denial messages in a user-friendly way, you can use the `setroubleshoot` tool.

3.1 Overview of `setroubleshoot`

3.1.1 What is `setroubleshoot`?

`setroubleshoot` is a tool that collects SELinux audit events from the kernel and analyses these events. If such an event occurs, `setroubleshoot` informs the administrator.

3.1.2 `setroubleshoot` components

The SELinux troubleshooting process involves the following components, all of which are installed on SUSE Linux Micro by default.

- `setroubleshoot-server` provides the following tools:
 - `setroubleshootd`—the main daemon handling incoming requests and plug-in definitions. The daemon is activated on demand and does not require running via the `systemd` service. It can be managed only by a privileged user and a dedicated `setroubleshoot` user.
 - a database of alerts in the file `/var/lib/setroubleshoot/setroubleshoot_database.xml`
 - `sealert`—a command-line user interface to analyze the `/var/log/audit.log`
 - `sedispatch`—an audit dispatcher that scans SELinux AVC messages and transforms them into a Dbus message, then passed to the daemon.
- `setroubleshoot-plugins`—the plug-ins are used for AVC message analysis and provide suggestions on how to fix problems.

3.1.3 How does `setroubleshoot` work?

`setroubleshoot` comprises a daemon and analysis plug-ins. When a plug-in detects a problem, it is reported to the daemon, which then checks whether this is a known problem. If not, the new problem is added to the database along with a suggested solution.

3.1.4 Benefits of **setroubleshoot**

setroubleshoot provides the following functionalities to help you solve problems on your SELinux secured systems:

- Sending alerts to the administrator when there is an AVC denial.
- Automatic analysis of AVC denials.
- Suggesting possible fixes, such as adjusting system configuration or installing updates and so on.
- Browsing of previous alerts.

3.2 Configuring **setroubleshoot**

Even though the configuration of **setroubleshoot** does not require adjustment, you may face particular use cases when you need to change the defaults. The following sections provide the usual use cases.

The configuration file for **setroubleshoot** is `/etc/setroubleshoot`. Usually, you do not have to modify the configuration besides setting the e-mail notifications. However, if you need to change the configuration, you can either edit the file, or you can use the **setroubleshootd** command to configure a particular item. The command syntax is the following:

```
# setroubleshootd -c  
SECTION.OPTION=VALUE
```

For example, to set the `from_address` option, run the command as follows:

```
# setroubleshootd -c  
email.from_address="example@mail.com"
```

3.2.1 Configuring **setroubleshoot** logging level

The default logging level (the value of `sealert_log` and `setroubleshootd_log`) is set to `warning`. However, you can set the value to one of the following:

critical

Only serious errors that prevent the system from functioning are logged.

error

Serious errors that may influence the system are reported.

warning

An indication that something unexpected happened, or that a problem might occur in the near future. However, the system works as expected.

info

A confirmation that the system is running correctly is logged.

debug

Detailed information for debugging purposes is logged.

3.2.2 Configuring `setroubleshoot` to send e-mail notifications

`setroubleshoot` can send you e-mail notifications if there is an AVC denial in the system.

To get these notifications, proceed as follows:

1. Open the `/etc/setroubleshoot/setroubleshoot.conf`.
2. In the file, adjust the following configuration items to suit your needs:

`smtp_host`

If the SMTP server does not run on the local host, fill in the server address.

`smtp_port`

The default is 25. Usually, this value does not require any adjustment.

`from_address`

Add the sender address.

`subject`

Configure a generic subject of all messages.

`recipients_filepath`

Specify the location of the notification recipients list.

`use_sendmail`

Set to `true` if you use SendMail.

3. Create the mail recipients file on the path defined by the `recipients_filepath` option (`/var/lib/setroubleshoot/email_alerts-recipients` by default).

Each e-mail address must be on a separate line. Comments are denoted with the # symbol.

3.2.3 Configuring the `setroubleshoot` database

You can change the amount of records in the `setroubleshootd` database, its location or the file name prefix.

`database_dir`

Specify an absolute path to the directory where the database XML file should reside.

`filename`

Configure a custom prefix of the database file name. The file name then looks as follows: `FILENAME_PREFIX_database.xml`.

`max_alerts`

Defines the maximum number of records in the database. Specify `0` for an unlimited number of records.

`max_alert_age`

Alerts older than the set limit are deleted from the database. You can use the units: *year, month, day, hour, minute and second* even in the plural form and you can use more than one unit, for example, 3 weeks 2 days, which equals to 23 days. If left empty, there is no limit.

3.2.4 Configure `setroubleshoot` to collect information from remote servers

You can configure `setroubleshoot` to gather SELinux audit data from remote servers. To do so, configure the address list.

`[listen_for_client] address_list`

On the server side.

`[client_connect_to] address_list`

On the client side.

Addresses on the list are in this format:

```
[{FAMILY}]ADDRESS[:PORT_NUMBER]
```

Where *{FAMILY}* is *{inet}* or *{unix}%{path}s*. If the address family is *inet*, you can optionally specify a port number, otherwise the port number is set to the default specified by the `default_port` configuration option. The default value *{unix}%{path}s hostname* means listening on the local Unix domain socket.

3.3 Running the `/var/log/audit/audit.log` analysis

To let the `setroubleshoot` tool analyze the audit log file, run the command:

```
> sudo sealert -a /var/log/audit/audit.log
```

In the following example output, there are two port values assigned to the SSHD service:

```
100% done
found 1 alerts in /var/log/audit/audit.log
-----

SELinux is preventing sshd from name_bind access on the tcp_socket port 2222.

**** Plugin bind_ports (92.2 confidence) suggests ****

If you want to allow sshd to bind to network port 2222
Then you need to modify the port type.
Do
# semanage port -a -t PORT_TYPE -p tcp 2222 ①
   where PORT_TYPE is one of the following: ssh_port_t, vnc_port_t, xserver_port_t.

**** Plugin catchall_boolean (7.83 confidence) suggests ****

If you want to allow nis to enabled
Then you must tell SELinux about this by enabling the 'nis_enabled' boolean.

Do
setsebool -P nis_enabled 1

**** Plugin catchall (1.41 confidence) suggests ****

If you believe that sshd should be allowed name_bind access on the port 2222 tcp_socket
by default.
Then you should report this as a bug.
You can generate a local policy module to allow this access.
Do
allow this access for now by executing:
# ausearch -c 'sshd' --raw | audit2allow -M my-sshd
```

```
# semodule -X 300 -i my-sshd.pp

Additional Information:
...

First Seen                2024-02-07 14:26:27 UTC
Last Seen                 2024-02-08 03:30:12 UTC
Local ID                 b5cbdd75-3f8d-425d-af75-f6cbf1540ffd

Raw Audit Messages
type=AVC msg=audit(1707363012.797:25): avc: denied { name_bind } for
pid=841 comm="sshd" src=2222 scontext=system_u:system_r:sshd_t:s0-s0:c0.c1023
tcontext=system_u:object_r:unreserved_port_t:s0 tclass=tcp_socket permissive=0

Hash: sshd,sshd_t,unreserved_port_t,tcp_socket,name_bind
```

- 1 The `bind_ports` plug-in provides the most suitable solution for the problem here.

4 Legal Notice

Copyright© 2006–2025 SUSE LLC and contributors. All rights reserved.

Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.2 or (at your option) version 1.3; with the Invariant Section being this copyright notice and license. A copy of the license version 1.2 is included in the section entitled “GNU Free Documentation License”.

For SUSE trademarks, see <https://www.suse.com/company/legal/>. All other third-party trademarks are the property of their respective owners. Trademark symbols (®, ™ etc.) denote trademarks of SUSE and its affiliates. Asterisks (*) denote third-party trademarks.

All information found in this book has been compiled with utmost attention to detail. However, this does not guarantee complete accuracy. Neither SUSE LLC, its affiliates, the authors, nor the translators shall be held liable for possible errors or the consequences thereof.

A GNU Free Documentation License

Copyright (C) 2000, 2001, 2002 Free Software Foundation, Inc. 51 Franklin St, Fifth Floor, Boston, MA 02110-1301 USA. Everyone is permitted to copy and distribute verbatim copies of this license document, but changing it is not allowed.

0. PREAMBLE

The purpose of this License is to make a manual, textbook, or other functional and useful document "free" in the sense of freedom: to assure everyone the effective freedom to copy and redistribute it, with or without modifying it, either commercially or non-commercially. Secondly, this License preserves for the author and publisher a way to get credit for their work, while not being considered responsible for modifications made by others.

This License is a kind of "copyleft", which means that derivative works of the document must themselves be free in the same sense. It complements the GNU General Public License, which is a copyleft license designed for free software.

We have designed this License to use it for manuals for free software, because free software needs free documentation: a free program should come with manuals providing the same freedoms that the software does. But this License is not limited to software manuals; it can be used for any textual work, regardless of subject matter or whether it is published as a printed book. We recommend this License principally for works whose purpose is instruction or reference.

1. APPLICABILITY AND DEFINITIONS

This License applies to any manual or other work, in any medium, that contains a notice placed by the copyright holder saying it can be distributed under the terms of this License. Such a notice grants a world-wide, royalty-free license, unlimited in duration, to use that work under the conditions stated herein. The "Document", below, refers to any such manual or work. Any member of the public is a licensee, and is addressed as "you". You accept the license if you copy, modify or distribute the work in a way requiring permission under copyright law.

A "Modified Version" of the Document means any work containing the Document or a portion of it, either copied verbatim, or with modifications and/or translated into another language.

A "Secondary Section" is a named appendix or a front-matter section of the Document that deals exclusively with the relationship of the publishers or authors of the Document to the Document's overall subject (or to related matters) and contains nothing that could fall directly within that overall subject. (Thus, if the Document is in part a textbook of mathematics, a Secondary Section may not explain any mathematics.) The relationship could be a matter of historical connection with the subject or with related matters, or of legal, commercial, philosophical, ethical or political position regarding them.

The "Invariant Sections" are certain Secondary Sections whose titles are designated, as being those of Invariant Sections, in the notice that says that the Document is released under this License. If a section does not fit the above definition of Secondary then it is not allowed to be designated as Invariant. The Document may contain zero Invariant Sections. If the Document does not identify any Invariant Sections then there are none.

The "Cover Texts" are certain short passages of text that are listed, as Front-Cover Texts or Back-Cover Texts, in the notice that says that the Document is released under this License. A Front-Cover Text may be at most 5 words, and a Back-Cover Text may be at most 25 words.

A "Transparent" copy of the Document means a machine-readable copy, represented in a format whose specification is available to the general public, that is suitable for revising the document straightforwardly with generic text editors or (for images composed of pixels) generic paint programs or (for drawings) some widely available drawing editor, and that is suitable for input to text formatters or for automatic translation to a variety of formats suitable for input to text formatters. A copy made in an otherwise Transparent file format whose markup, or absence of markup, has been arranged to thwart or discourage subsequent modification by readers is not Transparent. An image format is not Transparent if used for any substantial amount of text. A copy that is not "Transparent" is called "Opaque".

Examples of suitable formats for Transparent copies include plain ASCII without markup, Texinfo input format, LaTeX input format, SGML or XML using a publicly available DTD, and standard-conforming simple HTML, PostScript or PDF designed for human modification. Examples of transparent image formats include PNG, XCF and JPG. Opaque formats include proprietary formats that can be read and edited only by proprietary word processors, SGML or XML for which the DTD and/or processing tools are not generally available, and the machine-generated HTML, PostScript or PDF produced by some word processors for output purposes only.

The "Title Page" means, for a printed book, the title page itself, plus such following pages as are needed to hold, legibly, the material this License requires to appear in the title page. For works in formats which do not have any title page as such, "Title Page" means the text near the most prominent appearance of the work's title, preceding the beginning of the body of the text.

A section "Entitled XYZ" means a named subunit of the Document whose title either is precisely XYZ or contains XYZ in parentheses following text that translates XYZ in another language. (Here XYZ stands for a specific section name mentioned below, such as "Acknowledgements", "Dedications", "Endorsements", or "History".) To "Preserve the Title" of such a section when you modify the Document means that it remains a section "Entitled XYZ" according to this definition.

The Document may include Warranty Disclaimers next to the notice which states that this License applies to the Document. These Warranty Disclaimers are considered to be included by reference in this License, but only as regards disclaiming warranties: any other implication that these Warranty Disclaimers may have is void and has no effect on the meaning of this License.

2. VERBATIM COPYING

You may copy and distribute the Document in any medium, either commercially or non-commercially, provided that this License, the copyright notices, and the license notice saying this License applies to the Document are reproduced in all copies, and that you add no other conditions whatsoever to those of this License. You may not use technical measures to obstruct or control the reading or further copying of the copies you make or distribute. However, you may accept compensation in exchange for copies. If you distribute a large enough number of copies you must also follow the conditions in section 3.

You may also lend copies, under the same conditions stated above, and you may publicly display copies.

3. COPYING IN QUANTITY

If you publish printed copies (or copies in media that commonly have printed covers) of the Document, numbering more than 100, and the Document's license notice requires Cover Texts, you must enclose the copies in covers that carry, clearly and legibly, all these Cover Texts: Front-Cover Texts on the front cover, and Back-Cover Texts on the back cover. Both covers must also clearly and legibly identify you as the publisher of these copies. The front cover must present the full title with all words of the title equally prominent and visible. You may add other material on the covers in addition. Copying with changes limited to the covers, as long as they preserve the title of the Document and satisfy these conditions, can be treated as verbatim copying in other respects.

If the required texts for either cover are too voluminous to fit legibly, you should put the first ones listed (as many as fit reasonably) on the actual cover, and continue the rest onto adjacent pages.

If you publish or distribute Opaque copies of the Document numbering more than 100, you must either include a machine-readable Transparent copy along with each Opaque copy, or state in or with each Opaque copy a computer-network location from which the general network-using public has access to download using public-standard network protocols a complete Transparent

copy of the Document, free of added material. If you use the latter option, you must take reasonably prudent steps, when you begin distribution of Opaque copies in quantity, to ensure that this Transparent copy will remain thus accessible at the stated location until at least one year after the last time you distribute an Opaque copy (directly or through your agents or retailers) of that edition to the public.

It is requested, but not required, that you contact the authors of the Document well before redistributing any large number of copies, to give them a chance to provide you with an updated version of the Document.

4. MODIFICATIONS

You may copy and distribute a Modified Version of the Document under the conditions of sections 2 and 3 above, provided that you release the Modified Version under precisely this License, with the Modified Version filling the role of the Document, thus licensing distribution and modification of the Modified Version to whoever possesses a copy of it. In addition, you must do these things in the Modified Version:

- A. Use in the Title Page (and on the covers, if any) a title distinct from that of the Document, and from those of previous versions (which should, if there were any, be listed in the History section of the Document). You may use the same title as a previous version if the original publisher of that version gives permission.
- B. List on the Title Page, as authors, one or more persons or entities responsible for authorship of the modifications in the Modified Version, together with at least five of the principal authors of the Document (all of its principal authors, if it has fewer than five), unless they release you from this requirement.
- C. State on the Title page the name of the publisher of the Modified Version, as the publisher.
- D. Preserve all the copyright notices of the Document.
- E. Add an appropriate copyright notice for your modifications adjacent to the other copyright notices.
- F. Include, immediately after the copyright notices, a license notice giving the public permission to use the Modified Version under the terms of this License, in the form shown in the Addendum below.
- G. Preserve in that license notice the full lists of Invariant Sections and required Cover Texts given in the Document's license notice.

- H. Include an unaltered copy of this License.
- I. Preserve the section Entitled "History", Preserve its Title, and add to it an item stating at least the title, year, new authors, and publisher of the Modified Version as given on the Title Page. If there is no section Entitled "History" in the Document, create one stating the title, year, authors, and publisher of the Document as given on its Title Page, then add an item describing the Modified Version as stated in the previous sentence.
- J. Preserve the network location, if any, given in the Document for public access to a Transparent copy of the Document, and likewise the network locations given in the Document for previous versions it was based on. These may be placed in the "History" section. You may omit a network location for a work that was published at least four years before the Document itself, or if the original publisher of the version it refers to gives permission.
- K. For any section Entitled "Acknowledgements" or "Dedications", Preserve the Title of the section, and preserve in the section all the substance and tone of each of the contributor acknowledgements and/or dedications given therein.
- L. Preserve all the Invariant Sections of the Document, unaltered in their text and in their titles. Section numbers or the equivalent are not considered part of the section titles.
- M. Delete any section Entitled "Endorsements". Such a section may not be included in the Modified Version.
- N. Do not retitle any existing section to be Entitled "Endorsements" or to conflict in title with any Invariant Section.
- O. Preserve any Warranty Disclaimers.

If the Modified Version includes new front-matter sections or appendices that qualify as Secondary Sections and contain no material copied from the Document, you may at your option designate some or all of these sections as invariant. To do this, add their titles to the list of Invariant Sections in the Modified Version's license notice. These titles must be distinct from any other section titles.

You may add a section Entitled "Endorsements", provided it contains nothing but endorsements of your Modified Version by various parties--for example, statements of peer review or that the text has been approved by an organization as the authoritative definition of a standard.

You may add a passage of up to five words as a Front-Cover Text, and a passage of up to 25 words as a Back-Cover Text, to the end of the list of Cover Texts in the Modified Version. Only one passage of Front-Cover Text and one of Back-Cover Text may be added by (or through

arrangements made by) any one entity. If the Document already includes a cover text for the same cover, previously added by you or by arrangement made by the same entity you are acting on behalf of, you may not add another; but you may replace the old one, on explicit permission from the previous publisher that added the old one.

The author(s) and publisher(s) of the Document do not by this License give permission to use their names for publicity for or to assert or imply endorsement of any Modified Version.

5. COMBINING DOCUMENTS

You may combine the Document with other documents released under this License, under the terms defined in section 4 above for modified versions, provided that you include in the combination all of the Invariant Sections of all of the original documents, unmodified, and list them all as Invariant Sections of your combined work in its license notice, and that you preserve all their Warranty Disclaimers.

The combined work need only contain one copy of this License, and multiple identical Invariant Sections may be replaced with a single copy. If there are multiple Invariant Sections with the same name but different contents, make the title of each such section unique by adding at the end of it, in parentheses, the name of the original author or publisher of that section if known, or else a unique number. Make the same adjustment to the section titles in the list of Invariant Sections in the license notice of the combined work.

In the combination, you must combine any sections Entitled "History" in the various original documents, forming one section Entitled "History"; likewise combine any sections Entitled "Acknowledgements", and any sections Entitled "Dedications". You must delete all sections Entitled "Endorsements".

6. COLLECTIONS OF DOCUMENTS

You may make a collection consisting of the Document and other documents released under this License, and replace the individual copies of this License in the various documents with a single copy that is included in the collection, provided that you follow the rules of this License for verbatim copying of each of the documents in all other respects.

You may extract a single document from such a collection, and distribute it individually under this License, provided you insert a copy of this License into the extracted document, and follow this License in all other respects regarding verbatim copying of that document.

7. AGGREGATION WITH INDEPENDENT WORKS

A compilation of the Document or its derivatives with other separate and independent documents or works, in or on a volume of a storage or distribution medium, is called an "aggregate" if the copyright resulting from the compilation is not used to limit the legal rights of the compilation's users beyond what the individual works permit. When the Document is included in an aggregate, this License does not apply to the other works in the aggregate which are not themselves derivative works of the Document.

If the Cover Text requirement of section 3 is applicable to these copies of the Document, then if the Document is less than one half of the entire aggregate, the Document's Cover Texts may be placed on covers that bracket the Document within the aggregate, or the electronic equivalent of covers if the Document is in electronic form. Otherwise they must appear on printed covers that bracket the whole aggregate.

8. TRANSLATION

Translation is considered a kind of modification, so you may distribute translations of the Document under the terms of section 4. Replacing Invariant Sections with translations requires special permission from their copyright holders, but you may include translations of some or all Invariant Sections in addition to the original versions of these Invariant Sections. You may include a translation of this License, and all the license notices in the Document, and any Warranty Disclaimers, provided that you also include the original English version of this License and the original versions of those notices and disclaimers. In case of a disagreement between the translation and the original version of this License or a notice or disclaimer, the original version will prevail.

If a section in the Document is Entitled "Acknowledgements", "Dedications", or "History", the requirement (section 4) to Preserve its Title (section 1) will typically require changing the actual title.

9. TERMINATION

You may not copy, modify, sublicense, or distribute the Document except as expressly provided for under this License. Any other attempt to copy, modify, sublicense or distribute the Document is void, and will automatically terminate your rights under this License. However, parties who have received copies, or rights, from you under this License will not have their licenses terminated so long as such parties remain in full compliance.

10. FUTURE REVISIONS OF THIS LICENSE

The Free Software Foundation may publish new, revised versions of the GNU Free Documentation License from time to time. Such new versions will be similar in spirit to the present version, but may differ in detail to address new problems or concerns. See <https://www.gnu.org/copyleft/>.

Each version of the License is given a distinguishing version number. If the Document specifies that a particular numbered version of this License "or any later version" applies to it, you have the option of following the terms and conditions either of that specified version or of any later version that has been published (not as a draft) by the Free Software Foundation. If the Document does not specify a version number of this License, you may choose any version ever published (not as a draft) by the Free Software Foundation.

ADDENDUM: How to use this License for your documents

```
Copyright (c) YEAR YOUR NAME.  
Permission is granted to copy, distribute and/or modify this document  
under the terms of the GNU Free Documentation License, Version 1.2  
or any later version published by the Free Software Foundation;  
with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts.  
A copy of the license is included in the section entitled "GNU  
Free Documentation License".
```

If you have Invariant Sections, Front-Cover Texts and Back-Cover Texts, replace the "with...Texts." line with this:

```
with the Invariant Sections being LIST THEIR TITLES, with the  
Front-Cover Texts being LIST, and with the Back-Cover Texts being LIST.
```

If you have Invariant Sections without Cover Texts, or some other combination of the three, merge those two alternatives to suit the situation.

If your document contains nontrivial examples of program code, we recommend releasing these examples in parallel under your choice of free software license, such as the GNU General Public License, to permit their use in free software.