

Analyzing Performance Metrics Using the Performance Co-Pilot Analysis Toolkit

WHAT?

For performance monitoring purposes, SUSE Linux Enterprise Micro provides a container image that enables you to run the Performance Co-Pilot (PCP) analysis toolkit in a container.

WHY?

You want to monitor performance on your system, and this article provides information on how to configure and use the toolkit.

EFFORT

It takes approximately 40 minutes of reading time.

GOAL

You will be able to start the PCP container with a configuration that suits your needs.

REQUIREMENTS

- A running instance of SLE Micro.

Publication Date: 12 Dec 2024

Contents

1	Performance Co-Pilot analysis toolkit	3
2	Running the PCP container	3
3	Configuring PCP services	6
4	Managing PCP metrics	10
5	Legal Notice	13
A	GNU Free Documentation License	14

1 Performance Co-Pilot analysis toolkit

The toolkit comprises tools for gathering and processing performance information collected either in real time or from PCP archive logs.

The performance data is collected by *performance metrics domain agents* and passed to the `pmcd` daemon. The daemon coordinates the gathering and exporting of performance statistics in response to requests from the PCP monitoring tools. `pmlogger` is then used to log the metrics. For details, refer to the [PCP documentation \(https://pcp.readthedocs.io/en/latest/UAG/IntroductionToPcp.html#\)](https://pcp.readthedocs.io/en/latest/UAG/IntroductionToPcp.html#).

1.1 Getting the PCP container image

The PCP container image is based on the *BCI-Init* container that utilizes `systemd` used to manage the PCP services.

You can pull the container image using Podman or from the Cockpit Web management console. To pull the image by using Podman, run the following command:

```
# podman pull registry.suse.com/suse/pcp:latest
```

To get the container image using Cockpit, go to *Podman containers*, click *Get new image*, and search for *pcp*. Then select the image from the registry.suse.com for SLE 15 SP4 and download it.

2 Running the PCP container

The following command shows minimal options that you need to use to run a PCP container:

```
# podman run -d \
--systemd always \
-p HOST_IP:HOST_PORT:CONTAINER_PORT \
-v HOST_DIR:/var/log/pcp/pmlogger \
PCP_CONTAINER_IMAGE
```

where the options have the following meaning:

`-d`

The container runs in a detached mode without `tty`.

--systemd always

Runs the container in the systemd mode. All services needed to run in the PCP container are started automatically by systemd in the container.

--privileged

The container runs with extended privileges. Use this option if your system has SELinux enabled, otherwise the collected metrics are incomplete.

-v HOST_DIR:/var/log/pcp/pmlogger

Creates a bind mount so that pmlogger archives are written to the HOST_DIR on the host. By default, pmlogger stores the collected metrics in /var/log/pcp/pmlogger.

PCP_CONTAINER_IMAGE

Is the downloaded PCP container image.

Other useful options of the podman run command follow:

OTHER OPTIONS

-p HOST_IP:HOST_PORT:CONTAINER_PORT

Publishes ports of the container by mapping a container port onto a host port. If you do not specify HOST_IP, the ports are mapped on the local host. If you omit the HOST_PORT value, a random port number is used. By default, the pmcd daemon listens on and exposes the PMAPI to receive metrics on the port 44321, so we recommend mapping this port on the same port number on the host. The pmproxy daemon listens on and exposes the REST PMWEBAPI to access metrics on the 44322 port by default, so it is recommended to map this port on the same host port number.

--net host

The container uses the host's network. Use this option to collect metrics from the host's network interfaces.

-e

The option enables you to set the following environment variables:

PCP_SERVICES

Is a comma-separated list of services to start by systemd in the container.

Default services are: pmcd, pmie, pmlogger, pmproxy.

You can use this variable to run a container with a list of services that is different from the default one, for example, only with pmlogger:

```
# podman run -d \
```

```
--name pmlogger \  
--systemd always \  
-e PCP_SERVICES=pmlogger \  
-v pcp-archives:/var/log/pcp/pmlogger \  
registry.suse.com/suse/pcp:latest
```

HOST_MOUNT

Is a path inside the container to the bind mount of the host's root file system. The default value is not set.

REDIS_SERVERS

Specifies a connection to a Redis server. In a non-clustered setup, provide a comma-separated list of host specs. In a clustered setup, provide any individual cluster host, other hosts in the cluster are discovered automatically. The default value is: `localhost:6379`.

If you need to use a different configuration than the one provided by the environment variables, proceed as described in [Section 3, “Configuring PCP services”](#).

2.1 Starting the PCP container automatically on boot

After you run the PCP container, you can configure `systemd` to start the container on boot. To do so, follow the procedure below:

1. Create a unit file for the container by using the `podman generate systemd` command:

```
# podman generate systemd --name CONTAINER_NAME > /etc/systemd/system/  
container-CONTAINER_NAME.service
```

where `CONTAINER_NAME` is the name of the PCP container you used when running the container from the container image.

2. Enable the service in `systemd`:

```
# systemctl enable container-CONTAINER_NAME
```

3 Configuring PCP services

All services that run inside the PCP container have a default configuration that might not suit your needs. If you need a custom configuration that cannot be covered by the environment variables, create configuration files for the PCP services and pass them to the PCP using a bind mount as follows:

```
# podman run -d \  
  --name CONTAINER_NAME \  
  --systemd always \  
  -v $HOST_CONFIG:CONTAINER_CONFIG_PATH:z \  
  -v HOST_LOGS_PATH:/var/log/pcp/pmlogger \  
  registry.suse.com/suse/pcp:latest
```

Where:

CONTAINER_NAME

Is an optional container name.

HOST_CONFIG

Is an absolute path to the config you created on the host machine. You can choose any file name you want.

CONTAINER_CONFIG_PATH

Is an absolute path to a particular configuration file inside the container. Each available configuration file is described in the corresponding sections further.

HOST_LOGS_PATH

Is a directory that should be a bind mount to the container logs.

For example, a container called `pcp`, with the configuration file `pmcd` on the host machine and the `pcp-archives` directory for logs on the host machine, is run by the following command:

```
# podman run -d \  
  --name pcp \  
  --systemd always \  
  -v $(pwd)/pcp-archives:/var/log/pcp/pmlogger \  
  -v $(pwd)/pmcd:/etc/sysconfig/pмcd \  
  registry.suse.com/suse/pcp:latest
```

3.1 Custom **pmcd** daemon configuration

The **pmcd** daemon configuration is stored in the `/etc/sysconfig/pmcd` file. The file stores environment variables that modify the behavior of the **pmcd** daemon.

You can add the following variables to the `/etc/sysconfig/pmcd` file to configure the **pmcd** daemon:

PMCD_LOCAL

Defines whether the remote host can connect to the **pmcd** daemon. If set to `0`, remote connections to the daemon are allowed. If set to `1`, the daemon listens only on the local host. The default value is `0`.

PMCD_MAXPENDING

Defines the maximum count of pending connections to the agent. The default value is `5`.

PMCD_ROOT_AGENT

If the `pmdaroot` is enabled (the value is set to `1`), adding a new PDMA does not trigger restarting of other PMDAs. If `pmdaroot` is not enabled, **pmcd** will require restarting all PMDAs when a new PDMA is added. The default value is `1`.

PMCD_RESTART_AGENTS

If set to `1`, the **pmcd** daemon tries to restart any exited PDMA. Enable this option only if you have enabled `pmdaroot`, as **pmcd** itself does not have privileges to restart PDMA.

PMCD_WAIT_TIMEOUT

Defines the maximum time in seconds **pmcd** can wait to accept a connection. After this time, the connection is reported as failed. The default value is `60`.

PCP_NSS_INIT_MODE

Defines the mode in which **pmcd** initializes the NSS certificate database when secured connections are used. The default value is `readonly`. You can set the mode to `readwrite`, but if the initialization fails, the default value is used as a fallback.

An example follows:

```
PMCD_LOCAL=0
PMCD_MAXPENDING=5
PMCD_ROOT_AGENT=1
PMCD_RESTART_AGENTS=1
PMCD_WAIT_TIMEOUT=70
PCP_NSS_INIT_MODE=readwrite
```

3.2 Custom **pmlogger** configuration

The custom configuration for the **pmlogger** is stored in the following configuration files:

- /etc/sysconfig/pmlogger
- /etc/pcp/pmlogger/control.d/local

3.2.1 The /etc/sysconfig/pmlogger file

You can use the following attributes to configure the **pmlogger**:

PMLOGGER_LOCAL

Defines whether **pmlogger** allows connections from remote hosts. If set to *1*, **pmlogger** allows connections from a local host only.

PMLOGGER_MAXPENDING

Defines the maximum count of pending connections. The default value is 5.

PMLOGGER_INTERVAL

Defines the default sampling interval **pmlogger** uses. The default value is *60 s*. Keep in mind that this value can be overridden by the **pmlogger** command line.

PMLOGGER_CHECK_SKIP_LOGCONF

Setting this option to *yes* disables the regeneration and checking of the **pmlogger** configuration if the configuration **pmlogger** comes from **pmlogconf**. The default behavior is to regenerate configuration files and check for changes every time **pmlogger** is started.

An example follows:

```
PMLOGGER_LOCAL=1
PMLOGGER_MAXPENDING=5
PMLOGGER_INTERVAL=10
PMLOGGER_CHECK_SKIP_LOGCONF=yes
```

3.2.2 The /etc/pcp/pmlogger/control.d/local file

The file /etc/pcp/pmlogger/control.d/local stores specifications of the host, which metrics should be logged, the logging frequency (default is 24 hours), and **pmlogger** options. For example:

```
# === VARIABLE ASSIGNMENTS ===
```



```
#
# DO NOT REMOVE OR EDIT THE FOLLOWING LINE
$version=1.1

# Uncomment one of the lines below to enable/disable compression behaviour
# that is different to the pmlogger_daily default.
# Value is days before compressing archives, 0 is immediate compression,
# "never" or "forever" suppresses compression.
#
#$PCP_COMPRESSAFTER=0
#$PCP_COMPRESSAFTER=3
#$PCP_COMPRESSAFTER=never

# === LOGGER CONTROL SPECIFICATIONS ===
#
#Host          P? S? directory          args

# local primary logger
LOCALHOSTNAME y n PCP_ARCHIVE_DIR/LOCALHOSTNAME -r -T24h10m -c config.default -v
100Mb
```



Note: Defaults point to local host

If you run the **pmlogger** in a container on a different machine than the one that runs the **pmcd** (a client), change the following line to point to the client:

```
# local primary logger
CLIENT_HOSTNAME y n PCP_ARCHIVE_DIR/CLIENT_HOSTNAME -r -T24h10m -c
config.default -v 100Mb
```

For example, for the slemicro_1 host name, the line should look as follows:

```
# local primary logger
slemicro_1 y n PCP_ARCHIVE_DIR/slemicro_1 -r -T24h10m -c config.default -v
100Mb
```

4 Managing PCP metrics

4.1 Listing PCP metrics

From within the container, you can use the command **pminfo** to list metrics. For example, to list all available performance metrics, run:

```
# pminfo
```

You can list a group of related metrics by specifying the metrics prefix:

```
# pminfo METRIC_PREFIX
```

For example, to list all metrics related to kernel, use:

```
# pminfo disk

disk.dev.r_await
disk.dm.await
disk.dm.r_await
disk.md.await
disk.md.r_await
...
```

You can also specify additional strings to narrow down the list of metrics, for example:

```
# pminfo disk.dev

disk.dev.read
disk.dev.write
disk.dev.total
disk.dev.blkread
disk.dev.blkwrite
disk.dev.blktotal
...
```

To get online help text of a particular metric, use the **-t** option followed by the metric, for example:

```
# pminfo -t kernel.cpu.util.user

kernel.cpu.util.user [percentage of user time across all CPUs, including guest CPU time]
```

To display a description text of a particular metric, use the `-T` option followed by the metric, for example:

```
# pminfo -T kernel.cpu.util.user

Help:
percentage of user time across all CPUs, including guest CPU time
```

4.2 Checking local metrics

After you start the PCP container, you can verify that metrics are being recorded properly by running the following command inside the container:

```
# pcp

Performance Co-Pilot configuration on localhost:

platform: Linux localhost 5.3.18-150300.59.68-default #1 SMP Wed May 4 11:29:09 UTC 2022
(ea30951) x86_64
hardware: 1 cpu, 1 disk, 1 node, 1726MB RAM
timezone: UTC
services: pmcd pmproxy
          pmcd: Version 5.2.2-1, 9 agents, 4 clients
          pmda: root pmcd proc pmproxy xfs linux mmv kvm jbd2
pmlogger: primary logger: /var/log/pcp/pmlogger/localhost/20220607.09.24
          pmie: primary engine: /var/log/pcp/pmie/localhost/pmie.log
```

Now check if the logs are written to a proper destination:

```
# ls PATH_TO_PMLLOGGER_LOGS
```

where PATH_TO_PMLLOGGER_LOGS should be /var/log/pcp/pmlogger/localhost/ in this case.

4.3 Recording metrics from remote systems

You can deploy collector containers that collect metrics from different remote systems than the ones where the **pmlogger** containers are running. Each remote collector system needs the **pmcd** daemon and a set of **pmda**. To deploy several collectors with a centralized monitoring system, proceed as follows.

1. On each system you want to collect metrics from (clients), run a container with the **pmcd** daemon:

```
# podman run -d \
  --name pcp-pmcd \
  --privileged \
  --net host \
  --systemd always \
  -e PCP_SERVICES=pmcd \
  -e HOST_MOUNT=/host \
  -v /:/host:ro,rslave \
  registry.suse.com/suse/pcp:latest
```

2. On the monitoring system, create a **pmlogger** configuration file for each client **control.CLIENT** with the following content:

```
$version=1.1

CLIENT_HOSTNAME n n PCP_ARCHIVE_DIR/CLIENT -N -r -T24h10m -c config.default -v 100Mb
```

Keep in mind that the **CLIENT_HOSTNAME** must be resolvable in DNS. You can use IP addresses or fully qualified domain names (FQDN) instead.

3. On the monitoring system, create a directory for each client to store the recorded logs:

```
# mkdir /root/pcp-archives/CLIENT
```

For example, for **slemicro_1**:

```
# mkdir /root/pcp-archives/slemicro_1
```

4. On the monitoring system, run a container with **pmlogger** for each client:

```
# podman run -d \
  --name pcp-pmlogger-CLIENT \
  --systemd always \
  -e PCP_SERVICES=pmlogger \
  -v /root/pcp-archives/CLIENT:/var/log/pcp/pmlogger:z \
  -v $(pwd)/control.CLIENT:/etc/pcp/pmlogger/control.d/local:z \
  registry.suse.com/suse/pcp:latest
```

For example, for a client called **slemicro_1**:

```
# podman run -d \
  --name pcp-pmlogger-slemicro_1 \
```

```
--systemd always \
-e PCP_SERVICES=pmlogger \
-v /root/pcp-archives:/var/log/pcp/pmlogger:z \
-v $(pwd)/control.slemicro_1:/etc/pcp/pmlogger/control.d/local:z \
registry.suse.com/suse/pcp:latest
```



Note

The second bind mount points to the configuration file created in [Step 2](#) and replaces the default **pmlogger** configuration. If you do not create this bind mount, **pmlogger** uses the default `/etc/pcp/pmlogger/control.d/local` file and logging from clients fails as the default configuration points to a local host. For details about the configuration file, refer to [Section 3.2.2, “The `/etc/pcp/pmlogger/control.d/local` file”](#).

5. To check if the log collection is working properly, run:

```
# ls -l pcp-archives/CLIENT/CLIENT
```

For example:


```
# ls -l pcp-archives/slemicro_1/slemicro_1

total 1076
-rw-r--r--. 1 systemd-network systemd-network 876372 Jun  8 11:24 20220608.10.58.0
-rw-r--r--. 1 systemd-network systemd-network    312 Jun  8 11:22
20220608.10.58.index
-rw-r--r--. 1 systemd-network systemd-network 184486 Jun  8 10:58
20220608.10.58.meta
-rw-r--r--. 1 systemd-network systemd-network    246 Jun  8 10:58 Latest
-rw-r--r--. 1 systemd-network systemd-network  24595 Jun  8 10:58 pmlogger.log
```

5 Legal Notice

Copyright© 2006–2024 SUSE LLC and contributors. All rights reserved.

Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.2 or (at your option) version 1.3; with the Invariant Section being this copyright notice and license. A copy of the license version 1.2 is included in the section entitled “GNU Free Documentation License”.

For SUSE trademarks, see <https://www.suse.com/company/legal/> . All other third-party trademarks are the property of their respective owners. Trademark symbols (®, [™] etc.) denote trademarks of SUSE and its affiliates. Asterisks (*) denote third-party trademarks.

All information found in this book has been compiled with utmost attention to detail. However, this does not guarantee complete accuracy. Neither SUSE LLC, its affiliates, the authors, nor the translators shall be held liable for possible errors or the consequences thereof.

A GNU Free Documentation License

Copyright (C) 2000, 2001, 2002 Free Software Foundation, Inc. 51 Franklin St, Fifth Floor, Boston, MA 02110-1301 USA. Everyone is permitted to copy and distribute verbatim copies of this license document, but changing it is not allowed.

0. PREAMBLE

The purpose of this License is to make a manual, textbook, or other functional and useful document "free" in the sense of freedom: to assure everyone the effective freedom to copy and redistribute it, with or without modifying it, either commercially or non-commercially. Secondly, this License preserves for the author and publisher a way to get credit for their work, while not being considered responsible for modifications made by others.

This License is a kind of "copyleft", which means that derivative works of the document must themselves be free in the same sense. It complements the GNU General Public License, which is a copyleft license designed for free software.

We have designed this License to use it for manuals for free software, because free software needs free documentation: a free program should come with manuals providing the same freedoms that the software does. But this License is not limited to software manuals; it can be used for any textual work, regardless of subject matter or whether it is published as a printed book. We recommend this License principally for works whose purpose is instruction or reference.

1. APPLICABILITY AND DEFINITIONS

This License applies to any manual or other work, in any medium, that contains a notice placed by the copyright holder saying it can be distributed under the terms of this License. Such a notice grants a world-wide, royalty-free license, unlimited in duration, to use that work under

the conditions stated herein. The "Document", below, refers to any such manual or work. Any member of the public is a licensee, and is addressed as "you". You accept the license if you copy, modify or distribute the work in a way requiring permission under copyright law.

A "Modified Version" of the Document means any work containing the Document or a portion of it, either copied verbatim, or with modifications and/or translated into another language.

A "Secondary Section" is a named appendix or a front-matter section of the Document that deals exclusively with the relationship of the publishers or authors of the Document to the Document's overall subject (or to related matters) and contains nothing that could fall directly within that overall subject. (Thus, if the Document is in part a textbook of mathematics, a Secondary Section may not explain any mathematics.) The relationship could be a matter of historical connection with the subject or with related matters, or of legal, commercial, philosophical, ethical or political position regarding them.

The "Invariant Sections" are certain Secondary Sections whose titles are designated, as being those of Invariant Sections, in the notice that says that the Document is released under this License. If a section does not fit the above definition of Secondary then it is not allowed to be designated as Invariant. The Document may contain zero Invariant Sections. If the Document does not identify any Invariant Sections then there are none.

The "Cover Texts" are certain short passages of text that are listed, as Front-Cover Texts or Back-Cover Texts, in the notice that says that the Document is released under this License. A Front-Cover Text may be at most 5 words, and a Back-Cover Text may be at most 25 words.

A "Transparent" copy of the Document means a machine-readable copy, represented in a format whose specification is available to the general public, that is suitable for revising the document straightforwardly with generic text editors or (for images composed of pixels) generic paint programs or (for drawings) some widely available drawing editor, and that is suitable for input to text formatters or for automatic translation to a variety of formats suitable for input to text formatters. A copy made in an otherwise Transparent file format whose markup, or absence of markup, has been arranged to thwart or discourage subsequent modification by readers is not Transparent. An image format is not Transparent if used for any substantial amount of text. A copy that is not "Transparent" is called "Opaque".

Examples of suitable formats for Transparent copies include plain ASCII without markup, Texinfo input format, LaTeX input format, SGML or XML using a publicly available DTD, and standard-conforming simple HTML, PostScript or PDF designed for human modification. Examples of transparent image formats include PNG, XCF and JPG. Opaque formats include proprietary

formats that can be read and edited only by proprietary word processors, SGML or XML for which the DTD and/or processing tools are not generally available, and the machine-generated HTML, PostScript or PDF produced by some word processors for output purposes only.

The "Title Page" means, for a printed book, the title page itself, plus such following pages as are needed to hold, legibly, the material this License requires to appear in the title page. For works in formats which do not have any title page as such, "Title Page" means the text near the most prominent appearance of the work's title, preceding the beginning of the body of the text.

A section "Entitled XYZ" means a named subunit of the Document whose title either is precisely XYZ or contains XYZ in parentheses following text that translates XYZ in another language. (Here XYZ stands for a specific section name mentioned below, such as "Acknowledgements", "Dedications", "Endorsements", or "History".) To "Preserve the Title" of such a section when you modify the Document means that it remains a section "Entitled XYZ" according to this definition.

The Document may include Warranty Disclaimers next to the notice which states that this License applies to the Document. These Warranty Disclaimers are considered to be included by reference in this License, but only as regards disclaiming warranties: any other implication that these Warranty Disclaimers may have is void and has no effect on the meaning of this License.

2. VERBATIM COPYING

You may copy and distribute the Document in any medium, either commercially or non-commercially, provided that this License, the copyright notices, and the license notice saying this License applies to the Document are reproduced in all copies, and that you add no other conditions whatsoever to those of this License. You may not use technical measures to obstruct or control the reading or further copying of the copies you make or distribute. However, you may accept compensation in exchange for copies. If you distribute a large enough number of copies you must also follow the conditions in section 3.

You may also lend copies, under the same conditions stated above, and you may publicly display copies.

3. COPYING IN QUANTITY

If you publish printed copies (or copies in media that commonly have printed covers) of the Document, numbering more than 100, and the Document's license notice requires Cover Texts, you must enclose the copies in covers that carry, clearly and legibly, all these Cover Texts: Front-Cover Texts on the front cover, and Back-Cover Texts on the back cover. Both covers must also

clearly and legibly identify you as the publisher of these copies. The front cover must present the full title with all words of the title equally prominent and visible. You may add other material on the covers in addition. Copying with changes limited to the covers, as long as they preserve the title of the Document and satisfy these conditions, can be treated as verbatim copying in other respects.

If the required texts for either cover are too voluminous to fit legibly, you should put the first ones listed (as many as fit reasonably) on the actual cover, and continue the rest onto adjacent pages.

If you publish or distribute Opaque copies of the Document numbering more than 100, you must either include a machine-readable Transparent copy along with each Opaque copy, or state in or with each Opaque copy a computer-network location from which the general network-using public has access to download using public-standard network protocols a complete Transparent copy of the Document, free of added material. If you use the latter option, you must take reasonably prudent steps, when you begin distribution of Opaque copies in quantity, to ensure that this Transparent copy will remain thus accessible at the stated location until at least one year after the last time you distribute an Opaque copy (directly or through your agents or retailers) of that edition to the public.

It is requested, but not required, that you contact the authors of the Document well before redistributing any large number of copies, to give them a chance to provide you with an updated version of the Document.

4. MODIFICATIONS

You may copy and distribute a Modified Version of the Document under the conditions of sections 2 and 3 above, provided that you release the Modified Version under precisely this License, with the Modified Version filling the role of the Document, thus licensing distribution and modification of the Modified Version to whoever possesses a copy of it. In addition, you must do these things in the Modified Version:

- A. Use in the Title Page (and on the covers, if any) a title distinct from that of the Document, and from those of previous versions (which should, if there were any, be listed in the History section of the Document). You may use the same title as a previous version if the original publisher of that version gives permission.
- B. List on the Title Page, as authors, one or more persons or entities responsible for authorship of the modifications in the Modified Version, together with at least five of the principal authors of the Document (all of its principal authors, if it has fewer than five), unless they release you from this requirement.
- C. State on the Title page the name of the publisher of the Modified Version, as the publisher.
- D. Preserve all the copyright notices of the Document.
- E. Add an appropriate copyright notice for your modifications adjacent to the other copyright notices.
- F. Include, immediately after the copyright notices, a license notice giving the public permission to use the Modified Version under the terms of this License, in the form shown in the Addendum below.
- G. Preserve in that license notice the full lists of Invariant Sections and required Cover Texts given in the Document's license notice.
- H. Include an unaltered copy of this License.
- I. Preserve the section Entitled "History", Preserve its Title, and add to it an item stating at least the title, year, new authors, and publisher of the Modified Version as given on the Title Page. If there is no section Entitled "History" in the Document, create one stating the title, year, authors, and publisher of the Document as given on its Title Page, then add an item describing the Modified Version as stated in the previous sentence.

- J. Preserve the network location, if any, given in the Document for public access to a Transparent copy of the Document, and likewise the network locations given in the Document for previous versions it was based on. These may be placed in the "History" section. You may omit a network location for a work that was published at least four years before the Document itself, or if the original publisher of the version it refers to gives permission.
- K. For any section Entitled "Acknowledgements" or "Dedications", Preserve the Title of the section, and preserve in the section all the substance and tone of each of the contributor acknowledgements and/or dedications given therein.
- L. Preserve all the Invariant Sections of the Document, unaltered in their text and in their titles. Section numbers or the equivalent are not considered part of the section titles.
- M. Delete any section Entitled "Endorsements". Such a section may not be included in the Modified Version.
- N. Do not retitle any existing section to be Entitled "Endorsements" or to conflict in title with any Invariant Section.
- O. Preserve any Warranty Disclaimers.

If the Modified Version includes new front-matter sections or appendices that qualify as Secondary Sections and contain no material copied from the Document, you may at your option designate some or all of these sections as invariant. To do this, add their titles to the list of Invariant Sections in the Modified Version's license notice. These titles must be distinct from any other section titles.

You may add a section Entitled "Endorsements", provided it contains nothing but endorsements of your Modified Version by various parties--for example, statements of peer review or that the text has been approved by an organization as the authoritative definition of a standard.

You may add a passage of up to five words as a Front-Cover Text, and a passage of up to 25 words as a Back-Cover Text, to the end of the list of Cover Texts in the Modified Version. Only one passage of Front-Cover Text and one of Back-Cover Text may be added by (or through arrangements made by) any one entity. If the Document already includes a cover text for the same cover, previously added by you or by arrangement made by the same entity you are acting on behalf of, you may not add another; but you may replace the old one, on explicit permission from the previous publisher that added the old one.

The author(s) and publisher(s) of the Document do not by this License give permission to use their names for publicity for or to assert or imply endorsement of any Modified Version.

5. COMBINING DOCUMENTS

You may combine the Document with other documents released under this License, under the terms defined in section 4 above for modified versions, provided that you include in the combination all of the Invariant Sections of all of the original documents, unmodified, and list them all as Invariant Sections of your combined work in its license notice, and that you preserve all their Warranty Disclaimers.

The combined work need only contain one copy of this License, and multiple identical Invariant Sections may be replaced with a single copy. If there are multiple Invariant Sections with the same name but different contents, make the title of each such section unique by adding at the end of it, in parentheses, the name of the original author or publisher of that section if known, or else a unique number. Make the same adjustment to the section titles in the list of Invariant Sections in the license notice of the combined work.

In the combination, you must combine any sections Entitled "History" in the various original documents, forming one section Entitled "History"; likewise combine any sections Entitled "Acknowledgements", and any sections Entitled "Dedications". You must delete all sections Entitled "Endorsements".

6. COLLECTIONS OF DOCUMENTS

You may make a collection consisting of the Document and other documents released under this License, and replace the individual copies of this License in the various documents with a single copy that is included in the collection, provided that you follow the rules of this License for verbatim copying of each of the documents in all other respects.

You may extract a single document from such a collection, and distribute it individually under this License, provided you insert a copy of this License into the extracted document, and follow this License in all other respects regarding verbatim copying of that document.

7. AGGREGATION WITH INDEPENDENT WORKS

A compilation of the Document or its derivatives with other separate and independent documents or works, in or on a volume of a storage or distribution medium, is called an "aggregate" if the copyright resulting from the compilation is not used to limit the legal rights of the compilation's users beyond what the individual works permit. When the Document is included in an aggregate, this License does not apply to the other works in the aggregate which are not themselves derivative works of the Document.

If the Cover Text requirement of section 3 is applicable to these copies of the Document, then if the Document is less than one half of the entire aggregate, the Document's Cover Texts may be placed on covers that bracket the Document within the aggregate, or the electronic equivalent of covers if the Document is in electronic form. Otherwise they must appear on printed covers that bracket the whole aggregate.

8. TRANSLATION


Translation is considered a kind of modification, so you may distribute translations of the Document under the terms of section 4. Replacing Invariant Sections with translations requires special permission from their copyright holders, but you may include translations of some or all Invariant Sections in addition to the original versions of these Invariant Sections. You may include a translation of this License, and all the license notices in the Document, and any Warranty Disclaimers, provided that you also include the original English version of this License and the original versions of those notices and disclaimers. In case of a disagreement between the translation and the original version of this License or a notice or disclaimer, the original version will prevail.

If a section in the Document is Entitled "Acknowledgements", "Dedications", or "History", the requirement (section 4) to Preserve its Title (section 1) will typically require changing the actual title.

9. TERMINATION

You may not copy, modify, sublicense, or distribute the Document except as expressly provided for under this License. Any other attempt to copy, modify, sublicense or distribute the Document is void, and will automatically terminate your rights under this License. However, parties who have received copies, or rights, from you under this License will not have their licenses terminated so long as such parties remain in full compliance.

10. FUTURE REVISIONS OF THIS LICENSE

The Free Software Foundation may publish new, revised versions of the GNU Free Documentation License from time to time. Such new versions will be similar in spirit to the present version, but may differ in detail to address new problems or concerns. See <https://www.gnu.org/copyleft/> .

Each version of the License is given a distinguishing version number. If the Document specifies that a particular numbered version of this License "or any later version" applies to it, you have the option of following the terms and conditions either of that specified version or of any later version that has been published (not as a draft) by the Free Software Foundation. If the Document does not specify a version number of this License, you may choose any version ever published (not as a draft) by the Free Software Foundation.

ADDENDUM: How to use this License for your documents

```
Copyright (c) YEAR YOUR NAME.  
Permission is granted to copy, distribute and/or modify this document  
under the terms of the GNU Free Documentation License, Version 1.2  
or any later version published by the Free Software Foundation;  
with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts.  
A copy of the license is included in the section entitled "GNU  
Free Documentation License".
```

If you have Invariant Sections, Front-Cover Texts and Back-Cover Texts, replace the "with...Texts." line with this:

```
with the Invariant Sections being LIST THEIR TITLES, with the  
Front-Cover Texts being LIST, and with the Back-Cover Texts being LIST.
```

If you have Invariant Sections without Cover Texts, or some other combination of the three, merge those two alternatives to suit the situation.

If your document contains nontrivial examples of program code, we recommend releasing these examples in parallel under your choice of free software license, such as the GNU General Public License, to permit their use in free software.