

Copiando arquivos e diretórios com o rsync

O QUE É?

Você pode usar a ferramenta rsync para copiar arquivos local ou remotamente. O rsync é unidirecional, ou seja, copia os arquivos apenas em uma direção.

POR QUÊ?

Este artigo apresenta uma visão geral da ferramenta rsync e seu uso básico para copiar arquivos local e remotamente.

DEDICAÇÃO

Leva até 20 minutos para compreender o uso básico da ferramenta rsync.

META

Obter uma compreensão básica do rsync e de como usá-lo para transferências de arquivos.

REQUISITOS

Permissões de acesso aos locais de origem e de destino para copiar os arquivos.

Data de Publicação: 11/12/2025

Conteúdo

- 1 Conceito do rsync 3

2	Uso básico do rsync	3
3	Copiando arquivos e diretórios com o rsync localmente	5
4	Copiando arquivos e diretórios com o rsync remotamente	6
5	Configurando e usando um servidor Rsync	6
6	Apagando e atualizando arquivos e diretórios com o rsync	9
7	Solucionando problemas do rsync	10
8	Informações legais	10
A	GNU Free Documentation License	11

1 Conceito do rsync

Você pode usar a ferramenta `rsync` para transferir ou copiar arquivos local e remotamente. O `rsync` é unidirecional. Ele copia os arquivos em uma única direção e não sincroniza os dados. Em vez de transmitir todo o conteúdo do arquivo, o `rsync` minimiza a quantidade de dados copiados movendo apenas as modificações feitas no arquivo. Dessa forma, é possível transferir os dados por uma conexão de rede lenta.

Para copiar arquivos grandes usando o `rsync`, a detecção de mudanças requer uma determinada capacidade de processamento. Portanto, verifique se as máquinas tanto na origem quanto no destino têm recursos suficientes, incluindo RAM.

Use o `rsync` quando uma grande quantidade de dados com poucas mudanças precisa ser transmitida regularmente. Isso é útil para trabalhar com backups. O `rsync` também espelha servidores para testes que armazenam árvores completas de diretórios de servidores Web em um servidor Web na DMZ.

Este artigo inclui exemplos que mostram o uso do `rsync` para copiar arquivos local e remotamente. Este documento também explica como configurar e usar um servidor `rsync`.

2 Uso básico do rsync

Você pode usar o `rsync` em qualquer máquina em que tenha permissões de acesso e gravação.

Copie os arquivos do local de origem para o local de destino, conforme mostrado no seguinte exemplo:

```
> rsync [OPTION] SOURCE [SOURCE]... DESTINATION
```

Você pode ter várias entradas `SOURCE`, e os espaços reservados `SOURCE` e `DESTINATION` podem ser caminhos, URLs ou ambos.

Veja abaixo alguns casos de uso da cópia de arquivos:

- ```
> rsync -av /directory1/ /destination/
```

No exemplo acima, a barra à direita após o diretório indica o conteúdo, e não o diretório em si. Neste caso, apenas o conteúdo de /directory1 é copiado para /destination.

- `> rsync -av /directory1 /destination/`

No exemplo acima, o diretório /directory1 é copiado para /destination, o que resulta em /destination/directory1/.

- `> rsync -av example1.txt example2.txt /destination/directory/`

O exemplo acima mostra a ação de copiar os arquivos example1.txt e example2.txt para o diretório de destino.

As OPTIONS (opções) mais comuns estão listadas abaixo:

- -v  
mostra o texto da saída em mais detalhes.
- -a  
modo de arquivamento: copia arquivos recursivamente e preserva marcações de horário, propriedade de usuário/grupo, permissões de arquivos e links simbólicos
- -z  
compacta os dados transmitidos
- -n ou --dry-run  
faz uma execução de teste sem nenhuma modificação
- -r  
executa recursivamente nos diretórios
- --progress  
mostra o progresso durante a transferência
- -b  
faz backup durante a sincronização de dados
- -h  
mostra os números na saída em um formato legível para humanos
- -e  
para transferências remotas, instrui o rsync a usar o protocolo SSH
- -q or --quiet

silencia o comando `rsync` e a saída da opção

- `--version`  
imprime o número da versão do `rsync` e encerra

#### Copiar arquivos localmente com compactação

```
> rsync -avz example1.txt example2.txt /destination/
```

`-a`: modo de arquivamento

`-v`: detalhado

`-z`: compactar os dados durante a transferência

#### Copiar um diretório com compactação

```
> rsync -avz /sourcedirectory/ /destinationdirectory/
```

Transfere o conteúdo de `/sourcedirectory/` com compactação.

#### Transferência remota de arquivos com compactação

```
> rsync -avz example1.txt user@remote_host:/remote/destination/
```

Transfere o `example1.txt` para uma máquina remota por SSH enquanto compacta os dados.

#### Transferência remota de diretórios com compactação

```
> rsync -avz /sourcedirectory/ user@remote_host:/remote/destination/
```

Transfere o `/sourcedirectory/` para uma máquina remota por SSH enquanto compacta os dados.

## 3 Copiando arquivos e diretórios com o `rsync` localmente

Você poderá copiar arquivos dentro da mesma máquina usando o `rsync` se tiver permissão de gravação no local de destino.

Para copiar o arquivo `backup.tar.xz` para o local `/var/backup/`, use o comando `rsync -avz backup.tar.xz /var/backup/`.

O arquivo `backup.tar.xz` é copiado para `/var/backup/`, e o caminho absoluto é `/var/backup/backup.tar.xz`.

## 4 Copiando arquivos e diretórios com o rsync remotamente

Você pode usar o rsync para copiar arquivos de uma máquina para outra máquina remota. Verifique se você tem o rsync nas máquinas tanto de origem quanto de destino e está conectado à máquina remota por SSH.

Para copiar um único arquivo de um diretório em sua máquina para o diretório `/var/backup` em uma máquina remota, use o seguinte comando:

```
> rsync -avz example1.txt user@remote_host:/var/backup/
```



### Nota: Barra à direita

Certifique-se de adicionar a barra à direita após o diretório `/var/backup/`. Se você não inserir a barra, o arquivo `example1.txt` será copiado para `/var/backup`, e não dentro do diretório `/var/backup/`.

Verifique o arquivo copiado no caminho absoluto `/var/backup/example1.txt`.

Para copiar o diretório `source/` e seu conteúdo para o diretório `/var/backup/`:

```
> rsync -avz /source/ user@remote_host:/var/backup/
```

Verifique o diretório copiado no caminho absoluto `/var/backup/source/`.

## 5 Configurando e usando um servidor Rsync

Um servidor rsync permite sincronização de arquivos, backups automatizados e armazenamento centralizado. É possível executar o rsync como um daemon `rsyncd` que escuta na porta padrão 873 para conexões recebidas. Esse daemon pode receber `copying targets`.

### PROCEDIMENTO 1: CONFIGURANDO UM SERVIDOR RSYNC

O arquivo de configuração para o daemon rsync é separado em um arquivo principal e alguns módulos que contêm o destino de backup. Isso facilita adicionar outros destinos futuramente. É possível armazenar valores globais nos arquivos `/etc/rsyncd.d/*.inc`, enquanto os módulos são armazenados em `/etc/rsyncd.d/*.conf`.

A descrição a seguir explica como criar um servidor rsync com um destino de backup. Esse destino pode ser usado para armazenar os backups. Para criar um servidor rsync, faça o seguinte:

1. Na máquina local, crie um diretório `/var/backup` para armazenar todos os arquivos de backup.

```
> mkdir /var/backup
```

2. Especifique a propriedade:

Neste exemplo, o usuário `tux` no grupo `users` é proprietário do diretório:

```
> chown tux.users /var/backup
```

3. Configure o daemon `rsyncd`:

- a. Crie um diretório `/etc/rsyncd.d/`

```
> mkdir /etc/rsyncd.d/
```

- b. Crie o arquivo de configuração principal `/etc/rsyncd.conf` e adicione as seguintes linhas:

```
log file = /var/log/rsync.log ❶
pid file = /var/lock/rsync.lock ❷
merge /etc/rsyncd.d ❸
include /etc/rsyncd.d ❹
```

- ❶ `/var/log/rsync.log` é o local onde o rsync grava os registros.
  - ❷ `/var/lock/rsync.lock` é o arquivo que contém o ID do processo da instância do daemon rsync em execução.
  - ❸ Faz a fusão dos valores globais dos arquivos `/etc/rsyncd.d/*.inc` no arquivo de configuração principal.
  - ❹ Carrega os módulos (ou destinos) dos arquivos `/etc/rsyncd.d/*.conf`. Esses arquivos não devem conter nenhuma referência a valores globais.
4. Crie o módulo ou o destino de backup no arquivo `/etc/rsyncd.d/backup.conf` com as seguintes linhas:

```
backup.conf: backup module
[backup] ❶
uid = tux ❷
```

```
gid = users ③
path = /var/backup ④
auth users = tux ⑤
secrets file = /etc/rsyncd.secrets ⑥
comment = Our backup target ⑦
```

No exemplo apresentado:

- ① `[backup]` é o destino do backup. Você pode usar qualquer nome para o destino do backup. É possível usar um nome de acordo com sua finalidade e usar o mesmo nome no arquivo `*.conf`.
- ② `uid = tux` especifica o nome de usuário ou do grupo que é usado quando a transferência de arquivos é feita.
- ③ `gid = users` define o caminho para armazenar os backups (da Etapa 1).
- ④ `path = /var/backup` define o caminho para armazenar os backups (da Etapa 1).
- ⑤ `auth users = tux` especifica uma lista separada por vírgulas de usuários permitidos. Em sua forma mais simples, ela contém os nomes de usuário que têm permissão para conectar-se a este módulo. Em nosso caso, apenas o usuário `tux` é permitido.
- ⑥ `secrets file = /etc/rsyncd.secrets` especifica o caminho de um arquivo que contém as linhas com os nomes de usuário e as senhas simples.

5. Crie o arquivo `/etc/rsyncd.secrets` com o seguinte conteúdo e substitua `PASSPHRASE`:

```
user:passwd
tux:PASSPHRASE
```

6. Verifique se o arquivo pode ser lido apenas por `root`:

```
chmod 0600 /etc/rsyncd.secrets
```

7. Inicie e habilite o daemon `rsyncd` com:

```
> systemctl enable rsyncd
> systemctl start rsyncd
```

8. Na máquina remota, teste o acesso ao servidor `rsync`:

```
> rsync jupiter::
```

É exibida uma resposta semelhante a esta:

```
backup Our backup target
```

Se a resposta acima não aparecer, verifique o arquivo de configuração, o firewall e as configurações de rede.

As etapas acima criam um servidor `rsync` que você pode usar para armazenar backups. O exemplo também cria um arquivo de registro listando todas as conexões. Esse arquivo é armazenado em `/var/log/rsyncd.log`. Isso é útil para depurar as transferências.

9. Para listar o conteúdo do destino do backup, use o seguinte comando em sua máquina local:

```
> rsync -avz jupiter::backup
```

Esse comando lista todos os arquivos presentes no diretório `/var/backup` no servidor. Essa solicitação também é registrada no arquivo de registro `/var/log/rsyncd.log`.

10. Para copiar o diretório atual para o seu servidor de backup `rsync`, insira o diretório de origem. Se o diretório de origem for o seu diretório atual, use `.`

```
> rsync -avz . jupiter::backup
```

Por padrão, o `rsync` não apaga arquivos e diretórios quando é executado. Para habilitar a exclusão, a opção adicional `--delete` deve ser especificada. Para garantir que nenhum arquivo novo seja apagado, use a opção `--update` como alternativa. Qualquer conflito ocorrido deve ser resolvido manualmente.

## 6 Apagando e atualizando arquivos e diretórios com o rsync

Você poderá copiar e sincronizar arquivos dentro da mesma máquina usando o `rsync` se tiver permissão de gravação no local de destino. Você também poderá apagar arquivos ou diretórios após a cópia.

Para copiar os arquivos `example1.txt` e `example2.txt` de `/source/directory/` para `/destination/directory/`:

```
> rsync -av --update /source/directory/ /destination/directory/
```

O comando `rsync` atualizará os arquivos `example1.txt` e `example2.txt` no `/destination/directory/`, se ele for mais antigo que o arquivo de origem. Se a versão no destino for mais recente, os arquivos não serão substituídos. Além disso, todos os outros arquivos ou diretórios novos de `/source/directory/` serão copiados para `/destination/`.

Para copiar um arquivo existente e apagar um arquivo que não existe no diretório de destino:

```
> rsync -av --delete /source/directory/ /destination/directory/
```

Nesse cenário, os diretórios de origem e de destino contêm `example1.txt` e `example2.txt`. O `/destination/directory` contém um arquivo extra: `example3.txt`.

O comando `rsync` copia ou atualiza os arquivos `example1.txt` e `example2.txt` de `/source/directory/` para `/destination/directory/`. O comando também apaga o arquivo `example3.txt` de `/destination/directory/`, já que ele não existe em `/source/directory/`. Além disso, a estrutura de diretórios em `/destination/directory/` é limpa para corresponder ao `/source/directory/`.

## 7 Solucionando problemas do rsync

A cópia de arquivos ou pastas pode falhar por vários motivos. Verifique se você tem as permissões e os recursos necessários para executar a cópia do arquivo.

Os métodos de solução de problemas possíveis estão mencionados abaixo:

- Verifique se você selecionou a versão mais recente do `rsync`. Para transferir arquivos ou diretórios remotamente, verifique se o `rsync` está instalado nas máquinas de origem e de destino.
- Garanta que você tenha a permissão de acesso ao `rsync` necessária.
- Insira o nome de host correto para copiar os arquivos remotamente.
- Certifique-se de que o serviço `rsync` esteja em execução, se você usa o `rsync` no modo de `daemon`.

## 8 Informações legais

Copyright© 2006 – 2025 SUSE LLC e colaboradores. Todos os direitos reservados.

Permissão concedida para copiar, distribuir e/ou modificar este documento sob os termos da Licença GNU de Documentação Livre, Versão 1.2 ou (por sua opção) versão 1.3; com a Seção Invariante sendo estas informações de copyright e a licença. Uma cópia da versão 1.2 da licença está incluída na seção intitulada “GNU Free Documentation License” (Licença GNU de Documentação Livre).

Para saber as marcas registradas da SUSE, visite <https://www.suse.com/company/legal/>. Todas as marcas comerciais de terceiros pertencem a seus respectivos proprietários. Os símbolos de marca registrada (®, ™ etc.) indicam marcas registradas da SUSE e de suas afiliadas. Os asteriscos (\*) indicam marcas registradas de terceiros.

Todas as informações deste manual foram compiladas com a maior atenção possível aos detalhes. Entretanto, isso não garante uma precisão absoluta. A SUSE LLC, suas afiliadas, os autores ou tradutores não serão responsáveis por possíveis erros nem pelas consequências resultantes de tais erros.

## A GNU Free Documentation License

Copyright (C) 2000, 2001, 2002 Free Software Foundation, Inc. 51 Franklin St, Fifth Floor, Boston, MA 02110-1301 USA. Everyone is permitted to copy and distribute verbatim copies of this license document, but changing it is not allowed.

### 0. PREAMBLE

The purpose of this License is to make a manual, textbook, or other functional and useful document "free" in the sense of freedom: to assure everyone the effective freedom to copy and redistribute it, with or without modifying it, either commercially or non-commercially. Secondly, this License preserves for the author and publisher a way to get credit for their work, while not being considered responsible for modifications made by others.

This License is a kind of "copyleft", which means that derivative works of the document must themselves be free in the same sense. It complements the GNU General Public License, which is a copyleft license designed for free software.

We have designed this License to use it for manuals for free software, because free software needs free documentation: a free program should come with manuals providing the same freedoms that the software does. But this License is not limited to software manuals; it can be used for any textual work, regardless of subject matter or whether it is published as a printed book. We recommend this License principally for works whose purpose is instruction or reference.

## 1. APPLICABILITY AND DEFINITIONS

This License applies to any manual or other work, in any medium, that contains a notice placed by the copyright holder saying it can be distributed under the terms of this License. Such a notice grants a world-wide, royalty-free license, unlimited in duration, to use that work under the conditions stated herein. The "Document", below, refers to any such manual or work. Any member of the public is a licensee, and is addressed as "you". You accept the license if you copy, modify or distribute the work in a way requiring permission under copyright law.

A "Modified Version" of the Document means any work containing the Document or a portion of it, either copied verbatim, or with modifications and/or translated into another language.

A "Secondary Section" is a named appendix or a front-matter section of the Document that deals exclusively with the relationship of the publishers or authors of the Document to the Document's overall subject (or to related matters) and contains nothing that could fall directly within that overall subject. (Thus, if the Document is in part a textbook of mathematics, a Secondary Section may not explain any mathematics.) The relationship could be a matter of historical connection with the subject or with related matters, or of legal, commercial, philosophical, ethical or political position regarding them.

The "Invariant Sections" are certain Secondary Sections whose titles are designated, as being those of Invariant Sections, in the notice that says that the Document is released under this License. If a section does not fit the above definition of Secondary then it is not allowed to be designated as Invariant. The Document may contain zero Invariant Sections. If the Document does not identify any Invariant Sections then there are none.

The "Cover Texts" are certain short passages of text that are listed, as Front-Cover Texts or Back-Cover Texts, in the notice that says that the Document is released under this License. A Front-Cover Text may be at most 5 words, and a Back-Cover Text may be at most 25 words.

A "Transparent" copy of the Document means a machine-readable copy, represented in a format whose specification is available to the general public, that is suitable for revising the document straightforwardly with generic text editors or (for images composed of pixels) generic paint programs or (for drawings) some widely available drawing editor, and that is suitable for input

to text formatters or for automatic translation to a variety of formats suitable for input to text formatters. A copy made in an otherwise Transparent file format whose markup, or absence of markup, has been arranged to thwart or discourage subsequent modification by readers is not Transparent. An image format is not Transparent if used for any substantial amount of text. A copy that is not "Transparent" is called "Opaque".

Examples of suitable formats for Transparent copies include plain ASCII without markup, Texinfo input format, LaTeX input format, SGML or XML using a publicly available DTD, and standard-conforming simple HTML, PostScript or PDF designed for human modification. Examples of transparent image formats include PNG, XCF and JPG. Opaque formats include proprietary formats that can be read and edited only by proprietary word processors, SGML or XML for which the DTD and/or processing tools are not generally available, and the machine-generated HTML, PostScript or PDF produced by some word processors for output purposes only. The "Title Page" means, for a printed book, the title page itself, plus such following pages as are needed to hold, legibly, the material this License requires to appear in the title page. For works in formats which do not have any title page as such, "Title Page" means the text near the most prominent appearance of the work's title, preceding the beginning of the body of the text.

A section "Entitled XYZ" means a named subunit of the Document whose title either is precisely XYZ or contains XYZ in parentheses following text that translates XYZ in another language. (Here XYZ stands for a specific section name mentioned below, such as "Acknowledgements", "Dedications", "Endorsements", or "History".) To "Preserve the Title" of such a section when you modify the Document means that it remains a section "Entitled XYZ" according to this definition. The Document may include Warranty Disclaimers next to the notice which states that this License applies to the Document. These Warranty Disclaimers are considered to be included by reference in this License, but only as regards disclaiming warranties: any other implication that these Warranty Disclaimers may have is void and has no effect on the meaning of this License.

## 2. VERBATIM COPYING

You may copy and distribute the Document in any medium, either commercially or non-commercially, provided that this License, the copyright notices, and the license notice saying this License applies to the Document are reproduced in all copies, and that you add no other conditions whatsoever to those of this License. You may not use technical measures to obstruct or control the reading or further copying of the copies you make or distribute. However, you may accept compensation in exchange for copies. If you distribute a large enough number of copies you must also follow the conditions in section 3.

You may also lend copies, under the same conditions stated above, and you may publicly display copies.

### 3. COPYING IN QUANTITY

If you publish printed copies (or copies in media that commonly have printed covers) of the Document, numbering more than 100, and the Document's license notice requires Cover Texts, you must enclose the copies in covers that carry, clearly and legibly, all these Cover Texts: Front-Cover Texts on the front cover, and Back-Cover Texts on the back cover. Both covers must also clearly and legibly identify you as the publisher of these copies. The front cover must present the full title with all words of the title equally prominent and visible. You may add other material on the covers in addition. Copying with changes limited to the covers, as long as they preserve the title of the Document and satisfy these conditions, can be treated as verbatim copying in other respects.

If the required texts for either cover are too voluminous to fit legibly, you should put the first ones listed (as many as fit reasonably) on the actual cover, and continue the rest onto adjacent pages.

If you publish or distribute Opaque copies of the Document numbering more than 100, you must either include a machine-readable Transparent copy along with each Opaque copy, or state in or with each Opaque copy a computer-network location from which the general network-using public has access to download using public-standard network protocols a complete Transparent copy of the Document, free of added material. If you use the latter option, you must take reasonably prudent steps, when you begin distribution of Opaque copies in quantity, to ensure that this Transparent copy will remain thus accessible at the stated location until at least one year after the last time you distribute an Opaque copy (directly or through your agents or retailers) of that edition to the public.

It is requested, but not required, that you contact the authors of the Document well before redistributing any large number of copies, to give them a chance to provide you with an updated version of the Document.

## 4. MODIFICATIONS

You may copy and distribute a Modified Version of the Document under the conditions of sections 2 and 3 above, provided that you release the Modified Version under precisely this License, with the Modified Version filling the role of the Document, thus licensing distribution and modification of the Modified Version to whoever possesses a copy of it. In addition, you must do these things in the Modified Version:

- A. Use in the Title Page (and on the covers, if any) a title distinct from that of the Document, and from those of previous versions (which should, if there were any, be listed in the History section of the Document). You may use the same title as a previous version if the original publisher of that version gives permission.
- B. List on the Title Page, as authors, one or more persons or entities responsible for authorship of the modifications in the Modified Version, together with at least five of the principal authors of the Document (all of its principal authors, if it has fewer than five), unless they release you from this requirement.
- C. State on the Title page the name of the publisher of the Modified Version, as the publisher.
- D. Preserve all the copyright notices of the Document.
- E. Add an appropriate copyright notice for your modifications adjacent to the other copyright notices.
- F. Include, immediately after the copyright notices, a license notice giving the public permission to use the Modified Version under the terms of this License, in the form shown in the Addendum below.
- G. Preserve in that license notice the full lists of Invariant Sections and required Cover Texts given in the Document's license notice.
- H. Include an unaltered copy of this License.
- I. Preserve the section Entitled "History", Preserve its Title, and add to it an item stating at least the title, year, new authors, and publisher of the Modified Version as given on the Title Page. If there is no section Entitled "History" in the Document, create one stating the title, year, authors, and publisher of the Document as given on its Title Page, then add an item describing the Modified Version as stated in the previous sentence.
- J. Preserve the network location, if any, given in the Document for public access to a Transparent copy of the Document, and likewise the network locations given in the Document for previous versions it was based on. These may be placed in the "History"

section. You may omit a network location for a work that was published at least four years before the Document itself, or if the original publisher of the version it refers to gives permission.

- K. For any section Entitled "Acknowledgements" or "Dedications", Preserve the Title of the section, and preserve in the section all the substance and tone of each of the contributor acknowledgements and/or dedications given therein.
- L. Preserve all the Invariant Sections of the Document, unaltered in their text and in their titles. Section numbers or the equivalent are not considered part of the section titles.
- M. Delete any section Entitled "Endorsements". Such a section may not be included in the Modified Version.
- N. Do not retitle any existing section to be Entitled "Endorsements" or to conflict in title with any Invariant Section.
- O. Preserve any Warranty Disclaimers.

If the Modified Version includes new front-matter sections or appendices that qualify as Secondary Sections and contain no material copied from the Document, you may at your option designate some or all of these sections as invariant. To do this, add their titles to the list of Invariant Sections in the Modified Version's license notice. These titles must be distinct from any other section titles.

You may add a section Entitled "Endorsements", provided it contains nothing but endorsements of your Modified Version by various parties--for example, statements of peer review or that the text has been approved by an organization as the authoritative definition of a standard.

You may add a passage of up to five words as a Front-Cover Text, and a passage of up to 25 words as a Back-Cover Text, to the end of the list of Cover Texts in the Modified Version. Only one passage of Front-Cover Text and one of Back-Cover Text may be added by (or through arrangements made by) any one entity. If the Document already includes a cover text for the same cover, previously added by you or by arrangement made by the same entity you are acting on behalf of, you may not add another; but you may replace the old one, on explicit permission from the previous publisher that added the old one.

The author(s) and publisher(s) of the Document do not by this License give permission to use their names for publicity for or to assert or imply endorsement of any Modified Version.

## 5. COMBINING DOCUMENTS

You may combine the Document with other documents released under this License, under the terms defined in section 4 above for modified versions, provided that you include in the combination all of the Invariant Sections of all of the original documents, unmodified, and list them all as Invariant Sections of your combined work in its license notice, and that you preserve all their Warranty Disclaimers.

The combined work need only contain one copy of this License, and multiple identical Invariant Sections may be replaced with a single copy. If there are multiple Invariant Sections with the same name but different contents, make the title of each such section unique by adding at the end of it, in parentheses, the name of the original author or publisher of that section if known, or else a unique number. Make the same adjustment to the section titles in the list of Invariant Sections in the license notice of the combined work.

In the combination, you must combine any sections Entitled "History" in the various original documents, forming one section Entitled "History"; likewise combine any sections Entitled "Acknowledgements", and any sections Entitled "Dedications". You must delete all sections Entitled "Endorsements".

## 6. COLLECTIONS OF DOCUMENTS

You may make a collection consisting of the Document and other documents released under this License, and replace the individual copies of this License in the various documents with a single copy that is included in the collection, provided that you follow the rules of this License for verbatim copying of each of the documents in all other respects.

You may extract a single document from such a collection, and distribute it individually under this License, provided you insert a copy of this License into the extracted document, and follow this License in all other respects regarding verbatim copying of that document.

## 7. AGGREGATION WITH INDEPENDENT WORKS

A compilation of the Document or its derivatives with other separate and independent documents or works, in or on a volume of a storage or distribution medium, is called an "aggregate" if the copyright resulting from the compilation is not used to limit the legal rights of the compilation's users beyond what the individual works permit. When the Document is included in an aggregate, this License does not apply to the other works in the aggregate which are not themselves derivative works of the Document.

If the Cover Text requirement of section 3 is applicable to these copies of the Document, then if the Document is less than one half of the entire aggregate, the Document's Cover Texts may be placed on covers that bracket the Document within the aggregate, or the electronic equivalent of covers if the Document is in electronic form. Otherwise they must appear on printed covers that bracket the whole aggregate.

## 8. TRANSLATION

Translation is considered a kind of modification, so you may distribute translations of the Document under the terms of section 4. Replacing Invariant Sections with translations requires special permission from their copyright holders, but you may include translations of some or all Invariant Sections in addition to the original versions of these Invariant Sections. You may include a translation of this License, and all the license notices in the Document, and any Warranty Disclaimers, provided that you also include the original English version of this License and the original versions of those notices and disclaimers. In case of a disagreement between the translation and the original version of this License or a notice or disclaimer, the original version will prevail.

If a section in the Document is Entitled "Acknowledgements", "Dedications", or "History", the requirement (section 4) to Preserve its Title (section 1) will typically require changing the actual title.

## 9. TERMINATION

You may not copy, modify, sublicense, or distribute the Document except as expressly provided for under this License. Any other attempt to copy, modify, sublicense or distribute the Document is void, and will automatically terminate your rights under this License. However, parties who have received copies, or rights, from you under this License will not have their licenses terminated so long as such parties remain in full compliance.

## 10. FUTURE REVISIONS OF THIS LICENSE

The Free Software Foundation may publish new, revised versions of the GNU Free Documentation License from time to time. Such new versions will be similar in spirit to the present version, but may differ in detail to address new problems or concerns. See <https://www.gnu.org/copyleft/>.

Each version of the License is given a distinguishing version number. If the Document specifies that a particular numbered version of this License "or any later version" applies to it, you have the option of following the terms and conditions either of that specified version or of any later version that has been published (not as a draft) by the Free Software Foundation. If the Document does not specify a version number of this License, you may choose any version ever published (not as a draft) by the Free Software Foundation.

## ADDENDUM: How to use this License for your documents

```
Copyright (c) YEAR YOUR NAME.
Permission is granted to copy, distribute and/or modify this document
under the terms of the GNU Free Documentation License, Version 1.2
or any later version published by the Free Software Foundation;
with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts.
A copy of the license is included in the section entitled "GNU
Free Documentation License".
```

If you have Invariant Sections, Front-Cover Texts and Back-Cover Texts, replace the "with...Texts" line with this:

```
with the Invariant Sections being LIST THEIR TITLES, with the
Front-Cover Texts being LIST, and with the Back-Cover Texts being LIST.
```

If you have Invariant Sections without Cover Texts, or some other combination of the three, merge those two alternatives to suit the situation.

If your document contains nontrivial examples of program code, we recommend releasing these examples in parallel under your choice of free software license, such as the GNU General Public License, to permit their use in free software.