SAP

# SAP Data Intelligence 3 on CaaS Platform 4.2

Installation Guide

SUSE CaaS Platform 4.2 SUSE Linux Enterprise Server for SAP applications 15 SAP Data Intelligence 3

Dr. Ulrich Schairer, SAP Solutions Architect (SUSE) Kevin Klinger, SAP Solutions Architect (SUSE)



SAP Data Intelligence 3 on CaaS Platform 4.2

Installation Guide

Date: 2025-12-11

SAP Data Intelligence 3 is the tool set to govern big amount of data. SUSE CaaS Platform 4 is the Kubernetes base that makes deploying SAP Data Intelligence 3 easy. This document describes the installation and configuration of SUSE CaaS Platform 4 and SAP Data Intelligence 3.

**Disclaimer:** Documents published as part of the SUSE Best Practices series have been contributed voluntarily by SUSE employees and third parties. They are meant to serve as examples of how particular actions can be performed. They have been compiled with utmost attention to detail. However, this does not guarantee complete accuracy. SUSE cannot verify that actions described in these documents do what is claimed or whether actions described have unintended consequences. SUSE LLC, its affiliates, the authors, and the translators may not be held liable for possible errors or the consequences thereof.

# Contents

- 1 Introduction 4
- 2 Prerequisites 4
- 3 Installing SUSE CaaSP 4.2 5
- 4 Adding secure private Docker Registry for container images 9
- 5 SUSE Enterprise Storage 23
- 6 Installing SAP Data Intelligence 3 on top of SUSE CaaSP 4.2 58
- 7 Legal notice 86
- 8 GNU Free Documentation License 87

# 1 Introduction

This guide describes the on-premises installation of SAP Data Intelligence 3 on SUSE CaaS Platform 4.2.

# 2 Prerequisites

#### 2.1 Hardware

For sizing information, see in addition the SAP documentation: Sizing Guide for SAP Data Intelligence (https://help.sap.com/viewer/835f1e8d0dde4954ba0f451a9d4b5f10/3.0.latest/en-US)

At least eight nodes are needed for a Kubernetes cluster for production use.

- Minimal requirements:
  - three master nodes
  - four worker nodes
  - one or two loadbalancers (these can be virtual machines)

For the installation of SUSE CaaSP 4.2, additional hosts are needed:

- Management host
- Registry for storing container images

These can be virtual machines.

#### 2.2 Software

- SUSE Linux Enterprise 15 SP1
- SUSE CaaSP 4.2

# 3 Installing SUSE CaaSP 4.2

#### 3.1 Documentation

SUSE CaaS Platform 4.2 is documented here:

• SUSE CaaS Platform product documentation (https://documentation.suse.com/suse-caasp/4.2/) 

✓

#### 3.2 Preparations

On all the nodes, install SUSE Linux Enterprise 15 SP1 or higher, as per the documentation for CaaS Platform 4.2.

On each respective node, the following modules or products are required.

- Management host:
  - SUSE Linux Enterprise 15 SP1
  - SUSE Linux Enterprise 15 SP1 Containers Modules
  - SUSE Linux Enterprise 15 SP1 Public Cloud
  - SUSE CaaSP 4
- Kubernetes master nodes:
  - SUSE Linux Enterprise 15 SP1
  - SUSE Linux Enterprise 15 SP1 Public Cloud
  - SUSE CaaSP 4

- Kubernetes worker nodes:
  - SUSE Linux Enterprise 15 SP1
  - SUSE Linux Enterprise 15 SP1 Public Cloud
  - SUSE CaaSP 4
- Loadbalancer host:
  - SUSE Linux Enterprise Server for SAP applications 15 SP1 or
  - SUSE Linux Enterprise 15 SP1 plus High Availability Extension

## 3.3 Installing the SUSE CaaSP 4 cluster nodes

• Install SUSE Linux Enterprise 15 SP1.



#### Note

Use the "Expert Partitioner" to disable and remove any automatically-configured swap partitions on the Kubernetes nodes.

#### See the relevant product documentation:

- SUSE Linux Enterprise Server 15 SP1 Deployment Guide (https://documentation.suse.com/sles/15-SP1/single-html/SLES-deployment/#book-sle-deployment) 

  ✓
- SUSE CaaS Platform Deployment Guide (https://documentation.suse.com/suse-caasp/4.2/)

# 3.4 Installing the loadbalancer for the Kubernetes cluster

- Install SUSE Linux Enterprise 15 SP1
- Install ha-proxy or nginx
- Configure the loadbalancer

#### See the relevant product documentation:

• SUSE CaaS Platform Deployment Guide (https://documentation.suse.com/suse-caasp/4.2/sin-gle-html/caasp-deployment/) ▶

## 3.5 Installing the management workstation

- Install SUSE Linux Enterprise 15 SP1
- Add the necessary SUSE Linux Enterprise 15 SP1 modules: value

```
$ sudo SUSEConnect -r CAASP_REGISTRATION_CODE
$ sudo SUSEConnect -p sle-module-containers/15.1/x86_64
$ sudo SUSEConnect -p caasp/4.0/x86_64 -r CAASP_REGISTRATION_CODE
$ sudo SUSEConnect -p sle-module-python2/15.1/x86_64
```

### 3.6 Bootstrapping the SUSE CaaSP 4 cluster

- Run the skuba tool for initialization of the cluster.
- Make sure that <u>ssh</u> is working between all nodes without using passwords, and configure ssh-agent.

```
$ eval `ssh-agent`
$ ssh-add <path to key>

$ skuba cluster init --control-plane <LB IP/FQDN> my-cluster
```

Bootstrap the cluster:

```
$ cd my-cluster
$ skuba node bootstrap --target <IP/FQDN> <NODE NAME>
```

Add additional master nodes:

```
$ cd my-cluster
$ skuba node join --role master --target <IP/FQDN> <NODE NAME>
```

• Repeat this for all the master nodes.

• Add the worker nodes:

```
$ cd my-cluster
$ skuba node join --role worker --target <IP/FQDN> <NODE NAME>
```

- Repeat this for all worker nodes.
- Finally, check the cluster status.

```
$ cd my-cluster
$ skuba cluster status
$ cp -av ~/my-cluster/admin.conf ~/.kube/config
$ kubectl get nodes -o wide
```

# 4 Adding secure private Docker Registry for container images



#### Tip

This step is optional if you already have a private secure Docker Registry. If you skip this chapter, follow the instructions in *Section 5, "SUSE Enterprise Storage"*.

To satisfy the requirements for SAP Data Intelligence 3, you also need a Docker Registry. The easiest way to build and manage one is using the Harbor project (https://goharbor.io/) ₹.

To this end, you need to create a dedicated server for your Docker registry and the Harbor stack.



#### Warning

As Docker only allows characters within the range [a-z],[A-Z],[0-9] and '-' for domain names, make sure that your FQDN does not contain any other characters.

In our example, the server will be connected to a local bridge which provides common services (DNS, SMT, Docker-registry) for the SAP Data Intelligence stack. The FQDN of this server will be harbor-registry.example.com.

## 4.1 Prerequisites

Find the prerequisites for Harbor here: Harbor Installation Prerequisites (https://goharbor.io/docs/2.1.0/install-config/installation-prereqs/) 

✓

Before you can set up Harbor, you need to install Docker and Docker Compose.

• To install Docker, run:

```
# zypper in -y docker
```

 To install Docker Compose, you must download the executable from its GitHub repository (https://github.com/docker/compose) 
 and save it into a directory within your \$PATH.
 For example, run:

```
# curl -L "https://github.com/docker/compose/releases/download/1.25.5/docker-
compose-$(uname -s)-$(uname -m)" -o /usr/local/bin/docker-compose
```

```
# chmod +x /usr/local/bin/docker-compose
# ln -s /usr/local/bin/docker-compose /usr/bin/docker-compose
```

The next steps will generate the certificates used to make Harbor secure. These can also be found in the document Configure HTTPS Access to Harbor (https://goharbor.io/docs/2.1.0/install-config/configure-https/) .

1. First, generate a CA certificate private key:

```
# openssl genrsa -out ca.key 4096
```

2. Then, generate a certificate with the given key for your domain.



#### Note

For all further steps, replace <FQDN> with your fully qualified domain name. In our example, this would be harbor-registry.example.com.

```
# openssl req -x509 -new -nodes -sha512 -days 3650 \
  -subj "/C=DE/ST=BW/0=SUSE/CN=<FQDN>" \
  -key ca.key \
  -out ca.crt
```

Your CA certificate is now ready for use.

3. Next, you must generate a server certificate as follows:

```
# openssl genrsa -out <FQDN>.key 4096
```

4. Generate a certificate signing request (CSR):

```
# openssl req -sha512 -new \
  -subj "/C=DE/ST=BW/0=SUSE/CN=<FQDN>" \
  -key <FQDN>.key \
  -out <FQDN>.csr
```

5. Create an x509 v3 extension file with the following content:

```
authorityKeyIdentifier=keyid,issuer
basicConstraints=CA:FALSE
keyUsage = digitalSignature, nonRepudiation, keyEncipherment, dataEncipherment
```

```
extendedKeyUsage = serverAuth
subjectAltName = @alt_names

[alt_names]
DNS.1=<FQDN>
DNS.2=<hostname>
```

**6.** Use the extension file to generate a certificate:

```
# openssl x509 -req -sha512 -days 3650 \
   -extfile v3.ext \
   -CA ca.crt -CAkey ca.key -CAcreateserial \
   -in $fqdn.csr \
   -out $fqdn.crt
```

7. Copy the .crt and .key files to the system's certificate directory:

```
# cp <FQDN>.crt /etc/pki/trust/anchors/
# cp <FQDN>.key /etc/pki/trust/anchors/
```

8. As Docker interprets <u>.crt</u> files as CA certificates and <u>.cert</u> files as clients, you must convert your .crt file as follows:

```
# openssl x509 -inform PEM -in <FQDN>.crt -out $<FQDN>.cert
```

9. You can now copy the newly created certificates to your Docker certificate directory. If the directory /etc/docker/certs.d does not exist, create it.

```
# mkdir /etc/docker/certs.d/<FQDN>
# cp <FQDN>.cert /etc/docker/certs.d/<FQDN>/
# cp <FQDN>.key /etc/docker/certs.d/<FQDN>/
# cp ca.crt /etc/docker/certs.d/<FQDN>/
```



#### Note

If you want to expose your registry on a port other than 443, you must create a directory /etc/docker/certs.d/<FQDN>:<Port> and copy the certificates to this directory instead.

**10**. To introduce the certificates to Docker, restart the Docker daemon:

```
# systemctl restart docker
```

## 4.2 Setting up Harbor

1. Fetch the Harbor installer and extract its contents:

```
# wget https://github.com/goharbor/harbor/releases/download/v2.1.1/harbor-online-
installer-v2.1.1.tgz
# tar xvf harbor-online-installer-v2.1.1.tgz
```

**2**. Enter the extracted directory:

```
# cd harbor
```

- 3. Within this directory, you should find a file called <a href="harbor.yml.tmpl">harbor.yml.tmpl</a>. It contains the configuration for the Harbor Registry and must be adjusted.
  - a. First, edit the hostname field and enter your FQDN.
  - b. Next, update the **HTTPS** configuration. The subentries <u>certificate</u> and <u>private\_key</u> must be adjusted so they point to the <u>.crt</u> and <u>.key</u> files you created in <u>Section 4.1, "Prerequisites"</u>.

This should look like the following:

If you want to expose registry on a port other than 443, you can change the port sub-entry to match your desired port.

- c. You should also change the <u>administrator</u> password for Harbor, which by default is defined in the field harbor\_admin\_password: Harbor12345.
- d. The last field to mention is <a href="data\_volume">data\_volume</a>: /data, which defines where all Harbor data will be stored. If you want Harbor to store the data somewhere else, enter the path to the desired directory here.
- 4. When done, save your changes, and rename the file by removing the .tmpl suffix:

```
# mv harbor.yml.tmpl harbor.yml
```

5. As Harbor uses <u>nginx</u> as a reverse proxy for all services, you must run the <u>prepare</u> script to configure it correctly:

```
# ./prepare
```

6. You can now start the needed containers using Docker Compose:

```
# docker-compose up -d
```

Harbor should now be up and running.

7. Distribute the CA certificate to all Kubernetes nodes, so they can access the registry. Run the following commands on all the nodes:

```
# scp <FQDN>:/etc/docker/certs.d/<FQDN>/ca.crt /etc/docker/certs.d/<FQDN>/<FQDN>.crt
# systemctl restart docker
```

For the example < FQDN > of harbor-registry.example.com, this looks like the following:

```
# scp harbor-registry.example.com:/etc/docker/certs.d/harbor-registry.example.com/
ca.crt /etc/docker/certs.d/harbor-registry.example.com/harbor-
registry.example.com.crt
# systemctl restart docker
```

# 4.3 Verifying configuration and setting up Harbor projects

To verify Harbor is running, you may access its Web front-end by visiting https:// $<\!FQDN\!>$  from your browser.






FIGURE 2: HARBOR CERTIFICATE WARNING

You can toggle the lower box by clicking Advanced... Then click Accept the Risk and Continue. You will be redirected to the login page of your Harbor registry.



Enter  $\underline{\mathtt{admin}}$  as the user name and enter the password specified in the  $\underline{\mathtt{harbor.yml}}$  file. By default, this is "Harbor12345".

By default, you will be redirected to the project page which holds the "libraries" project.



You should also check if the Docker clients on your Kubernetes nodes can access the registry. To do so, run:

```
# docker login <FQDN>
```

You will be prompted to enter a user name and password. Use <u>admin</u> for the user name, and the password you set in harbor.yml (default: "Harbor12345").

If Docker can access the registry, you will see a message displayed that states "Login Succeeded" or similar.

If your machines cannot resolve the FQDN of your registry, edit your <u>/etc/hosts</u> file and add a line with the following information:

```
<IP> <FQDN> <Hostname>
```

In our example, this will look as follows:

```
192.168.180.100 harbor-registry.example.com harbor-registry
```

Create the namespaces on your registry that are needed for SAP Data Intelligence 3:

- com.sap.hana.container
- com.sap.datahub.linuxx86 64
- com.sap.datahub.linuxx86 64.gcc6
- consul
- elasticsearch
- fabric8
- google\_containers
- grafana
- kibana
- prom
- vora
- kaniko-project
- com.sap.bds.docker

# 5 SUSE Enterprise Storage



Tip

This step is optional if you already have a storage that provides RBD volumes and/or S3 buckets. If you skip this chapter, follow the instructions in Section 6.4, "Installing SAP Data Intelligence 3".

An on-premises installation of SAP Data Intelligence 3 requires SUSE Enterprise Storage 5.5 or higher.

If you plan to use SUSE Enterprise Storage not only for your Kubernetes dynamic storage class but also for your Kubernetes control plane (virtualized or not), you should reserve enough resources to address the <a href="etcd">etcd</a> requirements specified in the <a href="etcd">etcd</a> Hardware recommendations (https://etcd.io/docs/current/op-guide/hardware/)

The following steps will deploy a minimalist, virtualized, test-oriented instance of SUSE Enterprise Storage 6. In our example, we will build a four-nodes (1 Admin + 3 OSD) Ceph cluster.

### 5.1 Before starting

 Obtain registration codes for SUSE Linux Enterprise Server 15 SP1 and SUSE Enterprise Storage from https://scc.suse.com 

, or have SMT/RMT properly set up and already mirroring these products.

#### • SCC (https://scc.suse.com) ✓




FIGURE 5: SUSE CUSTOMER CENTER - SUSE LINUX ENTERPRISE SERVER

• SMT (https://documentation.suse.com/smt/11.3/html/SLE-smt/index.html) ▶





FIGURE 6: "SUSE CUSTOMER CENTER - SUSE ENTERPRISE STORAGE

- 3. Select your preferred language and keyboard layout. Then select the option "SUSE Linux Enterprise Server 15 SP1" and click the "Next" button.
- 4. You need to agree to the license agreement. Click "Next" again.
- **5.** The registration screen should be displayed.



- 6. Now, either enter your e-mail and the registration code you collected from the SCC as described in the previous chapter, or select "Register System via local SMT Server" and enter the URL of your SMT server.
- **7.** If required, you can use the **Network Configuration** button at the top right to configure your network settings.



# Add On Product

- I would li<u>k</u>e to install a
  - O Scan Using SLP...
  - Specify <u>U</u>RL...
  - O FTP...
  - O HTTP..
  - O HTTPS..
  - O SMB/CIFS
  - O NFS..
  - O CD...
  - O DVD..
  - O Hard Disk...
  - O USB Mass Storag
  - O Local Directory...
  - O Local ISO Image..
  - Download reposit

Help

- **8**. When the system is registered, you will see the "Add On Product" page. You can skip it by clicking the "Next" button again.
- 9. The "Suggested Partitioning" page will be displayed. You may edit the proposed partitioning if needed. For our example, we accept the proposal and continue by clicking the "Next" button.



# Suggested Partitioning

Initial layout proposed with the default Guid Changes to partitioning:

- Create GPT on /dev/vda
- Create partition /dev/vda1 (8.00 Mil
- Create partition /dev/vda2 (16.40 Gi
- Create partition /dev/vda3 (7.93 GiB
   Create partition /dev/vda4 (15.66 GiB
- 9 subvolume actions (see details)


Help

Release Notes...

10.	On the Zone.	"Clock	and	Time	Zone"	page,	you	should	select	your	preferre	d Regio	on and	Time




# Clock and Time Zone



Click "Other Settings" to open the "Change Date and Time" page. Select the "Synchronize with NTP-Server" option. Then select an NTP server and click the "Accept" button.




# Change Date and Time



# Important

All machines in the cluster must synchronize with the same NTP Server!

11. Next, you can create a user with name and password of your choice. When done, confirm and click "Next".



12.	Now the "Installation Settings" page is displayed. De "disable" button located behind "Firewall will be en	



# Installation Settings

Click a headline to make changes.

## Software

- Product: SUSE Linux Enterprise Server
- Product: Basesystem Module
- Product: Server Applications Module
- Product: SUSE Enterprise Storage 6
- Patterns:
  - Minimal Base System
- Size of Packages to Install: 1.3 GiB
- Downloading from Remote Repositorie

## **Booting**

- Boot Loader Type: GRUB2
- Enable Trusted Boot: no
- Status Location: /dev/vda (MBR)
- Change Location:
  - Install bootcode into MBR (do n
  - Do not install boot code into a r
- Order of Hard Disks: /dev/vda, /dev/vdi

# <u>Security</u>

- CPU Mitigations: Auto
- Firewall will be disabled (enable)
- SSH service will be enabled (disable)

# **Network Configuration**

- Configured with DHCP: eth0
- Hostname: Set by DHCP

#### Kdump

- Kdump status: enabled
- Value(s) of crashkernel option: 166M,h
- Dump format: Izo
- Target of dumps: /var/crash
- Number of dumps: 5

13. To finalize the installation, go to "Extension and Module

FIGURE 14: SLES SETUP INSTALLATION SETTINGS PAGE

Help

Release Notes...



# Extension and Module Selection

#### Available Extensions and Modules

- SUSE CaaS Platform 4.0 x86\_64
- SUSE Enterprise Storage 6 x86\_64
- SUSE Linux Enterprise High Availability Ext
- SUSE Linux Enterprise Live Patching 15 SP
- SUSE Linux Enterprise Workstation Extensi
  SUSE Package Hub 15 SP1 x86\_64
- ☑ Basesystem Module 15 SP1 x86\_64
- Containers Module 15 SP1 x86\_64
- Desktop Applications Module 15 SP1 x86\_i
- Development Tools Module 15 SP1 x86\_64
- Legacy Module 15 SP1 x86\_64
- Public Cloud Module 15 SP1 x86\_64
- Python 2 Module 15 SP1 x86\_64
- SUSE Cloud Application Platform Tools Mo

Details (English only)

SUSE Enterprise Storage 6 for SUSE Linux Ente

Help

Set up at least four machines the same way.

# 5.3 Setting up SUSE Enterprise Storage

Check that your machines have the correct host names:

```
# hostname -f
```

This should output the FQDN of the machine. If this is not the case, you can use the following command to set the name:

```
# hostnamectl --set-hostname <FQDN>
```

For the document at hand, we use the following machine names:

- admin.example.com
- mon1.example.com
- mon2.example.com
- mon3.example.com

To ensure that DNS resolution for these names works properly, you should edit the <a href=//etc/hosts file on the nodes as follows:</a>

```
127.0.0.1 localhost

<Admin-IP> admin.example.com admin

<Mon1-IP> mon1.example.com mon1

<Mon2-IP> mon2.example.com mon2

<Mon3-IP> mon3.example.com mon3
```

If you do not know the IP address of a machine, run:

```
$ ip a
```

# .00PBA: < link/loopb inet 127. valid eth0@if9: link/ether inet 172.1

FIGURE 16: FETCH IP

# 5.3.1 Preparing the nodes

1. On the OSD Nodes, install salt-minion and deepsea:

```
# zypper in -y salt-minion deepsea
```

2. On the Admin Node, install salt-minion, salt-master, and deepsea:

```
# zypper in -y salt-minion salt-master deepsea
```

3. Set the Salt master on all machines by editing the associated line:

```
# echo "master: admin.example.com" > /etc/salt/minion
```

4. On the Admin node, enable the salt-master service:

```
# systemctl enable salt-master --now
```

**5.** Enable the salt-minion service on all nodes:

```
# systemctl enable salt-minion --now
```

**6.** Now accept the Salt keys on the admin node:

```
# salt-key --accept-all -y
```



# Tip

To check the keys, use the command <u>salt-key -L</u>. This should output something like:

```
Admin:~ # salt-key -L
Accepted Keys:
admin.example.com
mon1.example.com
mon2.example.com
mon3.example.com
Denied Keys:
Unaccepted Keys:
Rejected Keys:
```

FIGURE 17: SALT KEYS

7. Make all nodes DeepSea minions:

```
# echo "deepsea_minions: '*'" > /srv/pillar/ceph/deepsea_minions.sls
```

8. Synchronize your Salt minions:

```
# salt '*' saltutil.sync_all
```

9. Make sure your desired disks are all cleared. To this end, you can use:

```
# wipefs -a /dev/vdb
```



# Note

Be aware that you might need to change the device (vdb) here. Ensure you clear all disks on all nodes.

10. Apply the cleared disks by using:

```
# salt '*' state.apply ceph.subvolume
```

# 5.3.2 Deploying the cluster



# Tip

You can watch the progress of the Ceph stages in a separate terminal with the command deepsea monitor.

Now you can run the first stage of deploying the Ceph cluster.

1. First, prepare the cluster:

```
# salt-run state.orch ceph.stage.prep
```

2. The result for the preparation stage should look similar to this:

```
[1/17]
[2/17]
[3/17]
[4/17]
[5/17]
[6/17]
[7/17]
[8/17]
[10/17]
[11/17]
[12/17]
[13/17]
[14/17]
Γ16/171
[17/17]
```

FIGURE 18: CLUSTER DEPLOYMENT - PREPARATION

**3**. The next stage is collecting information about the nodes:

```
# salt-run state.orch ceph.stage.discovery
```

```
Parsing orchestration ceph.stage.discovery steps... 

Parsing ceph.stage.discovery steps... 

[1/3] minions.ready(timeout=300)... 

(0.4s) 

(2/3] ceph.refresh on admin.example.com... 

(0.5s) 

(3/3] populate.proposals... 

(5s) 

Ended stage: ceph.stage.discovery succeeded=3/3 time=12.7s
```

FIGURE 19: CLUSTER DEPLOYMENT - STAGE 1

4. Before you can run the last three stages, you must provide a role configuration for the nodes. This will be stored in /srv/pillar/ceph/proposals/policy.cfg. This example uses the following configuration:

```
#General config
config/stack/default/global.yml
config/stack/default/ceph/cluster.yml
#CEPH Cluster members
cluster-ceph/cluster/admin.example.com.sls
cluster-ceph/cluster/mon1.example.com.sls
cluster-ceph/cluster/mon2.example.com.sls
cluster-ceph/cluster/mon3.example.com.sls
#CEPH Admin nodes
role-admin/cluster/mon1.example.com.sls
role-admin/cluster/mon2.example.com.sls
role-admin/cluster/mon3.example.com.sls
#CEPH Master node
role-master/cluster/admin.example.com.sls
#CEPH Manager nodes
role-mgr/cluster/mon1.example.com.sls
role-mgr/cluster/mon2.example.com.sls
role-mgr/cluster/mon3.example.com.sls
#CEPH Monitor nodes
role-mon/cluster/mon1.example.com.sls
role-mon/cluster/mon2.example.com.sls
role-mon/cluster/mon3.example.com.sls
```

```
#CEPH RGW nodes
role-rgw/cluster/admin.example.com.sls
role-rgw/cluster/mon1.example.com.sls
role-rgw/cluster/mon2.example.com.sls
role-rgw/cluster/mon3.example.com.sls

#CEPH Storage nodes
role-storage/cluster/admin.example.com.sls
role-storage/cluster/mon1.example.com.sls
role-storage/cluster/mon2.example.com.sls
role-storage/cluster/mon3.example.com.sls
```

5. You can now safely deploy your configuration:

```
# salt-run state.orch ceph.stage.configure
```

```
Stage initialization output:
deepsea_minions : valid
yaml_syntax : valid
[1/15]

        ceph.refresh on
        / (2s)

        mon1.example.com.
        / (1s)

        admin.example.com.
        / (1s)

        mon2.example.com.
        / (1s)

        mon3.example.com.
        / (2s)

[2/15]
[3/15]

    ceph.packages on
    v (53s)

    mon1.example.com
    v (34s)

    admin.example.com
    v (34s)

    mon2.example.com
    v (58s)

    mon3.example.com
    v (57s)

[4/15]
[5/15]
[6/15]
               ceph.mon.key on admin.example.com. ✓ (0.4s)
[7/15]
Γ8/15T
[9/15]
[10/15]
[11/15]
[12/15]
[13/15]
[14/15]
[15/15]
```

FIGURE 20: CLUSTER DEPLOYMENT - STAGE 2

6. Deploy your configuration to the cluster:

```
# salt-run state.orch ceph.stage.deploy
```

```
output:

: not installed

: disabled

: valid

: valid
public_network
public_interface
cluster_network
cluster_interface
ip_version
monitors
subvolume
mgrs
storage
storage_role
rgw
ganesha
master_role
time_server
fqdn
[1/51]
           ceph.configuration.check on admin.example.com...... ✓ (0.3s)
[2/51]
[3/51]
             ceph.configuration on
mon3.example.com.
admin.example.com.
mon2.example.com.
mon1.example.com.
[4/51]
             ceph.monitoring.prometheus.exporters.mgr_exporter on
admin.example.com.....
[50/51]
              ceph.monitoring.prometheus.exporters.rbd_exporter on
admin.example.com......
[51/51]
```

FIGURE 21: CLUSTER DEPLOYMENT - STAGE 3

7. When the deployment stage has been successfully passed, check the cluster health to insure that all is running properly.

```
# ceph -s
```

FIGURE 22: CHECKING CLUSTER HEALTH

**8.** The last stage to run is deploying the service roles, which were specified in the <a href="mailto:policy.cfg">policy.cfg</a> file:

```
# salt-run state.orch ceph.stage.services
```

```
Stage initialization output:
No minions matched the target. No command was sent, no jid was assigned.
kernel_module : valid
openattic-disabled : valid
[2/17]
[3/17]
[4/17]
[5/17]
[6/17]
[7/17]
[8/17]
[9/17]
              ceph.rgw.restart on
mon1.example.com....
[11/17]
[12/17]
[13/17]
[14/17]
[15/17]
[16/17]
[17/17]
```

FIGURE 23: CLUSTER DEPLOYMENT - STAGE 4

# 5.4 Access the dashboard and create a new pool

After the Ceph cluster is up and running, you must create a pool for SAP Data Intelligence 3.

In our example, we will use the dashboard for this purpose.

1. The dashboard is published by any of the monitor nodes. To access it, use a Web browser:




FIGURE 24: CLUSTER DASHBOARD

Get the credentials to log in by running the following command on the Admin Node:

```
# salt-call grains.get dashboard_creds
```

```
Admin:~ # salt-call grains.get dashboard_creds
local:
-----
admin:
G1WBCQApXG
```

FIGURE 25: CLUSTER DASHBOARD LOGIN

After logging in, the landing page should appear.

2. Select the "Pools" tab at the top of the page:




FIGURE 26: CLUSTER DASHBOARD LANDING PAGE

The Pools page gives an overview of the currently defined pools.

3. Click the "Create" button at the top of the table to create a new pool:




FIGURE 27: CLUSTER DASHBOARD POOLS

- 4. Enter the name of the pool. As "Pool type", select replicated.
- 5. On the left side of "Applications", click the pencil symbol and select rbd.
- 6. Confirm the creation of the pool by clicking the "CreatePool" button at the bottom.




FIGURE 28: CLUSTER DASHBOARD CREATING POOLS



# **Important**

Make note of the name of the pool. It will be needed in Section 6.4.1.2, "Creating Storage Class".

7. After this, the pools page is displayed again, and the newly created pool is shown in the table of pools.




FIGURE 29: CLUSTER DASHBOARD NEW POOL

8. Now provide access to this pool through an RBD device. Go to the RDB overview page by selecting "Block→Images"




FIGURE 30: CLUSTER DASHBOARD ACCESSING POOL

An overview of the configured RDBs is displayed.

9. Click the Create button.



FIGURE 31: CLUSTER DASHBOARD RDB OVERVIEW

**10.** Enter the name, and if it is not already selected, select the previously created pool. Select the size of the RBD and confirm the creation by clicking the "CreateRBD" button.




FIGURE 32: CLUSTER DASHBOARD CREATING NEW RDB

The overview page of the RBDs is shown again. It now contains your newly created RBD.



FIGURE 33: CLUSTER DASHBOARD RDB UPDATED OVERVIEW

At this point, the SUSE Enterprise Storage cluster is ready for usage with SAP Data Intelligence.

# 6 Installing SAP Data Intelligence 3 on top of SUSE CaaSP 4.2

## 6.1 Documentation

- SAP Notes:
  - Release Notes for SAP Data Intelligence 3 (https://launchpad.support.sap.com/#/notes/2871970) 

    ✓
  - Installation Guide for SAP Data Intelligence 3 (https://help.sap.com/view-er/a8d90a56d61a49718ebcb5f65014bbe7/3.0.latest/en-US) ▶

# 6.2 Planning the installation with the SAP Maintenance Planner

For the installation of SAP Data Intelligence, you should start here: SAP Maintenance Planner (https://support.sap.com/en/alm/solution-manager/processes-72/maintenance-planner.html) ▶



#### Note

You need to have your SAP S-User available.

• The landing page of the SAP Maintenance Planner looks as follows:




FIGURE 34: SAP MAINTENANCE PLANNER START PAGE

Click "Plan a New System" on the right.

• The next page displayed looks as follows:




FIGURE 35: SAP MAINTENANCE PLANNER: SELECT PLAN

You will see a circle where all options except the option "Plan" are greyed out. Click the "Plan" option.

• The next page shows the "Define Change" step of your planning:




FIGURE 36: SAP MAINTENANCE PLANNER: SELECT CONTAINER BASED PRODUCT

• On the left, there is a window with three toggle buttons. Select "CONTAINER BASED" and click "OK":




FIGURE 37: SAP MAINTENANCE PLANNER: SELECT CONTAINER BASED PRODUCT #2

• To the right, the option "SAP DATA INTELLIGENCE" should appear. When you select it, a sub-selection should open with choices for "SAP DATA INTELLIGENCE 3" and "SAP DATA HUB 2". Select "SAP DATA INTELLIGENCE 3":




FIGURE 38: SAP MAINTENANCE PLANNER: SELECT DATA INTELLIGENCE 3

 A pop-up window will appear to inform you about the related SAP note. Click "Continue" to proceed:




FIGURE 39: SAP MAINTENANCE PLANNER: SELECT CONTINUE

• On the right hand side, a drop-down box is shown with "Select Support Package Stack". Click this, and select from the available patch levels as needed:




FIGURE 40: SAP MAINTENANCE PLANNER: SELECT FROM AVAILABLE PATCH LEVELS AS YOU NEED.

• To the left, the sub-selection for "SAP DATA INTELLIGENCE 3" will need changes. Select what you need and click the "Confirm Selection" at the very right:




FIGURE 41: SAP MAINTENANCE PLANNER: SELECT ACCORDING YOUR NEEDS AND CONFIRM.

• An overview of your selection is shown. If this fits your needs, click the "Next" button at the upper right corner:




FIGURE 42: SAP MAINTENANCE PLANNER: SELECT NEXT IF SATISFIED

• Next, select the operating system upon which SAP Data Intelligence will be installed. Select "Linux on x86\_64 64bit" and click "Confirm Selection":




FIGURE 43: SAP MAINTENANCE PLANNER: SELECT LINUX AND CONFIRM

• The next page shows the preselected files to use and download. Again, click the "Next" button on the upper right:




FIGURE 44: SAP MAINTENANCE PLANNER: CONFIRM

• You should now arrive at the "Download Files" page. The required **SLC bridge** is already preselected. Click "Next" to proceed:




FIGURE 45: SAP MAINTENANCE PLANNER: EXECUTE PLAN

• Your maintenance plan is shown as PDF. Confirm everything by clicking the "Execute Plan" button on the upper right side:



FIGURE 46: SAP MAINTENANCE PLANNER: DOWNLOAD STACK.XML AND SLC BRIDGE INSTALLER

• Download the **SLC Bridge Installer** and copy it to your management workstation. You will need this file in *Section 6.3, "Installing the SAP SLC Bridge"*.

• You will be prompted to enter the FQDN and the port of the machine your SLC bridge will run on:




FIGURE 47: SAP MAINTENANCE PLANNER: ENTER FQDN OF HOST WHERE THE SLC BRIDGE WILL RUN

• Fill in the values. An example looks as follows:




FIGURE 48: SAP MAINTENANCE PLANNER: EXAMPLE FOR HOST AND PORT

# 6.3 Installing the SAP SLC Bridge

- Download the file containing the SLC Bridge Installer.
- If you have not already done so, copy this file to the management workstation.
- Run the **SLC Bridge Installer** on the management workstation.
  - \$ ./SLCB01\_<YOUR DOWNLOADED VERSION>.EXE init

```
Actibities Different States St
```

FIGURE 49: SAP SLC BRIDGE INSTALLER

• This interactive script gathers all the necessary information to run the SAP SLC Bridge, and at the end, deploys it into the CaaSP cluster.




FIGURE 50: SAP SLC BRIDGE INFORMATION

• Identify the service port for the SLC Bridge:

```
# kubectl -n sap-slcbridge get pods
                                READY
                                                            AGE
NAME
                                        STATUS
                                                 RESTARTS
di-platform-full-product-bridge
                                2/2
                                        Running 0
                                                            3d23h
slcbridgebase-858f895bd6-74gps
                                                            10d
                                2/2
                                        Running 1
# kubectl -n sap-slcbridge get svc
NAME
                                        TYPE
                                                    CLUSTER-IP
                                                                  EXTERNAL-IP
PORT(S)
                 AGE
di-platform-full-product-bridge-service
                                        ClusterIP
                                                    10.101.2.224
                                                                  <none>
9000/TCP
                 3d23h
                                                    10.97.79.26
slcbridgebase-service
                                        NodePort
                                                                  <none>
9000:30778/TCP 10d
```

In our example, the port number on which the SLC Bridge listens is 30778.

 Make a note of this information. It is needed for the installation process via SAP Maintenance Planner.

```
Execute step Mait for Kubernetes Object MasterSecret

Execute step Mait for Kubernetes Object MasterSecret

Execute step Mait for Kubernetes Object MginuSecret

Execute step Mait for Kubernet
```

FIGURE 51: SAP SLC BRIDGE

# 6.4 Installing SAP Data Intelligence 3

This section describes the installation of SAP Data Intelligence 3 on top of SUSE CaaSP 4.2.

# 6.4.1 Preparations

Before the installation of SAP DI 3 can start, some preparation work must be done:

- Create a namespace on the Kubernetes cluster.
- Define a (default) storage class on the Kubernetes cluster.
- Adapt PodSecurityPolicies.
- Create the necessary ClusterRoleBindings.
- If you use self-signed certificates for the private registry, a special secret must be created.



#### Note

Unless otherwise specified, all these tasks are run from the management workstation.

#### 6.4.1.1 Creating namespace for SAP Data Intelligence 3 on Kubernetes

Define the namespace into which SAP Data Intelligence 3 will be installed:

```
$ kubectl create namespace <YOUR NAMESPACE>
```

## 6.4.1.2 Creating Storage Class

- Create the storage class to provide volumes for SAP Data Intelligence 3 on SUSE Enterprise Storage.
- Make sure that you have:
  - the connection data for your SUSE Enterprise Storage at hand
  - the IP addresses and port number (default: 6789) of the monitor nodes of your SES cluster
  - created a data pool on your SES cluster for use with SAP Data Intelligence 3
  - the name of this pool (datahub in this example) available
- Edit the example below to fit your environment.

```
$ cat > storageClass.yaml <<EOF</pre>
apiVersion: storage.kubernetes.io/v1
kind: StorageClass
metadata:
 annotations:
    storageclass.kubernetes.io/is-default-class: "true"
 name: datahub
 namespace: default
parameters:
 adminId: admin
 adminSecretName: ceph-admin-secret
 adminSecretNamespace: default
 imageFeatures: layering
 imageFormat: "2"
 monitors: <IP ADDRESS OF MONITOR 1>:6789, <IP ADDRESS OF MONITOR 2>:6789, <IP
ADDRESS OF MONITOR 3 >:6789
  pool: datahub
 userId: admin
 userSecretName: ceph-user-secret
provisioner: kubernetes.io/rbd
reclaimPolicy: Delete
```

```
volumeBindingMode: Immediate
EOF

$ kubectl create -f storageClass.yaml
```

- Create secrets for the StorageClass.
  - Create the secrets needed to access the storage.
  - Obtain the keys from your SES cluster. These are located in ceph.admin.keyring and ceph.user.keyring.

You must encode the keys with base64.

key: <YOUR BASE64 ENCODED KEY HERE>

\$ kubectl apply -f ceph-admin-secret.yaml
\$ kubectl apply -f ceph-user-secret.yaml

E0F

```
$ echo <YOUR KEY HERE> | base64
$ cat > ceph-admin-secret.yaml <<EOF</pre>
apiVersion: v1
kind: Secret
metadata:
    name: ceph-admin-secret
type: "kubernetes.io/rbd"
data:
   key: <YOUR BASE64 ENCODED KEY HERE>
E0F
$ cat > ceph-user-secret.yaml <<EOF</pre>
apiVersion: v1
kind: Secret
metadata:
   name: ceph-user-secret
type: "kubernetes.io/rbd"
```

• Create the credentials for accessing the StorageClass from the namespace where DI 3 will be installed into.

```
$ kubectl -n <YOUR NAMESPACE FOR DI 3> create -f ceph-admin-secret.yaml
$ kubectl -n <YOUR NAMESPACE FOR DI 3> create -f ceph-user-secret.yaml
```

#### 6.4.1.3 Creating PodSecurityPolicies and ClusterRoleBindings

PodSecurityPolicies

```
$ kubectl edit psp suse.caasp.psp.privileged
```

# Change the pathPrefix in allowedHostPaths to /

ClusterRoleBindings

```
$ cat > clusterrolebinding.yaml << EOF</pre>
apiVersion: rbac.authorization.k8s.io/v1
kind: ClusterRoleBinding
metadata:
 name: suse:caasp:psp:privileged:default
roleRef:
 apiGroup: rbac.authorization.k8s.io
 kind: ClusterRole
 name: suse:caasp:psp:privileged
subjects:
- kind: ServiceAccount
 name: default
 namespace: XXX
- kind: ServiceAccount
 name: vora-vsystem-XXX
 namespace: XXX
- kind: ServiceAccount
 name: vora-vsystem-XXX-vrep
 namespace: XXX
- kind: ServiceAccount
 name: XXX-elasticsearch
 namespace: XXX
- kind: ServiceAccount
 name: XXX-fluentd
 namespace: XXX
- kind: ServiceAccount
 name: XXX-nodeexporter
 namespace: XXX
- kind: ServiceAccount
 name: vora-vflow-server
 namespace: XXX
- kind: ServiceAccount
 name: mlf-deployment-api
 namespace: XXX
E0F
$ sed -i s/XXX/<your-di-namespace>/g clusterrolebinding.yaml
$ kubectl apply -f clusterrolebinding.yaml
```

Additional changes

```
$ kubectl edit clusterrolebinding system:node
```

Insert the following at the end of the file:

```
subjects:
- apiGroup: rbac.authorization.k8s.io
kind: Group
name: system:nodes
```

 If you use self-signed SSL certificates for the secure private registry, create a secret for accessing this registry.



### Note

The certificate chain should be saved in pem format into a single file called cert.

```
export NAMESPACE=<your namespace>
mv cert cert_with_carriage_return
tr -d '\r' < cert_with_carriage_return > cert
kubectl create secret generic cmcertificates --from-file=cert -n $NAMESPACE
```

### 6.4.2 Installing SAP Data Intelligence 3

After you successfully finished the preparation stages, proceed with the installation of SAP Data Intelligence 3. To do so, several steps must be executed.

### 6.4.2.1 Connecting to the SLC Bridge

- Point your browser to the SLC Bridge service:
  - https://<yournode>:<yourport>/docs/index.html
- Fill in your credentials you created during the deployment of the SLC Bridge.

### 6.4.2.2 Installing the workflow

• Connect and authenticate to the SLC Bridge service created above. Use the credentials created during the setup of the SLC Bridge:




FIGURE 52: CONNECT AND AUTHENTICATE TO THE SLCB SERVICE

• Select "Planned software Changes":




FIGURE 53: INSTALLING PLANNED SOFTWARE CHANGES

• Select the SAP Data Intelligence deployment required by your needs. Click "Next":




FIGURE 54: INSTALLING THE REQUIRED SAP DI DEPLOYMENT

• Enter the Kubernetes namespace created beforehand, for example di310. Click "Next":




FIGURE 55: INSTALLING PRE-REQUISITES CHECK




FIGURE 56: INSTALLATION ENTER KUBERNETES NAMESPACE

• Select "Advanced Installation":




FIGURE 57: INSTALLING ADVANCED INSTALLATION

• Enter the URI of your Private secure registry. Click "Next":




FIGURE 58: INSTALLING PRIVATE CONTAINER REGISTRY

• Enter a password for the system tenant in SAP DI 3.0:




FIGURE 59: ENTER SYSTEM TENANT PASSWORD

• Assign a name to the initially created tenant, for example "default":




FIGURE 60: ASSIGN A NAME TO CREATED DEFAULT TENANT

• Create the administrator user for the default tenant in SAP DI 3.0:




FIGURE 61: CREATE ADMIN USER NAME OF DEFAULT TENANT

• Set the password for the administrator user of the default tenant:




FIGURE 62: SET ADMIN USER PASSWORD

• If you need a proxy to connect to the Internet, set the proxy settings accordingly:




FIGURE 63: SET PROXY SETTINGS

• Select if you want to use a checkpoint storage:




FIGURE 64: CONFIGURE CHECKPOINT STORAGE

• Define the storage class that should be used by SAP DI 3.0. Enter the name of the storage class you created previously:




FIGURE 65: DEFINE STORAGE CLASS TO BE USED

• For the SAP DI 3 installation on SUSE CaaSP 4.2 the docker log path needs to be adapted. Check the check box and click "Next":




FIGURE 66: ADAPT DOCKER LOG PATH

• Enter the docker log path: "/var/log/containers"




FIGURE 67: ENTER DOCKER LOG PATH

#### • Enable Kaniko:




FIGURE 68: ENABLE KANIKO

• Here, a different private registry can be configured if needed. To proceed, click "Next":




FIGURE 69: CONFIGURE DOCKER REGISTRY FOR SAP DI MODELER IMAGES

• Enable the loading of NFS kernel modules. This ensures that the NFS kernel modules are loaded on all Kubernetes nodes. Check the check box and click "Next":




FIGURE 70: LOADING NFS KERNEL MODULES

• If needed, enable Network policies. Click "Next":




FIGURE 71: ENABLE NETWORK POLICIES

• Configure timeout during installation, leave the default and click "Next":




FIGURE 72: CONFIGURING TIMEOUT DURING INSTALLATION OF SAP DI 3

- In the field "Additional Installation Parameters", enter:
  - -e diagnostic.fluentd.logDriverFormat=regexp -e vsystem.vRep.exportsMask=true




FIGURE 73: ADDITIONAL INSTALLATION PARAMETERS 1




FIGURE 74: ADDITIONAL INSTALLATION PARAMETERS 2

• Check the Summary page. Check if the settings are correct:




FIGURE 75: SUMMARY OF INSTALLATION PARAMETERS

• Click "Next" to start the deployment of SAP DI 3.0.

Your installation should now be finished.

# 7 Legal notice

Copyright © 2006–2025 SUSE LLC and contributors. All rights reserved.

Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.2 or (at your option) version 1.3; with the Invariant Section being this copyright notice and license. A copy of the license version 1.2 is included in the section entitled "GNU Free Documentation License".

SUSE, the SUSE logo and YaST are registered trademarks of SUSE LLC in the United States and other countries. For SUSE trademarks, see https://www.suse.com/company/legal/ ♂.

Linux is a registered trademark of Linus Torvalds. All other names or trademarks mentioned in this document may be trademarks or registered trademarks of their respective owners.

Documents published as part of the SUSE Best Practices series have been contributed voluntarily by SUSE employees and third parties. They are meant to serve as examples of how particular actions can be performed. They have been compiled with utmost attention to detail. However, this does not guarantee complete accuracy. SUSE cannot verify that actions described in these documents do what is claimed or whether actions described have unintended consequences. SUSE LLC, its affiliates, the authors, and the translators may not be held liable for possible errors or the consequences thereof.

Below we draw your attention to the license under which the articles are published.

### 8 GNU Free Documentation License

Copyright © 2000, 2001, 2002 Free Software Foundation, Inc. 51 Franklin St, Fifth Floor, Boston, MA 02110-1301 USA. Everyone is permitted to copy and distribute verbatim copies of this license document, but changing it is not allowed.

#### 0. PREAMBLE

The purpose of this License is to make a manual, textbook, or other functional and useful document "free" in the sense of freedom: to assure everyone the effective freedom to copy and redistribute it, with or without modifying it, either commercially or noncommercially. Secondarily, this License preserves for the author and publisher a way to get credit for their work, while not being considered responsible for modifications made by others.

This License is a kind of "copyleft", which means that derivative works of the document must themselves be free in the same sense. It complements the GNU General Public License, which is a copyleft license designed for free software.

We have designed this License in order to use it for manuals for free software, because free software needs free documentation: a free program should come with manuals providing the same freedoms that the software does. But this License is not limited to software manuals; it can be used for any textual work, regardless of subject matter or whether it is published as a printed book. We recommend this License principally for works whose purpose is instruction or reference.

#### 1. APPLICABILITY AND DEFINITIONS

This License applies to any manual or other work, in any medium, that contains a notice placed by the copyright holder saying it can be distributed under the terms of this License. Such a notice grants a world-wide, royalty-free license, unlimited in duration, to use that work under the conditions stated herein. The "Document", below, refers to any such manual or work. Any member of the public is a licensee, and is addressed as "you". You accept the license if you copy, modify or distribute the work in a way requiring permission under copyright law.

A "Modified Version" of the Document means any work containing the Document or a portion of it, either copied verbatim, or with modifications and/or translated into another language.

A "Secondary Section" is a named appendix or a front-matter section of the Document that deals exclusively with the relationship of the publishers or authors of the Document to the Document's overall subject (or to related matters) and contains nothing that could fall directly within that overall subject. (Thus, if the Document is in part a textbook of mathematics, a Secondary Section may not explain any mathematics.) The relationship could be a matter of historical connection with the subject or with related matters, or of legal, commercial, philosophical, ethical or political position regarding them.

The "Invariant Sections" are certain Secondary Sections whose titles are designated, as being those of Invariant Sections, in the notice that says that the Document is released under this License. If a section does not fit the above definition of Secondary then it is not allowed to be designated as Invariant. The Document may contain zero Invariant Sections. If the Document does not identify any Invariant Sections then there are none.

The "Cover Texts" are certain short passages of text that are listed, as Front-Cover Texts or Back-Cover Texts, in the notice that says that the Document is released under this License. A Front-Cover Text may be at most 5 words, and a Back-Cover Text may be at most 25 words.

A "Transparent" copy of the Document means a machine-readable copy, represented in a format whose specification is available to the general public, that is suitable for revising the document straightforwardly with generic text editors or (for images composed of pixels) generic paint programs or (for drawings) some widely available drawing editor, and that is suitable for input to text formatters or for automatic translation to a variety of formats suitable for input to text formatters. A copy made in an otherwise Transparent file format whose markup, or absence of markup, has been arranged to thwart or discourage subsequent modification by readers is not Transparent. An image format is not Transparent if used for any substantial amount of text. A copy that is not "Transparent" is called "Opaque".

Examples of suitable formats for Transparent copies include plain ASCII without markup, Texinfo input format, LaTeX input format, SGML or XML using a publicly available DTD, and standard-conforming simple HTML, PostScript or PDF designed for human modification. Examples of transparent image formats include PNG, XCF and JPG. Opaque formats include proprietary formats that can be read and edited only by proprietary word processors, SGML or XML for which the DTD and/or processing tools are not generally available, and the machine-generated HTML, PostScript or PDF produced by some word processors for output purposes only.

The "Title Page" means, for a printed book, the title page itself, plus such following pages as are needed to hold, legibly, the material this License requires to appear in the title page. For works in formats which do not have any title page as such, "Title Page" means the text near the most prominent appearance of the work's title, preceding the beginning of the body of the text.

A section "Entitled XYZ" means a named subunit of the Document whose title either is precisely XYZ or contains XYZ in parentheses following text that translates XYZ in another language. (Here XYZ stands for a specific section name mentioned below, such as "Acknowledgements", "Dedications", "Endorsements", or "History".) To "Preserve the Title" of such a section when you modify the Document means that it remains a section "Entitled XYZ" according to this definition. The Document may include Warranty Disclaimers next to the notice which states that this License applies to the Document. These Warranty Disclaimers are considered to be included by reference in this License, but only as regards disclaiming warranties: any other implication that these Warranty Disclaimers may have is void and has no effect on the meaning of this License.

#### 2. VERBATIM COPYING

You may copy and distribute the Document in any medium, either commercially or noncommercially, provided that this License, the copyright notices, and the license notice saying this License applies to the Document are reproduced in all copies, and that you add no other conditions whatsoever to those of this License. You may not use technical measures to obstruct or control the reading or further copying of the copies you make or distribute. However, you may accept compensation in exchange for copies. If you distribute a large enough number of copies you must also follow the conditions in section 3.

You may also lend copies, under the same conditions stated above, and you may publicly display copies.

### 3. COPYING IN QUANTITY

If you publish printed copies (or copies in media that commonly have printed covers) of the Document, numbering more than 100, and the Document's license notice requires Cover Texts, you must enclose the copies in covers that carry, clearly and legibly, all these Cover Texts: Front-Cover Texts on the front cover, and Back-Cover Texts on the back cover. Both covers must also clearly and legibly identify you as the publisher of these copies. The front cover must present the full title with all words of the title equally prominent and visible. You may add other material on the covers in addition. Copying with changes limited to the covers, as long as they preserve the title of the Document and satisfy these conditions, can be treated as verbatim copying in other respects.

If the required texts for either cover are too voluminous to fit legibly, you should put the first ones listed (as many as fit reasonably) on the actual cover, and continue the rest onto adjacent pages.

If you publish or distribute Opaque copies of the Document numbering more than 100, you must either include a machine-readable Transparent copy along with each Opaque copy, or state in or with each Opaque copy a computer-network location from which the general network-using public has access to download using public-standard network protocols a complete Transparent copy of the Document, free of added material. If you use the latter option, you must take reasonably prudent steps, when you begin distribution of Opaque copies in quantity, to ensure that this Transparent copy will remain thus accessible at the stated location until at least one year after the last time you distribute an Opaque copy (directly or through your agents or retailers) of that edition to the public.

It is requested, but not required, that you contact the authors of the Document well before redistributing any large number of copies, to give them a chance to provide you with an updated version of the Document.

### 4. MODIFICATIONS

You may copy and distribute a Modified Version of the Document under the conditions of sections 2 and 3 above, provided that you release the Modified Version under precisely this License, with the Modified Version filling the role of the Document, thus licensing distribution and modification of the Modified Version to whoever possesses a copy of it. In addition, you must do these things in the Modified Version:

- A. Use in the Title Page (and on the covers, if any) a title distinct from that of the Document, and from those of previous versions (which should, if there were any, be listed in the History section of the Document). You may use the same title as a previous version if the original publisher of that version gives permission.
- B. List on the Title Page, as authors, one or more persons or entities responsible for authorship of the modifications in the Modified Version, together with at least five of the principal authors of the Document (all of its principal authors, if it has fewer than five), unless they release you from this requirement.
- C. State on the Title page the name of the publisher of the Modified Version, as the publisher.
- D. Preserve all the copyright notices of the Document.

- E. Add an appropriate copyright notice for your modifications adjacent to the other copyright notices.
- F. Include, immediately after the copyright notices, a license notice giving the public permission to use the Modified Version under the terms of this License, in the form shown in the Addendum below.
- **G.** Preserve in that license notice the full lists of Invariant Sections and required Cover Texts given in the Document's license notice.
- H. Include an unaltered copy of this License.
- I. Preserve the section Entitled "History", Preserve its Title, and add to it an item stating at least the title, year, new authors, and publisher of the Modified Version as given on the Title Page. If there is no section Entitled "History" in the Document, create one stating the title, year, authors, and publisher of the Document as given on its Title Page, then add an item describing the Modified Version as stated in the previous sentence.
- J. Preserve the network location, if any, given in the Document for public access to a Transparent copy of the Document, and likewise the network locations given in the Document for previous versions it was based on. These may be placed in the "History" section. You may omit a network location for a work that was published at least four years before the Document itself, or if the original publisher of the version it refers to gives permission.
- K. For any section Entitled "Acknowledgements" or "Dedications", Preserve the Title of the section, and preserve in the section all the substance and tone of each of the contributor acknowledgements and/or dedications given therein.
- L. Preserve all the Invariant Sections of the Document, unaltered in their text and in their titles. Section numbers or the equivalent are not considered part of the section titles.
- M. Delete any section Entitled "Endorsements". Such a section may not be included in the Modified Version.
- N. Do not retitle any existing section to be Entitled "Endorsements" or to conflict in title with any Invariant Section.
- O. Preserve any Warranty Disclaimers.

If the Modified Version includes new front-matter sections or appendices that qualify as Secondary Sections and contain no material copied from the Document, you may at your option designate some or all of these sections as invariant. To do this, add their titles to the list of Invariant Sections in the Modified Version's license notice. These titles must be distinct from any other section titles.

You may add a section Entitled "Endorsements", provided it contains nothing but endorsements of your Modified Version by various parties—for example, statements of peer review or that the text has been approved by an organization as the authoritative definition of a standard.

You may add a passage of up to five words as a Front-Cover Text, and a passage of up to 25 words as a Back-Cover Text, to the end of the list of Cover Texts in the Modified Version. Only one passage of Front-Cover Text and one of Back-Cover Text may be added by (or through arrangements made by) any one entity. If the Document already includes a cover text for the same cover, previously added by you or by arrangement made by the same entity you are acting on behalf of, you may not add another; but you may replace the old one, on explicit permission from the previous publisher that added the old one.

The author(s) and publisher(s) of the Document do not by this License give permission to use their names for publicity for or to assert or imply endorsement of any Modified Version.

### 5. COMBINING DOCUMENTS

You may combine the Document with other documents released under this License, under the terms defined in section 4 above for modified versions, provided that you include in the combination all of the Invariant Sections of all of the original documents, unmodified, and list them all as Invariant Sections of your combined work in its license notice, and that you preserve all their Warranty Disclaimers.

The combined work need only contain one copy of this License, and multiple identical Invariant Sections may be replaced with a single copy. If there are multiple Invariant Sections with the same name but different contents, make the title of each such section unique by adding at the end of it, in parentheses, the name of the original author or publisher of that section if known, or else a unique number. Make the same adjustment to the section titles in the list of Invariant Sections in the license notice of the combined work.

In the combination, you must combine any sections Entitled "History" in the various original documents, forming one section Entitled "History"; likewise combine any sections Entitled "Acknowledgements", and any sections Entitled "Dedications". You must delete all sections Entitled "Endorsements".

### 6. COLLECTIONS OF DOCUMENTS

You may make a collection consisting of the Document and other documents released under this License, and replace the individual copies of this License in the various documents with a single copy that is included in the collection, provided that you follow the rules of this License for verbatim copying of each of the documents in all other respects.

You may extract a single document from such a collection, and distribute it individually under this License, provided you insert a copy of this License into the extracted document, and follow this License in all other respects regarding verbatim copying of that document.

### 7. AGGREGATION WITH INDEPENDENT WORKS

A compilation of the Document or its derivatives with other separate and independent documents or works, in or on a volume of a storage or distribution medium, is called an "aggregate" if the copyright resulting from the compilation is not used to limit the legal rights of the compilation's users beyond what the individual works permit. When the Document is included in an aggregate, this License does not apply to the other works in the aggregate which are not themselves derivative works of the Document.

If the Cover Text requirement of section 3 is applicable to these copies of the Document, then if the Document is less than one half of the entire aggregate, the Document's Cover Texts may be placed on covers that bracket the Document within the aggregate, or the electronic equivalent of covers if the Document is in electronic form. Otherwise they must appear on printed covers that bracket the whole aggregate.

### 8. TRANSLATION

Translation is considered a kind of modification, so you may distribute translations of the Document under the terms of section 4. Replacing Invariant Sections with translations requires special permission from their copyright holders, but you may include translations of some or all

Invariant Sections in addition to the original versions of these Invariant Sections. You may include a translation of this License, and all the license notices in the Document, and any Warranty Disclaimers, provided that you also include the original English version of this License and the original versions of those notices and disclaimers. In case of a disagreement between the translation and the original version of this License or a notice or disclaimer, the original version will prevail.

If a section in the Document is Entitled "Acknowledgements", "Dedications", or "History", the requirement (section 4) to Preserve its Title (section 1) will typically require changing the actual title.

### 9. TERMINATION

You may not copy, modify, sublicense, or distribute the Document except as expressly provided for under this License. Any other attempt to copy, modify, sublicense or distribute the Document is void, and will automatically terminate your rights under this License. However, parties who have received copies, or rights, from you under this License will not have their licenses terminated so long as such parties remain in full compliance.

### 10. FUTURE REVISIONS OF THIS LICENSE

(not as a draft) by the Free Software Foundation.

The Free Software Foundation may publish new, revised versions of the GNU Free Documentation License from time to time. Such new versions will be similar in spirit to the present version, but may differ in detail to address new problems or concerns. See <a href="http://www.gnu.org/copyleft/">http://www.gnu.org/copyleft/</a>. Each version of the License is given a distinguishing version number. If the Document specifies that a particular numbered version of this License "or any later version" applies to it, you have the option of following the terms and conditions either of that specified version or of any later version that has been published (not as a draft) by the Free Software Foundation. If the Document does not specify a version number of this License, you may choose any version ever published

## ADDENDUM: How to use this License for your documents

Copyright (c) YEAR YOUR NAME.

Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.2

or any later version published by the Free Software Foundation; with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts. A copy of the license is included in the section entitled "GNU Free Documentation License".

If you have Invariant Sections, Front-Cover Texts and Back-Cover Texts, replace the "with... Texts." line with this:

```
with the Invariant Sections being LIST THEIR TITLES, with the Front-Cover Texts being LIST, and with the Back-Cover Texts being LIST.
```

If you have Invariant Sections without Cover Texts, or some other combination of the three, merge those two alternatives to suit the situation.

If your document contains nontrivial examples of program code, we recommend releasing these examples in parallel under your choice of free software license, such as the GNU General Public License, to permit their use in free software.