

# Oracle WebLogic Server 12cR2 on SUSE Linux Enterprise Server 12 SP3

Installation Guide for x86-64 Architectures

SUSE Linux Enterprise Server 12 SP3  
Oracle Fusion Middleware 12c

Chen Wu, ISV Technical Manager (SUSE)  
Arun Singh, ISV Technical Manager (SUSE)

# Oracle WebLogic Server 12cR2 on SUSE Linux Enterprise Server 12 SP3

## Installation Guide for x86-64 Architectures

Oracle WebLogic Server 12c R2 is a reliable application server for building and deploying enterprise Java EE applications with support for new features for lowering cost of operations, improving performance, enhancing scalability and supporting the Oracle Applications portfolio. WebLogic Server Java EE applications are based on standardized, modular components. Oracle WebLogic Server provides a complete set of services for those modules and handles many details of application behavior automatically, without requiring programming.

SUSE Linux Enterprise Server provides Oracle customers a scalable platform for demanding workloads and applications. Oracle and SUSE have teamed up to enable Linux in enterprises and have created world-class solutions that offer real-grid benefits for IT data centers today. This document provides the details for installing Oracle WebLogic Server 12cR2 on SUSE Linux Enterprise Server 12 SP3.


**Disclaimer:** Documents published as part of the SUSE Best Practices series have been contributed voluntarily by SUSE employees and third parties. They are meant to serve as examples of how particular actions can be performed. They have been compiled with utmost attention to detail. However, this does not guarantee complete accuracy. SUSE cannot verify that actions described in these documents do what is claimed or whether actions described have unintended consequences. SUSE LLC, its affiliates, the authors, and the translators may not be held liable for possible errors or the consequences thereof.

# Contents

- 1 Introduction 4
- 2 System Requirements and Specifications 4
- 3 Prerequisites 5
- 4 Oracle WebLogic Server 12cR2 Installation 7
- 5 Additional Comments 23
- 6 Legal notice 24
- 7 GNU Free Documentation License 25

# 1 Introduction

This document provides the details for installing Oracle WebLogic Server 12cR2 on SUSE Linux Enterprise Server 12 SP2. Details are provided for the Intel x86-64 versions of both Oracle WebLogic Server 12cR2 and SUSE Linux Enterprise Server 12. Similar steps apply to other platforms or architectures (x86, ia64, IBM Z and LinuxOne, etc.). If you encounter issues or have general questions, post your query to [suse-oracle@listx.novell.com](mailto:suse-oracle@listx.novell.com).

The official Oracle product documentation is available at: <http://docs.oracle.com/en/> 

## 2 System Requirements and Specifications

The following paragraphs provide details about the hardware and software requirements that need to be met to install Oracle WebLogic Server 12cR2 on top of SUSE Linux Enterprise Server 12 SP3. They also contain the specification of the test environment.

### 2.1 Hardware Requirements

TABLE 1: **HARDWARE REQUIREMENTS**

Requirement	Minimum
CPU	1-GHz CPU
Physical Memory	4 GB
Swap space	Approximately twice the size of RAM
Disk space in /tmp	2 GB
Disk space for software files	2 GB



### 2.2 Software Requirements

SUSE:

- SUSE Linux Enterprise Server 12 SP3 (x86\_64)

<https://www.suse.com/download/sles/> 

#### Oracle:


- WebLogic Server 12cR2 (12.2.1.2.0) (fmw\_12.2.1.2.0\_wls\_Disk1\_1of1.zip)  
[http://  
www.oracle.com/technetwork/middleware/fusion-middleware/downloads/index.html](http://www.oracle.com/technetwork/middleware/fusion-middleware/downloads/index.html) 
- Java SE Development Kit 8 (jdk-8u112-linux-x64.tar.gz)  
<http://www.oracle.com/technetwork/indexes/downloads/index.html#java> 

## 2.3 Testing Machine information

- HP DL388 Gen9 Server
- CPU: 2 \* Intel(R) Xeon(R) CPU E5-2630 v3 @ 2.40GHz
- RAM: 64 GB
- NIC: 8
- Local HDD: 2 TB
- Operating System: SUSE Linux Enterprise Server 12 SP3 (x86\_64)
- Kernel version: 4.4.73-5-default

## 3 Prerequisites

### 3.1 Installing SUSE Linux Enterprise Server 12

Install SUSE Linux Enterprise Server 12 SP3+ on your testing machine. To do so, follow the instructions in the official SUSE Linux Enterprise Server documentation at <https://documentation.suse.com/sles/12-SP5/> 




FIGURE 1: INSTALLATION OF SUSE LINUX ENTERPRISE SERVER- 1

In YaST, select the patterns you need. Make sure you select the patterns and packages required to run Oracle products (for example **orarun**).




FIGURE 2: INSTALLATION OF SUSE LINUX ENTERPRISE SERVER- 2

After the installation of SUSE Linux Enterprise Server, the following information about the operating system and the kernel version is displayed:


```
oracle@hpgen9-02:~> more /etc/os-release
NAME="SLES"
VERSION="12-SP3"
VERSION_ID="12.3"
PRETTY_NAME="SUSE Linux Enterprise Server 12 SP3"
ID="sles"
ANSI_COLOR="0;32"
CPE_NAME="cpe:/o:suse:sles:12:sp3"
oracle@hpgen9-02:~> uname -a
Linux hpgen9-02 4.4.73-5-default #1 SMP Tue Jul 4 15:33:39 UTC 2017 (b7ce4e4) x86_64 x86_64 x86_64 GNU/Linux
oracle@hpgen9-02:~>
```

FIGURE 3: OPERATING SYSTEM AND KERNEL VERSION

## 3.2 Installing Java

Oracle WebLogic Server 12cR2 (12.2.1.2.0) requires JDK version 1.8. Log in to the target system (SUSE Linux Enterprise Server 12 SP3 64-bit operating system) as a non-administration user. Download the Java SE Development Kit 8 (jdk-8u112-linux-x64.tar.gz) from <http://www.oracle.com/technetwork/indexes/downloads/index.html#java>.

Set the environment variables `JAVA_HOME` and `PATH` to ensure the proper JDK version is installed and ready for use.

A screenshot of a terminal window titled 'oracle@hpgen9-02:~'. The terminal shows the following commands and output: 'export JAVA\_HOME=/home/oracle/ORACLE\_SW/Java/jdk1.8.0\_112/' followed by 'export PATH=\$JAVA\_HOME/bin:\$PATH', then 'java -version' which outputs 'java version "1.8.0\_112"', 'Java(TM) SE Runtime Environment (build 1.8.0\_112-b15)', and 'Java HotSpot(TM) 64-Bit Server VM (build 25.112-b15, mixed mode)'.

```
oracle@hpgen9-02:~> export JAVA_HOME=/home/oracle/ORACLE_SW/Java/jdk1.8.0_112/
oracle@hpgen9-02:~> export PATH=$JAVA_HOME/bin:$PATH
oracle@hpgen9-02:~> java -version
java version "1.8.0_112"
Java(TM) SE Runtime Environment (build 1.8.0_112-b15)
Java HotSpot(TM) 64-Bit Server VM (build 25.112-b15, mixed mode)
oracle@hpgen9-02:~>
```

FIGURE 4: JAVA INFORMATION

# 4 Oracle WebLogic Server 12cR2 Installation

The following sections explain how to perform your Oracle WebLogic Server 12cR2 installation.

## 4.1 Installing Oracle WebLogic Server Software

Log in to the target system (SUSE Linux Enterprise Server 12 SP3 64-bit operating system) as a non-administration user. Download the Oracle WebLogic Server 12cR2 (12.2.1.2.0) from the Oracle Web site.



## Note: Permissions

Ensure the installation user has the proper permissions to install and configure the software.

Go to the directory where you downloaded the installation program. Extract the contents of the .zip archive `fmw_12.2.1.2.0_wls_Disk1_1of1.zip`) and launch the installation program by running `java -jar fmw.xxxx.jar`.

For the actual installation, follow the steps below:

### 1. Go to **Installation Inventory Setup**.




FIGURE 5: **INSTALLATION INVENTORY SETUP**

If this is your first Oracle installation on a host that is running SUSE Linux Enterprise Server, use the *Oracle Fusion Middleware 12c Installation Inventory Setup* screen to specify the location of the Oracle Central Inventory Directory and Operating System Group Name. Click **OK** to continue.

### 2. Proceed to **Welcome**.






FIGURE 6: WELCOME

Review the information on this screen carefully to be sure you have performed all the necessary preparation steps. Click **Next** to continue.

### 3. Proceed to **Auto Updates**.




FIGURE 7: AUTO UPDATES

Select the option **Skip Auto Updates**", to skip this screen. Click **Next** to continue.

#### 4. Proceed to **Installation Location**.




FIGURE 8: INSTALLATION LOCATION

Type the full path of the directory into the Oracle Home field. Click **Next** to continue.

## 5. Proceed to **Installation Type**.




FIGURE 9: **INSTALLATION TYPE**

Use this screen to determine the type of installation you want to perform, then click **Next** to continue.

## 6. Proceed to **Prerequisite Checks**.




FIGURE 10: PREREQUISITE CHECKS

The **Prerequisite Checks** results will be shown as above. Click **Next** to continue.

## 7. Proceed to **Security Updates** .




FIGURE 11: SECURITY UPDATES

If you want to register your installation, enter your e-mail address and your **My Oracle Support** password.




FIGURE 12: SECURITY UPDATES - 2

If you want to decline registration, deselect **I wish to receive security updates via My Oracle Support** and confirm your choice.

## 8. Proceed to **Installation Summary** .



FIGURE 13: INSTALLATION SUMMARY

This screen contains a list of the feature sets you selected for your installation. It also contains the approximate amount of disk space to be used by the feature sets when the installation is complete. Check the information, then click **Install** to continue.

## 9. Proceed to **Installation Progress**.




FIGURE 14: INSTALLATION PROGRESS

This screen shows the progress of the installation. When the progress bar reaches 100 percent, the installation is complete. Click **Finish** to continue.

10. Proceed to **Installation Complete**.




FIGURE 15: INSTALLATION COMPLETE

This screen appears at the conclusion of the installation. Select the option **Automatically Launch the Configuration Wizard**, then click **Finish** to exit the installer.

## 4.2 Creating and Configuring the WebLogic Domain

To start the domain configuration, you can choose from two options:

1. From the last-shown screen **Installation Complete**, you can automatically launch the WebLogic Configuration Wizard through the option **Automatically Launch the Configuration Wizard**.
2. You can also navigate to the directory `ORACLE_HOME/oracle_common/common/bin` and start the WebLogic Server Configuration Wizard by running the command `./config.sh`.

To set up your configuration, follow the steps below:

1. Go to **Configuration Type**.




FIGURE 16: CONFIGURATION TYPE

Select the option **Create a New Domain** and specify the Domain home directory in the **Domain Location** field. Click **Next** to continue.

## 2. Proceed to **Templates**.




FIGURE 17: TEMPLATES



On the **Templates** screen select **Basic WebLogic Server Domain** which is pre-selected by default. In addition, select **WebLogic Coherence Cluster Extension** for the configuration. Click **Next** to continue.

3. Proceed to **Administrator Account**.


The screenshot shows the 'Administrator Account' configuration screen in the Fusion Middleware Configuration Wizard. The window title is 'Fusion Middleware Configuration Wizard - Page 3 of 8'. On the left, a navigation pane lists the steps: 'Create Domain', 'Templates', 'Administrator Account' (which is highlighted), 'Domain Mode and JDK', 'Advanced Configuration', 'Configuration Summary', 'Configuration Progress', and 'End Of Configuration'. The main area contains three input fields: 'Name' with the value 'weblogic', 'Password' with masked characters, and 'Confirm Password' with masked characters. Below these fields is a note: 'Must be the same as the password. Password must contain at least 8 alphanumeric characters with at least one number or special character.' At the bottom, there are buttons for 'Help', '< Back', 'Next >', 'Finish', and 'Cancel'.

FIGURE 18: ADMINISTRATOR ACCOUNT

Specify the user name and password for the default WebLogic Administrator account for the domain. Click **Next** to continue.

4. Proceed to **Domain Mode and JDK**.




FIGURE 19: DOMAIN MODE AND JDK

Select **Development** in the Domain Mode field and **Oracle HotSpot** in the JDK field. Click **Next** to continue.

## 5. Proceed to Advanced Configuration.



FIGURE 20: ADVANCED CONFIGURATION

According to your requirements, select the desired options on the **Advanced Configuration** screen. Click **Next** to continue.

6. Proceed to **Configuration Summary**.




FIGURE 21: CONFIGURATION SUMMARY

Review the information on the **Configuration Summary** screen to verify everything is correct. Click **Create** to continue.

7. Proceed to **Configuration Progress**.




FIGURE 22: CONFIGURATION PROGRESS

The **Configuration Progress** screen shows the progress of your configuration. For different progress states, different messages are displayed. When you see the message **Domain Created successfully**", click **Next** to continue.

## 8. Proceed to End Of Configuration.





FIGURE 23: END OF CONFIGURATION

When you see the message **Oracle WebLogic Server Configuration Succeeded**, record the **Domain Location** and **Admin Server URL**. Click **Finish** to exit the Configuration Wizard.

### 4.3 Starting the Administration Server and Verifying the Configuration

To start the Administration Server through a terminal, go to the `DOMAIN_HOME/bin` directory and run the command `./startWebLogic.sh`.



```
oracle@hpugen9-02:/home/oracle/Oracle/Middleware/Oracle_Home/user_projects/domains/base_domain/bin
File Edit View Search Terminal Tabs Help
oracle@hpugen9-02:/ho... x oracle@hpugen9-02:/ho... x oracle@hpugen9-02:~ x oracle@hpugen9-02:~ x
<Aug 2, 2017, 5:59:23,877 PM GMT+08:00> <Notice> <WebLogicServer> <BEA-000365> <Server state changed to STANDBY.>
<Aug 2, 2017, 5:59:23,877 PM GMT+08:00> <Notice> <WebLogicServer> <BEA-000365> <Server state changed to STARTING>
<Aug 2, 2017, 5:59:23,925 PM GMT+08:00> <Notice> <Log Management> <BEA-170036> <The Logging monitoring service t
imer has started to check for logged message counts every 30 seconds.>
<Aug 2, 2017, 5:59:24,273 PM GMT+08:00> <Notice> <Log Management> <BEA-170027> <The server has successfully esta
blished a connection with the Domain Level Diagnostic Service.>
<Aug 2, 2017, 5:59:27,946 PM GMT+08:00> <Notice> <WebLogicServer> <BEA-000365> <Server state changed to ADMIN.>
<Aug 2, 2017, 5:59:28,1 PM GMT+08:00> <Notice> <WebLogicServer> <BEA-000365> <Server state changed to RESUMING.>
<Aug 2, 2017, 5:59:28,58 PM GMT+08:00> <Warning> <Server> <BEA-002611> <The hostname "localhost", maps to multip
le IP addresses: 127.0.0.1, 0:0:0:0:0:0:0:1.>
<Aug 2, 2017, 5:59:28,60 PM GMT+08:00> <Notice> <Server> <BEA-002613> <Channel "Default[2]" is now listening on
127.0.0.1:7001 for protocols iiop, t3, ldap, snmp, http.>
<Aug 2, 2017, 5:59:28,61 PM GMT+08:00> <Notice> <WebLogicServer> <BEA-000331> <Started the WebLogic Server Admin
istration Server "AdminServer" for domain "base_domain" running in development mode.>
<Aug 2, 2017, 5:59:28,61 PM GMT+08:00> <Notice> <Server> <BEA-002613> <Channel "Default[1]" is now listening on
0:0:0:0:0:0:0:1%lo:7001 for protocols iiop, t3, ldap, snmp, http.>
<Aug 2, 2017, 5:59:28,61 PM GMT+08:00> <Notice> <Server> <BEA-002613> <Channel "Default" is now listening on 192
.168.1.191:7001 for protocols iiop, t3, ldap, snmp, http.>
<Aug 2, 2017, 5:59:28,62 PM GMT+08:00> <Notice> <Server> <BEA-002613> <Channel "Default[2]" is now listening on
127.0.0.1:7001 for protocols iiop, t3, ldap, snmp, http.>
<Aug 2, 2017, 5:59:28,62 PM GMT+08:00> <Notice> <Server> <BEA-002613> <Channel "Default[1]" is now listening on
0:0:0:0:0:0:0:1%lo:7001 for protocols iiop, t3, ldap, snmp, http.>
<Aug 2, 2017, 5:59:28,63 PM GMT+08:00> <Notice> <WebLogicServer> <BEA-000360> <The server started in RUNNING mod
e.>
<Aug 2, 2017, 5:59:28,63 PM GMT+08:00> <Notice> <Server> <BEA-002613> <Channel "Default" is now listening on 192
.168.1.191:7001 for protocols iiop, t3, ldap, snmp, http.>
<Aug 2, 2017, 5:59:28,73 PM GMT+08:00> <Notice> <WebLogicServer> <BEA-000365> <Server state changed to RUNNING.>
```

FIGURE 24: STARTING THE ADMINISTRATION SERVER

Review the information displayed on the screen.

Access the Oracle WebLogic Server Administration Console.




FIGURE 25: ORACLE WEBLOGIC SERVER ADMINISTRATION CONSOLE

Fill in your user name and password. You are then proceeded to the **WebLogic Server 12cR2 Administration Console** home page.




FIGURE 26: ORACLE WEBLOGIC SERVER ADMINISTRATION CONSOLE HOME PAGE

The installation and configuration of your Oracle WebLogic Server 12cR2 is now successfully finished.


## 5 Additional Comments

This document shows how to create a standard installation topology for Oracle WebLogic Server. You can extend this topology to make it highly available and secure so that it is suitable for a production system.

## 6 Legal notice

Copyright ©2006-2025 SUSE LLC and contributors. All rights reserved.

Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.2 or (at your option) version 1.3; with the Invariant Section being this copyright notice and license. A copy of the license version 1.2 is included in the section entitled “GNU Free Documentation License”.

SUSE, the SUSE logo and YaST are registered trademarks of SUSE LLC in the United States and other countries. For SUSE trademarks, see <http://www.suse.com/company/legal/> . Linux is a registered trademark of Linus Torvalds. All other names or trademarks mentioned in this document may be trademarks or registered trademarks of their respective owners.

Documents published as part of the **SUSE Best Practices** series have been contributed voluntarily by SUSE employees and third parties. They are meant to serve as examples of how particular actions can be performed. They have been compiled with utmost attention to detail. However, this does not guarantee complete accuracy. SUSE cannot verify that actions described in these documents do what is claimed or whether actions described have unintended consequences. SUSE LLC, its affiliates, the authors, and the translators may not be held liable for possible errors or the consequences thereof.

Below we draw your attention to the license under which the articles are published.



# GNU Free Documentation License

Copyright (C) 2000, 2001, 2002 Free Software Foundation, Inc. 51 Franklin St, Fifth Floor, Boston, MA 02110-1301 USA. Everyone is permitted to copy and distribute verbatim copies of this license document, but changing it is not allowed.

## 0. PREAMBLE

The purpose of this License is to make a manual, textbook, or other functional and useful document "free" in the sense of freedom: to assure everyone the effective freedom to copy and redistribute it, with or without modifying it, either commercially or non-commercially. Secondly, this License preserves for the author and publisher a way to get credit for their work, while not being considered responsible for modifications made by others.

This License is a kind of "copyleft", which means that derivative works of the document must themselves be free in the same sense. It complements the GNU General Public License, which is a copyleft license designed for free software.

We have designed this License to use it for manuals for free software, because free software needs free documentation: a free program should come with manuals providing the same freedoms that the software does. But this License is not limited to software manuals; it can be used for any textual work, regardless of subject matter or whether it is published as a printed book. We recommend this License principally for works whose purpose is instruction or reference.

## 1. APPLICABILITY AND DEFINITIONS

This License applies to any manual or other work, in any medium, that contains a notice placed by the copyright holder saying it can be distributed under the terms of this License. Such a notice grants a world-wide, royalty-free license, unlimited in duration, to use that work under the conditions stated herein. The "Document", below, refers to any such manual or work. Any member of the public is a licensee, and is addressed as "you". You accept the license if you copy, modify or distribute the work in a way requiring permission under copyright law.

A "Modified Version" of the Document means any work containing the Document or a portion of it, either copied verbatim, or with modifications and/or translated into another language.

A "Secondary Section" is a named appendix or a front-matter section of the Document that deals exclusively with the relationship of the publishers or authors of the Document to the Document's overall subject (or to related matters) and contains nothing that could fall directly within that overall subject. (Thus, if the Document is in part a textbook of mathematics, a Secondary Section may not explain any mathematics.) The relationship could be a matter of historical connection with the subject or with related matters, or of legal, commercial, philosophical, ethical or political position regarding them.

The "Invariant Sections" are certain Secondary Sections whose titles are designated, as being those of Invariant Sections, in the notice that says that the Document is released under this License. If a section does not fit the above definition of Secondary then it is not allowed to be designated as Invariant. The Document may contain zero Invariant Sections. If the Document does not identify any Invariant Sections then there are none.

The "Cover Texts" are certain short passages of text that are listed, as Front-Cover Texts or Back-Cover Texts, in the notice that says that the Document is released under this License. A Front-Cover Text may be at most 5 words, and a Back-Cover Text may be at most 25 words.

A "Transparent" copy of the Document means a machine-readable copy, represented in a format whose specification is available to the general public, that is suitable for revising the document straightforwardly with generic text editors or (for images composed of pixels) generic paint programs or (for drawings) some widely available drawing editor, and that is suitable for input to text formatters or for automatic translation to a variety of formats suitable for input to text formatters. A copy made in an otherwise Transparent file format whose markup, or absence of markup, has been arranged to thwart or discourage subsequent modification by readers is not Transparent. An image format is not Transparent if used for any substantial amount of text. A copy that is not "Transparent" is called "Opaque".

Examples of suitable formats for Transparent copies include plain ASCII without markup, Texinfo input format, LaTeX input format, SGML or XML using a publicly available DTD, and standard-conforming simple HTML, PostScript or PDF designed for human modification. Examples of transparent image formats include PNG, XCF and JPG. Opaque formats include proprietary formats that can be read and edited only by proprietary word processors, SGML or XML for which the DTD and/or processing tools are not generally available, and the machine-generated HTML, PostScript or PDF produced by some word processors for output purposes only.

The "Title Page" means, for a printed book, the title page itself, plus such following pages as are needed to hold, legibly, the material this License requires to appear in the title page. For works in formats which do not have any title page as such, "Title Page" means the text near the most prominent appearance of the work's title, preceding the beginning of the body of the text.

A section "Entitled XYZ" means a named subunit of the Document whose title either is precisely XYZ or contains XYZ in parentheses following text that translates XYZ in another language. (Here XYZ stands for a specific section name mentioned below, such as "Acknowledgements", "Dedications", "Endorsements", or "History".) To "Preserve the Title" of such a section when you modify the Document means that it remains a section "Entitled XYZ" according to this definition.

The Document may include Warranty Disclaimers next to the notice which states that this License applies to the Document. These Warranty Disclaimers are considered to be included by reference in this License, but only as regards disclaiming warranties: any other implication that these Warranty Disclaimers may have is void and has no effect on the meaning of this License.

## 2. VERBATIM COPYING

You may copy and distribute the Document in any medium, either commercially or noncommercially, provided that this License, the copyright notices, and the license notice saying this License applies to the Document are reproduced in all copies, and that you add no other conditions whatsoever to those of this License. You may not use technical measures to obstruct or control the reading or further copying of the copies you make or distribute. However, you may accept compensation in exchange for copies. If you distribute a large enough number of copies you must also follow the conditions in section 3.

You may also lend copies, under the same conditions stated above, and you may publicly display copies.

## 3. COPYING IN QUANTITY

If you publish printed copies (or copies in media that commonly have printed covers) of the Document, numbering more than 100, and the Document's license notice requires Cover Texts, you must enclose the copies in covers that carry, clearly and legibly, all these Cover Texts: Front-Cover Texts on the front cover, and Back-Cover Texts on the back cover. Both covers must also clearly and legibly identify you as the publisher of these copies. The front cover must present the full title with all words of the title equally prominent and visible. You may add other material on the covers in addition. Copying with changes limited to the covers, as long as they preserve the title of the Document and satisfy these conditions, can be treated as verbatim copying in other respects. If the required texts for either cover are too voluminous to fit legibly, you should put the first ones listed (as many as fit reasonably) on the actual cover, and continue the rest onto adjacent pages.

If you publish or distribute Opaque copies of the Document numbering more than 100, you must either include a machine-readable Transparent copy along with each Opaque copy, or state in or with each Opaque copy a computer-network location from which the general network-using public has access to download using public-standard network protocols a complete Transparent copy of the Document, free of added material. If you use the latter option, you must take reasonably prudent steps, when you begin distribution of Opaque copies in quantity, to ensure that this Transparent copy will remain thus accessible at the stated location until at least one year after the last time you distribute an Opaque copy (directly or through your agents or retailers) of that edition to the public.

It is requested, but not required, that you contact the authors of the Document well before redistributing any large number of copies, to give them a chance to provide you with an updated version of the Document.

#### 4. MODIFICATIONS

You may copy and distribute a Modified Version of the Document under the conditions of sections 2 and 3 above, provided that you release the Modified Version under precisely this License, with the Modified Version filling the role of the Document, thus licensing distribution and modification of the Modified Version to whoever possesses a copy of it. In addition, you must do these things in the Modified Version:

- A. Use in the Title Page (and on the covers, if any) a title distinct from that of the Document, and from those of previous versions (which should, if there were any, be listed in the History section of the Document). You may use the same title as a previous version if the original publisher of that version gives permission.
- B. List on the Title Page, as authors, one or more persons or entities responsible for authorship of the modifications in the Modified Version, together with at least five of the principal authors of the Document (all of its principal authors, if it has fewer than five), unless they release you from this requirement.
- C. State on the Title page the name of the publisher of the Modified Version, as the publisher.
- D. Preserve all the copyright notices of the Document.
- E. Add an appropriate copyright notice for your modifications adjacent to the other copyright notices.
- F. Include, immediately after the copyright notices, a license notice giving the public permission to use the Modified Version under the terms of this License, in the form shown in the Addendum below.
- G. Preserve in that license notice the full lists of Invariant Sections and required Cover Texts given in the Document's license notice.
- H. Include an unaltered copy of this License.
- I. Preserve the section Entitled "History", Preserve its Title, and add to it an item stating at least the title, year, new authors, and publisher of the Modified Version as given on the Title Page. If there is no section Entitled "History" in the Document, create one stating the title, year, authors, and publisher of the Document as given on its Title Page, then add an item describing the Modified Version as stated in the previous sentence.
- J. Preserve the network location, if any, given in the Document for public access to a Transparent copy of the Document, and likewise the network locations given in the Document for previous versions it was based on. These may be placed in the "History" section. You may omit a network location for a work that was published at least four years before the Document itself, or if the original publisher of the version it refers to gives permission.
- K. For any section Entitled "Acknowledgements" or "Dedications", Preserve the Title of the section, and preserve in the section all the substance and tone of each of the contributor acknowledgements and/or dedications given therein.
- L. Preserve all the Invariant Sections of the Document, unaltered in their text and in their titles. Section numbers or the equivalent are not considered part of the section titles.
- M. Delete any section Entitled "Endorsements". Such a section may not be included in the Modified Version.
- N. Do not retitle any existing section to be Entitled "Endorsements" or to conflict in title with any Invariant Section.
- O. Preserve any Warranty Disclaimers.

If the Modified Version includes new front-matter sections or appendices that qualify as Secondary Sections and contain no material copied from the Document, you may at your option designate some or all of these sections as invariant. To do this, add their titles to the list of Invariant Sections in the Modified Version's license notice. These titles must be distinct from any other section titles.

You may add a section Entitled "Endorsements", provided it contains nothing but endorsements of your Modified Version by various parties--for example, statements of peer review or that the text has been approved by an organization as the authoritative definition of a standard.

You may add a passage of up to five words as a Front-Cover Text, and a passage of up to 25 words as a Back-Cover Text, to the end of the list of Cover Texts in the Modified Version. Only one passage of Front-Cover Text and one of Back-Cover Text may be added by (or through arrangements made by) any one entity. If the Document already includes a cover text for the same cover, previously added by you or by arrangement made by the same entity you are acting on behalf of, you may not add another; but you may replace the old one, on explicit permission from the previous publisher that added the old one.

The author(s) and publisher(s) of the Document do not by this License give permission to use their names for publicity for or to assert or imply endorsement of any Modified Version.

#### 5. COMBINING DOCUMENTS

You may combine the Document with other documents released under this License, under the terms defined in section 4 above for modified versions, provided that you include in the combination all of the Invariant Sections of all of the original documents, unmodified, and list them all as Invariant Sections of your combined work in its license notice, and that you preserve all their Warranty Disclaimers.

The combined work need only contain one copy of this License, and multiple identical Invariant Sections may be replaced with a single copy. If there are multiple Invariant Sections with the same name but different contents, make the title of each such section unique by adding at the end of it, in parentheses, the name of the original author or publisher of that section if known, or else a unique number. Make the same adjustment to the section titles in the list of Invariant Sections in the license notice of the combined work.

In the combination, you must combine any sections Entitled "History" in the various original documents, forming one section Entitled "History"; likewise combine any sections Entitled "Acknowledgements", and any sections Entitled "Dedications". You must delete all sections Entitled "Endorsements".

#### 6. COLLECTIONS OF DOCUMENTS

You may make a collection consisting of the Document and other documents released under this License, and replace the individual copies of this License in the various documents with a single copy that is included in the collection, provided that you follow the rules of this License for verbatim copying of each of the documents in all other respects.

You may extract a single document from such a collection, and distribute it individually under this License, provided you insert a copy of this License into the extracted document, and follow this License in all other respects regarding verbatim copying of that document.

#### 7. AGGREGATION WITH INDEPENDENT WORKS

A compilation of the Document or its derivatives with other separate and independent documents or works, in or on a volume of a storage or distribution medium, is called an "aggregate" if the copyright resulting from the compilation is not used to limit the legal rights of the compilation's users beyond what the individual works permit. When the Document is included in an aggregate, this License does not apply to the other works in the aggregate which are not themselves derivative works of the Document.

If the Cover Text requirement of section 3 is applicable to these copies of the Document, then if the Document is less than one half of the entire aggregate, the Document's Cover Texts may be placed on covers that bracket the Document within the aggregate, or the electronic equivalent of covers if the Document is in electronic form. Otherwise they must appear on printed covers that bracket the whole aggregate.

## 8. TRANSLATION

Translation is considered a kind of modification, so you may distribute translations of the Document under the terms of section 4. Replacing Invariant Sections with translations requires special permission from their copyright holders, but you may include translations of some or all Invariant Sections in addition to the original versions of these Invariant Sections. You may include a translation of this License, and all the license notices in the Document, and any Warranty Disclaimers, provided that you also include the original English version of this License and the original versions of those notices and disclaimers. In case of a disagreement between the translation and the original version of this License or a notice or disclaimer, the original version will prevail.

If a section in the Document is Entitled "Acknowledgements", "Dedications", or "History", the requirement (section 4) to Preserve its Title (section 1) will typically require changing the actual title.

## 9. TERMINATION

You may not copy, modify, sublicense, or distribute the Document except as expressly provided for under this License. Any other attempt to copy, modify, sublicense or distribute the Document is void, and will automatically terminate your rights under this License. However, parties who have received copies, or rights, from you under this License will not have their licenses terminated so long as such parties remain in full compliance.

## 10. FUTURE REVISIONS OF THIS LICENSE

The Free Software Foundation may publish new, revised versions of the GNU Free Documentation License from time to time. Such new versions will be similar in spirit to the present version, but may differ in detail to address new problems or concerns. See <http://www.gnu.org/copyleft/>.

Each version of the License is given a distinguishing version number. If the Document specifies that a particular numbered version of this License "or any later version" applies to it, you have the option of following the terms and conditions either of that specified version or of any later version that has been published (not as a draft) by the Free Software Foundation. If the Document does not specify a version number of this License, you may choose any version ever published (not as a draft) by the Free Software Foundation.

## ADDENDUM: How to use this License for your documents

```
Copyright (c) YEAR YOUR NAME.
Permission is granted to copy, distribute and/or modify this document
under the terms of the GNU Free Documentation License, Version 1.2
or any later version published by the Free Software Foundation;
with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts.
A copy of the license is included in the section entitled "GNU
Free Documentation License".
```

If you have Invariant Sections, Front-Cover Texts and Back-Cover Texts, replace the "with...Texts". line with this:

```
with the Invariant Sections being LIST THEIR TITLES, with the
Front-Cover Texts being LIST, and with the Back-Cover Texts being LIST.
```

If you have Invariant Sections without Cover Texts, or some other combination of the three, merge those two alternatives to suit the situation.

If your document contains nontrivial examples of program code, we recommend releasing these examples in parallel under your choice of free software license, such as the GNU General Public License, to permit their use in free software.